THE MARKER

COMPLETE ILLUSTRATED USER GUIDE

Your hole-by-hole golf companion

Use with The Scorecard, or independently without a Scorecard account. Keep scores for one to four golfers.

ONE AT A TIME

Alex 4 / Sam 5

ALL FOUR TOGETHER

Large-print edition | October 17, 2026 | Web app 0.5.4

Based on the current Cuberoot website instructions. Screen illustrations are teaching reconstructions, not account screenshots.

CONTENTS

1. Choose how to play

2. Sign in and recover access

3. Set up the round

4. Find and check a course

5. Enter a course yourself

6. Read the club card from a photo

7. Confirm the photo reading

8. Choose one to four players

9. Attach an available game

10. Enter scores, one golfer at a time

11. Enter all players together

12. Review and correct before posting

13. Understand the totals

14. Post eligible rounds to Scorecard

15. Confirm the posting result

16. Share a card

17. Resume, keep and delete cards


18. When something goes wrong

19. The Menu bubble during play

1. Choose how to play

The Marker is a companion to The Scorecard and a complete standalone scorecard for one to four players.

ILLUSTRATED SCREEN EXAMPLE



Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Choose Sign in with The Scorecard to use your existing account and pick golfers from your groups. Eligible finished rounds can be posted for those golfers.
2. Choose Play without an account to type player names, keep the card on this device and share it. No Scorecard account is required.
3. Continue your round appears when a round is already saved. Open the web app while connected before leaving for the course.

2. Sign in and recover access

Use the same email address and password as The Scorecard.

ILLUSTRATED SCREEN EXAMPLE

1 **Email**

2 **Password**

3 **Sign in**

4 **Forgot the password? Send a reset email**

Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Enter your Scorecard email and password, then tap Sign in. On the start screen, tap Start a new round.
2. For a forgotten password, enter your email and tap Forgot the password? Send a reset email. Follow the email to reset your shared Scorecard password.
3. Signing in needs an internet connection. If you have no account, return and choose Play without an account. Account and group setup are handled in The Scorecard.

3. Set up the round

Check these choices before you tee off.

ILLUSTRATED SCREEN EXAMPLE

1. **Date: 17 Oct 2026**
2. **Choose a course**
3. **White - 70.0 / 113 - par 72**
4. **18 holes / Front 9 / Back 9**
5. **Starting hole: 1**
6. **One golfer at a time / All four together**

Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Use the date minus and plus buttons to select the day played. Choose the course and the tee actually used.
2. Choose 18 holes, Front 9 or Back 9. A nine-hole card can

be shared but cannot be posted to The Scorecard.

3. Set the Starting hole for a shotgun start. An 18-hole round starting on 10 goes through 18, then 1 through 9.

4. Choose your score-entry layout. The selected course and tee apply to everyone on this card; use separate cards for different tees.

4. Find and check a course

Check the course data against the club's current scorecard.

ILLUSTRATED SCREEN EXAMPLE

1. **Course or club name**
2. **Show saved / Search online**
3. **Saved courses: Sample Links**
4. **Enter a course yourself**
5. **Check the holes**

Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Tap Choose a course. Enter a name and choose Show saved or Search online. Select the right club and tee.
2. Back in setup, tap Check the holes (par, yards, handicap) when available. Compare the hole details with the club's card.

3. If details are missing or wrong, use the correction option or Enter a course yourself. Online search needs a connection; previously saved courses are available locally.

4. Withdrawn course details cannot be used. Follow the message to find corrected data or enter the current club card. Course administration belongs in The Scorecard.

5. Enter a course yourself

Manual entry is available even when you cannot read a photo.

ILLUSTRATED SCREEN EXAMPLE

1 **Course name: Sample Links**

2 **Tee: White**

3 **Rating: 70.0 / Slope: 113**

4 **Hole 1 - Par 4 - Yards 360 - HCP 7**

5 **Use this course**

Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Choose Enter a course yourself. Type the course name and tee. Copy rating and slope from the club card if you intend to post.
2. Check every hole's par: the form starts with par 4, so change it where needed. Yards are optional.


3. Enter each HCP / Handicap / S.I. number exactly as printed. Use each number from 1 to 18 once, or leave all blank. Missing HCP makes stroke allocation approximate.

4. Tap Use this course. Manually entered data can be used for eligible Scorecard rounds; a photo or provider verification is not required.

6. Read the club card from a photo

This reads course details, not the players' handwritten scores.

ILLUSTRATED SCREEN EXAMPLE



Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Open Enter a course yourself. Type the course name and use a photo button. Lay the club card flat in good light.
2. Include all 18 holes, every tee, ratings, slopes, par, handicap numbers and printed totals. Avoid glare and cut-off edges.
3. Wait for the reading spinner. If asked, take a closer picture of the missing or unclear half.

4. Photo reading needs internet and an available daily allowance. Check the displayed pictures-left message. If unavailable, enter the details by hand.

7. Confirm the photo reading

A green check means the app's checks passed. You must still compare the values with the printed card.

ILLUSTRATED SCREEN EXAMPLE

1. **Check against the card**
2. **White tee Saved - OUT / IN totals**
3. **Par Saved - Handicap Saved**
4. **Red marks? Retake or correct**
5. **Saved This matches the card**

Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Review both nines and every tee, not just the tee you will play. Check rating, slope, yards, par, handicap numbers and totals.
2. Red marks indicate missing or problematic values. Retake the requested part, or choose Correct it by hand instead

and select a tee.


3. Read any warning about the printed card's own totals. Confirm only when the displayed data matches the card.

4. Tap This matches the card when available. Signed-in, verified data becomes shared course data; without an account it is saved on this device. Then choose your tee.

8. Choose one to four players

Group golfers can be posted; typed guests are scored and shared only.

ILLUSTRATED SCREEN EXAMPLE



Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Tap Choose the players. Signed-in users select a group and tap existing golfers. You may select golfers from your own groups, up to four total.
2. Add other people by typing a name and tapping Add. Without an account, enter each player this way. Typed


names are guests, even if they resemble a member's name.

3. Tap a selected member again to deselect; use Remove for a typed player. Check the names, then tap Tee off on hole ....

9. Attach an available game

Game selection is optional and appears during setup for signed-in users when games are available.

ILLUSTRATED SCREEN EXAMPLE



Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Set the correct date first. Under Part of a game, choose the appropriate listed game or leave Not part of a game selected.
2. Only available games covering that date are listed. Group access affects which games you can see.
3. For a card containing golfers from different groups, the game attaches only to rounds in the game's group. Create and manage games in The Scorecard.

10. Enter scores, one golfer at a time

Enter the strokes actually taken. The app calculates its handicap adjustment separately.

ILLUSTRATED SCREEN EXAMPLE

1. **Hole 1 - Par 4 - Saved Saved**
2. **Alex / Sam**
3. **Alex Green**
4. **4 - Par / 5 - Bogey / 6 - Double**
5. **Type a score / Picked up**
6. **Back / Card / Hole 2 ->**
7. **Example: tap Alex -> tap 4 (Par) -> tap Sam -> tap 5 (Bogey)**

Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.


HOW TO USE IT

1. Tap the golfer's name, then tap their score tile. The entered value is highlighted. Tap another value to correct it.
2. Tap the next golfer's name and enter that score. Use Type a score for a whole number from 1 to 20.
3. Use Picked up when the player did not finish the hole. This records X; it is not a zero.
4. When everyone has an entry, tap the next-hole button. After the final hole, tap Finish. Watch for save errors before continuing.

11. Enter all players together

Switch layouts at any time without losing scores.

ILLUSTRATED SCREEN EXAMPLE



Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Choose All four together in setup, or use Menu to switch during play. It also works with fewer than four players.
2. Tap + on an empty score to start at par. Then use minus or plus, or tap the score field and type a whole number from 1 to 20.


3. Type X for picked up. If your keyboard does not offer X, switch to one-golfer mode and tap Picked up.

4. Enter a score for everyone, then advance. Blank fields remain unfinished; they do not count as par.

12. Review and correct before posting

The whole card lets you return to a particular hole.

ILLUSTRATED SCREEN EXAMPLE



Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Tap Card while playing, or Review card on the finish screen. Scroll the card if needed to see every hole.
2. Tap the hole you want to change. Select the golfer and enter the correct score.


3. Continue through the round and return to Finish. Check the totals before posting. A saved historical card is a viewing screen; make corrections while the round is active.

4. After posting, changes to official rounds belong in The Scorecard with the appropriate access. The Marker does not provide a posted-round editor.

13. Understand the totals

Illustrative 18-hole example: gross 90, adjusted 88 and course handicap 10.

ILLUSTRATED SCREEN EXAMPLE



Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Gross adds entered strokes. For an X, the app substitutes that hole's handicap limit, so it is not a count of strokes actually finished on that hole.
2. Adjusted caps high hole scores at the app's handicap limit: normally par + 2 + strokes received. With no known course handicap, the app uses par + 5.
3. Net is gross minus course handicap when the round is

complete and a handicap is available. Do not use a nine-hole net display as a posted 18-hole result.

4. E means even with par. + and - show over and under par. Stroke notes depend on the selected tee, the player's index and hole handicap data.

14. Post eligible rounds to Scorecard

Posting and sharing are different actions.

ILLUSTRATED SCREEN EXAMPLE

1. **Round finished**
2. **Alex Green - Weekend Golfers**
3. **Sam Reed - Guest - shared only**
4. **Post 1 round to The Scorecard**
5. **Share the card / Review card**

Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Check all totals. Tap Post ... rounds to The Scorecard when shown. The number counts eligible group golfers, not guests.
2. Posting requires a signed-in card, at least one selected group golfer, 18 holes, rating and slope, and a score on every required hole. The server checks the submission

too.

3. Nine-hole cards, standalone cards and typed guests are kept and shared instead. Read the reason if no Post button is available.

4. A standalone card does not become postable just by signing in later. Start in signed-in mode and select the actual group golfers when posting is your goal.

15. Confirm the posting result

Do not treat Waiting or Checking as a successful post.

ILLUSTRATED SCREEN EXAMPLE

1 **Saved on this phone -> Waiting**

2 **Sent to The Scorecard -> Checking**

3 **Posted to The Scorecard -> Posted Saved**

4 **Not posted -> Read the reason**

Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Waiting means the card is saved locally for sending. Reopen The Marker on the same browser, sign in to the original account if needed and leave it open with a connection.
2. Checking means the submission reached the service and is being processed. Allow a few minutes and check again.
3. Posted Saved confirms acceptance. Open The Scorecard to verify the rounds. The service recalculates the

posting data, so its final values are authoritative.

4. For Not posted, read the reason and keep or share the card. Do not re-enter the same rounds while the original submission is still waiting or being checked.

16. Share a card

Share during play, after finishing or from Your cards.

ILLUSTRATED SCREEN EXAMPLE

1 **Share the card**

2 **WhatsApp**

3 **Email / Text message**

4 **Copy**

Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT


1. Tap Share the card. Your device may show its native share sheet; otherwise choose WhatsApp, Email, Text message or Copy.
2. Choose the recipients in your messaging app and send when ready. Sharing sends a text summary with hole scores; it does not post rounds to The Scorecard.
3. If Copy is blocked, press and hold the displayed text and copy it manually. An unfinished card can also be shared;

missing holes appear as dashes.

17. Resume, keep and delete cards

Local cards belong to this device and browser.

ILLUSTRATED SCREEN EXAMPLE



Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Return to the start screen through Menu. Use Continue your round to resume. To stop permanently without posting, choose End this round without posting and confirm.
2. Your cards holds the most recent 30 saved cards. Open one to view its scorecard, totals and posting status, or

share it.

3. Delete this card is available only when allowed. Deletion is permanent; posted cards and cards being checked cannot be deleted here.

4. Clearing browser data or changing devices does not carry local cards across. Share important cards before clearing data or exceeding the history limit.

18. When something goes wrong

Keep the card and resolve the displayed message first.

ILLUSTRATED SCREEN EXAMPLE

1. **No signal: continue the loaded round**
2. **Score NOT saved: stop and resolve**
3. **No course result: enter by hand**
4. **Photo unavailable: use manual entry**
5. **Posting delayed: reopen online**

Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. No signal: a loaded round can save scores locally. Search, sign-in, photo reading and posting need internet. This web release does not guarantee a fresh offline launch; keep the loaded page available.
2. Save error: do not assume the latest score was kept. Check browser storage, avoid private browsing and retry.

Share a copy before clearing anything.

3. Missing golfer: check the group and connection. A typed guest cannot be posted as that group golfer. Manage membership in The Scorecard.

4. Photo or posting problem: read the message, use manual course entry when needed, and check posting status online. For help, use Support on the app's start screen.

19. The Menu bubble during play

The Menu control appears at the top of the hole screen beside the saved indicator. Tap it without leaving your round.

ILLUSTRATED SCREEN EXAMPLE

1. **Switch to all four together / one golfer at a time**
2. **See the whole card**
3. **Share the card**
4. **Go to the start screen**
5. **End this round without posting**
6. **Back to hole 1 ->**

Teaching diagram using fictional example names and scores. Each numbered box represents an on-screen control or group of controls.

HOW TO USE IT

1. Tap Menu at the top right while entering scores.
2. Choose Switch to change the score-entry view. Your

entered scores stay saved.

3. See the whole card lets you review holes; Share the card sends a score summary.
4. Go to the start screen keeps the active round for Continue your round. End this round without posting is different: it ends the round and keeps a historical card without posting.
5. Tap Back to hole to continue scoring without changing anything.