CHAPTER 5

OPENING SCREEN HELP MENU

Use the commands on the Opening Screen Help menu to get onscreen help for WordStar commands and options, and to change the way WordStar displays menus and prompts.



HELP

Pull-down: ***ALT + H, H***
Classic: ***F1***

Displays help for the current command.

You can get onscreen help for every WordStar command and for each option in a dialog box.

If you are using pull-down menus, when you choose Help from the Help menu, you get an overview of WordStar help. To get help for a specific command, highlight it on the menu and press F1. To get help in a dialog box, press F1.

If you are using classic menus, press F1 at the Opening Menu or at the editing screen, and then press the command you want help with. To get help in a dialog box, press F1.

CHANGE HELP LEVEL

Pull-down: ***ALT + H, C***
Classic: ***F1 F1***

Changes which menus and prompts are displayed.

Once you're an experienced WordStar user, you might want to display classic menus instead of pull-down menus, or turn off the display of menus and confirmation prompts altogether. You can do either of these by changing the help level.

The classic menus take up one third of most screens, so turning them off by changing from help level 3 to help level 2 allows you to see considerably more of a document while you edit. Even when menus are not displayed, you can still use the commands.

Follow these steps to change the help level:

1. If you are using pull-down menus, choose Help→Change Help Level. If you are using classic menus, press F1 F1.
2. Choose the help level you want.

HELP LEVEL	DESCRIPTION
4	Pull-down menu names are displayed on the menu bar at the top of the screen. To see a menu, hold down the Alt key and press the first letter of the menu name. All prompts are displayed. This is the default setting.
3	All classic menus and prompts are displayed.
2	The classic Edit Menu is not displayed, but prompts are displayed. This gives a full-screen display of the document. Other classic menus are displayed if you pause after pressing the menu letter (^K, ^O, ^P, ^Q).

HELP LEVEL	DESCRIPTION
1	No menus are displayed during editing unless you ask for help. Dialog boxes asking you to confirm a response are not used either.
0	Menus are not displayed unless you ask for help. Confirmation dialog boxes are not displayed. You can move, copy, and delete hidden blocks.

3 Press F10 or choose OK.

At help levels 2 and below, you can display the classic Edit Menu by pressing F1.

You can change the default help level at the WINSTALL Set Basic Editing Defaults menu or using WSCHANGE (DBAA).