

🔑 The Sky Fills In key screens & transitions · phone · wall · dark-first

There is no onboarding and no empty state — the dashboard is the only place Vela has. First launch opens on the sky itself. The Clock is already lit, and every other service waits as a ghost — the standard card, unlit, stating what it gives and exactly what it costs. Connecting never leaves the surface for long, and always ends the same way: the card lights in place. Grafted from concept 3: the wall is a pure stage, and every connect action names its price plainly.

Dim sky · Clock lit → Tap a ghost → Pay its cost — a place · a sign-in · a key → It lights in place → Glance == Tend → The wall · PRO

One dial, two states

Glance shows only light. Tend reveals the sockets. A small Glance | Tend dial wakes on touch and sinks when idle — seam 1, solved at 1e.

Light above, unlit below

In Tend, lit cards keep their arrangement; remaining ghosts gather under a headline. You always see what you have while adding.

The return is the reward

Sign-in handoffs leave honestly and land back on the same sky, where the one card you left is lighting — seam 2, solved at 1c.


The wall is a pure stage

Only lit cards, zero chrome. A long hold summons Tend briefly; the phone stays the comfortable place to tend (a remote, secondary, never required).

Scope: every card Interior is a placeholder — the standard card, its SERVICE · WIDGET caption, and a plain value. Widget Internals are a later pass. Web render stands in for React Native; treat as structure, flow and feel.

1a First launch — the dim sky no onboarding, no empty state: one card already lit, four sockets waiting

PHONE · 0 SECONDS IN




WHAT A STRANGER READS, IN ORDER

- 1 The clock is ticking — the product is alive before they touch anything.
- 2 One muted line states the whole game: light the dim cards.
- 3 Each ghost is an unlit socket: what it gives (muted line) and what it costs (the only accent on screen).
- 4 The 10-second action: tap any ghost. There is nothing else to do — no tour, no skip button, nothing to dismiss.

First launch opens on Tend, so the sockets are visible. A ghost is the standard card with no fill — elevation stepped down to the field, text muted, border unchanged.


1b The cheapest light — Weather, a location only one sheet, one tap, then the socket fills where it stood

TAP THE WEATHER GHOST




The sheet names the cost before asking. Typing a city swaps the button to "Light the card".

IT LIGHTS IN PLACE



No spinner, no success page. The socket itself fills: surface steps up, shimmer sweeps, the pulse marks in-flight. The caption earns its widget name: WEATHER → WEATHER · TODAY.


LIT — THE FIRST VALUE



The value fades up in 200ms and it's done. The next ghosts sit right below — the sky itself is the next prompt.


1c The sign-in handoff — Linear (Google is the same door) seam 2: leave honestly, come back to the same sky, and the return is the reward

THE MOMENT BEFORE




State the handoff plainly before leaving. The trip out is expected — so the return can be the reward.

AWAY — THEIR SCREEN, NOT OURS




We don't restyle their login. The contrast is honest — it should feel like a different place.

THE RETURN — SAME SKY, ONE CARD LIGHTING



No reload, no interstitial, no "success" page. You land exactly where you left — and the one card you left is lighting, with a quiet "connected" badge.


LIT — PART OF THE SKY NOW



Above: the badge fades after a few seconds — the card is just part of the sky. Below: if the handoff dies, the socket says so where you left it, and offers the door again. No alert, no apology paragraph.


1d The key paste — Claude usage a paste, a check on the button itself, a light

TAP THE CLAUDE GHOST



The hint says exactly where the key lives. Checking happens on the button ("Checking..."), never a new screen.

IF THE KEY FAILS



The border carries the error. Nothing shakes, nothing turns red beyond the one line.

LIT



Same reward as every other shape: the sheet drops, the socket fills, the value fades up.


1e Glance == Tend — the one dial seam 1: touch wakes the dial, idle sinks it; flipping it is the only way anything can move

GLANCE, IDLE — CHROME FULLY SUNK



Only light. The unlit Calendar isn't here — Glance never shows a socket, so it can never feel empty or nagging.


A TOUCH WAKES THE DIAL — 5 SECONDS



ANY TOUCH

Waking is not tending — nothing can move yet. A brush against the screen can't wreck the sky. Untouched, the dial sinks again.

TEND — THE SOCKETS APPEAR




Hold-drag moves a card (it lifts one surface step; a headline slot opens where it will land). Tapping a card selects it — sizes S · M · W · L and Remove appear beneath. Ghosts gather under the UNLIT line, so you always see what's there while adding. Holding any card in Glance is a shortcut straight here.

Why a dial and not an edit button: the dial states the product's two postures — looking and tending — as one visible fact. It cannot be flipped by a brush (it's small, and waking a tending), it cannot dead-end (the other state is always one tap away), and it is the same control on phone, tablet and wall, so the mental model never changes.

1f The lived-in sky — phone, glance values dominate, chrome is gone; one pulse at most; stale is a badge, never a sentence

WEEKS LATER, AT A GLANCE




HELD BY THE SYSTEM'S RULES

The motion budget on this whole screen is one pulse (Weather, mid-refresh) and the ticking clock. Linear went stale eleven minutes ago — that is a dot and a word, not a banner.

The surface refreshes itself on schedule; nothing here asks to be tapped. This is the resting state of the product — job 4, untouched aliveness.


1g The wall — a pure stage only lit cards, zero chrome; one deliberate hold summons Tend; the one paid door

LANDSCAPE WALL · TABLET · DAY




Zero chrome — no wordmark, no settings, no clock in a corner because the Clock is a card. Taps do nothing. Glanced from across a room.

THE SAME WALL · AFTER DARK




Only the Clock recolors — the ember palette keeps it from blasting white into a dim room. The empty Calendar speaks plainly: "Nothing left today."

A ONE-SECOND HOLD, ANYWHERE




A tap does nothing; a deliberate 1-second hold asks, ignored, the bar sinks after 6 seconds and the stage returns. "Tend here" opens the same Tend as the phone — it sky left, unlit rail right — and flips back to Glance on its own after 30 idle seconds, so a wall can never be left mid-tend.

THE ONE PAID DOOR — "HANG ON A WALL"




Appears only at the door — the first time you flip a screen into wall mode. Everything else in this storyboard stays free, and "Not now" returns you to a fully working phone sky.

1h One card's whole life every state happens in the same socket; nothing ever leaves the sky to report status



GHOST — NOT CONNECTED



EMPTY — STILL LIT, STILL CALM

Try next: "prototype 1e so I can feel the Glance/Tend flip"; "show the OAuth return (1c) as a timed motion sequence"; "riff two alternatives for the ghost card anatomy in 1a"; "go on to the widget-internals pass"; Tweaks: annotations and live clock can be toggled on this file.