



AutoBonusRunner

User Guide

Installation, modes, controls, rewards, and everyday use
Version 1.0.1 | Tashi

AutoBonusRunner automatically plays supported Idle Slayer Bonus Stages. It detects the active stage, plans jumps from the live terrain, handles wall climbs and recovery, collects Bonus Spheres, and performs reward actions.

This guide covers installation, everyday controls, modes, and common troubleshooting. For route behavior, every setting, and detailed diagnostics, see the Complete Manual.

What AutoBonusRunner Does

- Supports Bonus Stages 1, 2, and 3.
- Adjusts jump timing for current movement speed and Spirit Boost.
- Handles gaps, height changes, trenches, wall contacts, and chained climbs.
- Continues normal terrain routing until a real reward object is confirmed.
- Uses small reward jumps, bow fire, and an available grounded Wind Dash.
- Can confirm the Bonus Stage start slider automatically.
- Handles the game's native one-use retry choice.
- Supports background control while the game window is unfocused.
- Records run results and detailed diagnostics.

AutoBonusRunner remains dormant outside supported Bonus Stages.

Installation

Idle Slayer Mod Manager (recommended)

- 1 Install and initialize Idle Slayer Mod Manager.
- 2 Install Idle Slayer Mods Core.
- 3 Import AutoBonusRunner.zip without extracting it.
- 4 Enable AutoBonusRunner and start the game.

Manual installation

Place AutoBonusRunner.dll in:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\Mods\
```

Do not place the DLL directly in the Idle Slayer game directory.

Compatibility

Do not run AutoBonusRunner together with Auto Jump or Bonus Stage Completer. Both can compete for Bonus Stage input, jump timing, start confirmation, and completion state. Disable or remove them before using AutoBonusRunner.

AutoAdventurer 2.0 includes automatic attacking. AutoBonusRunner's Skip mode provides the same quick-completion behavior as Bonus Stage Completer, while its other modes can preserve the native sphere requirement.

Default Control

Key	Action
U	Disable or re-enable automatic Bonus Stage control

An in-game notification confirms the new state. The key can be changed in `AutoBonusRunner.cfg`.

Disabling automatic control releases mod-owned jump input. Detection, diagnostics, and manual-jump observation remain available.

Recommended First Setup

- 1 Launch the game once so the configuration file is created.
- 2 Keep `Mode = "Auto"` for normal unattended play.
- 3 Keep `Skip Start Slider = true`.
- 4 Choose whether the game's native one-use retry should be accepted.
- 5 Enter a supported Bonus Stage; no additional key press is required.

Choosing a Mode

Mode	Ordinary Bonus Stage	Spirit Boost Bonus Stage
Auto	Requires 1 Bonus Sphere, then continues toward the reward	Preserves the game's native sphere requirement
Manual	Preserves the game's native sphere requirement	Preserves the game's native sphere requirement
Skip	Requires 1 Bonus Sphere	Requires 1 Bonus Sphere

Auto is the default. It preserves full Spirit Boost gameplay while allowing ordinary Bonus Stages to complete quickly. Manual is recommended when testing full routes or collecting the normal sphere requirement in every run.

The selected requirement is fixed for each section. If the requirement patch is unavailable, AutoBonusRunner fails safely to the game's native value.

Routing and Collection

AutoBonusRunner reads the active terrain and treats platform tops as landing intervals rather than single points. It evaluates current speed, jump hold time, predicted flight, landing safety, nearby spheres, and physical wall contacts.

The planner prioritizes survival and section completion. Sphere collection is best-effort beyond the amount required to finish. A run may use a normal jump, enter a trench intentionally, climb a contacted wall, or re-plan after an unexpected landing.

Spirit Boost changes horizontal speed during a section. The mod observes the real velocity and updates later predictions instead of relying only on the initial speed.

Completion and Rewards

Reaching the sphere requirement does not immediately disable routing. AutoBonusRunner continues across the terrain until it confirms a real reward box, coin, or gem on consecutive frames.

After that confirmation it can:

- issue small jump pulses;
- fire the bow directly;
- use a selected grounded Wind Dash when its icon is visible, unlocked, and ready.

These reward actions do not require AutoAdventurer.

Failure and Retry

- With `Auto Retry Enabled = true`, the mod chooses the real Continue option when the native one-use Second Wind choice is offered.
- With it set to `false`, the mod chooses No and exits.
- The mod does not create additional retry opportunities or repeatedly reopen the prompt.
- If automatic control is disabled with U, the retry prompt remains manual.

The run summary distinguishes successful completion, deaths, attempts, and completion after a retry.

Configuration File

Launch the game once to create:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\UserData\AutoBonusRunner.cfg
```

Default user settings:

```
[AutoBonusRunner]
"Debug Mode" = false

[AutoBonusRunner Automation]
Mode = "Auto"
"Enabled On Startup" = true
"Toggle Key" = "U"
"Auto Retry Enabled" = false
"Skip Start Slider" = true
```

Configuration Version is managed internally and should not be edited. Restart the game after changing settings so every value is loaded consistently.

Logs and Run Summaries

Important initialization messages, errors, user actions, and run summaries remain visible when Debug Mode is disabled. Route, physics, landing, and wall-recovery warnings are shown only when Debug Mode is enabled.

Independent session logs are stored in:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\UserData\AutoBonusRunner\Logs\
```

Enable Debug Mode only when investigating a reproducible problem. Detailed logs include terrain scans, route candidates, jump input, physics feedback, wall phases, predicted and actual landings, sphere progress, and reward actions.

Quick Troubleshooting

Nothing happens in a Bonus Stage

Press the configured toggle key and look for the enabled notification. Confirm that the stage is Bonus Stage 1, 2, or 3 and that AutoBonusRunner and Idle Slayer Mods Core are enabled.

The character does not jump correctly

Disable other automatic-jump mods. Two mods controlling the same jump input can cancel holds or releases.

The wrong sphere requirement is used

Check Mode, restart the game after editing, and confirm the startup log shows exactly one sphere-requirement patch.

A run dies but later completes

The controller includes recovery and native retry handling, but it does not guarantee a deathless run. Preserve the complete independent session log when the same location fails repeatedly.

Background control does not work

Confirm AutoBonusRunner is enabled and no overlay or other input mod is blocking the game process.

For more help, see Troubleshooting and Logging and Run Statistics.

Full Automation Suite

- AutoAdventurer handles active gameplay, quest selection and travel, Rage, movement abilities, events, and bosses.
- AutoProgression handles purchases, Ascension, craftables, materials, eggs, and quest maintenance.
- AutoClimber handles Ascending Heights routes, enemies, and rewards.
- AutoBonusRunner handles supported Bonus Stages and their reward phase.

Each mod works independently. Together, they automate complementary parts of Idle Slayer.

Support Development

If these mods save you time, you can support continued development through [PayPal](#).