visualization

Source: File RLLT2300_05F0.TXT

User manual

Version: 2015-09-15

Install

Get the last version from this <u>link</u> in the zip file. Unzip it, for example in the drive D:\ with the catalogs structure.




Иллюстрация 1: Project structure sample

Interpreter


This software works in the PHP interpreter. You can download it from the official build for your OS. For example for then Windows: http://windows.php.net/downloads/releases/php-5.6.13-nts-Win32-VC11-x86.zip. And Unzip in the any directory accessable catalog. For example: **D:\xv1\php\php.exe**.

Settings of the PHP


Settings od PHP in the file **D:\xv1t\php\php.ini**. If file dous not exists, please rename the file php.ini-production to the php.ini.

Find line	Change to
;date.timezone =	date.timezone = Europe/Samara
;extension=php_gd2.dll	extension=ext\php_gd2.dll

Task Shedule



Click a Start button and type «Tasks Scheduler»



Add the new task and set name rllt_viz




Иллюстрация 2: Add a action to the task

Program/script: D:\xv1t\php\php.exe

 $\label{localization} Add\ arguments: php\init.php\ $$ \bosch.com\dfsrb\DfsRU\LOC\SmrP\CC\LOG-SmrP\LOG-SmrP-General\3000\ IT\ and\ Processes\500\ SAP\ raports\10\ UC4\ reports\3\ TO\ visualization\RLLT230\ 0\ 05F0.TXT$

Start in: D:\xv1t\projects\rllt_viz




Иллюстрация 3: Add a time trigger

Dayly

Repeat task every: 1 minutes

Set up a screen saver




Иллюстрация 4: Desktop, Right click, Personalize




Иллюстрация 5: Click on Screen Saver




Иллюстрация 6: Select Photos, Press Settings button.




Иллюстрация 7: Set to folder: **D:**\xv1t\tmp\rllt_viz

Main settings

Main setting in the file **D:\xv1t\projects\rllt_viz\settings.ini**Recommended edit this file in the editor such as «notepad++»

```
; This file is a simple option; for the settings of the viz
  This file is a simple options
[visualization]
html_out=no
;yes or no
jpg_out=yes
[time]
;Take current time from
;os - From the operation system
;file from the file (From German time + timezone_diff_hours )
;current=os
current=os
;This array of values of field Typ1, as Samara time
local_time_values=800
;German time zone diff Samara time zone in Hours
timezone_diff_hours=2
;Max Interval for green line of row
success_max_hours=1
;Fields in the visualization table divide by «,»
fields=TO number, Quantity, Material, Source Sbin, D. Stype, Dest. Sbin
;Fields for right text alignment
fields_text_right=Quantity
;Set font size of the table
font_size=30
;This section about German column names to English
[fields]
TO number=TA-Nummer
TO pos=Pos.
Source Stype=Typ1
D. Stype=Typ2
Source Sbin=Vonplatz
Dest. Sbin=Nachplatz
Quantity=Sollmenge Nach
UM=BME
Material=Material
;Header string of the main viz table
header=Open transfer orders
;Main layout file name in the php/element/ catalog
layout=layout0
[image]
width=1920
height=1080
```