System Utility Commands:

- date
- uptime
- hostname
- uname
- which
- cal
- bc

date

Print or set the system date and time

```
Usage: date [OPTION]... [+FORMAT]
 or: date [-u|--utc|--universal] [MMDDhhmm[[CC]YY][.ss]]
Display the current time in the given FORMAT, or set the system date.
Mandatory arguments to long options are mandatory for short options too.
 -d, --date=STRING display time described by STRING, not 'now'
 -f, --file=DATEFILE like --date once for each line of DATEFILE
 -I[TIMESPEC], --iso-8601[=TIMESPEC] output date/time in ISO 8601 format.
                           TIMESPEC='date' for date only (the default),
                           'hours', 'minutes', 'seconds', or 'ns' for date
                           and time to the indicated precision.
 -r, --reference=FILE
                           display the last modification time of FILE
 -R, --rfc-2822
                           output date and time in RFC 2822 format.
                           Example: Mon, 07 Aug 2006 12:34:56 -0600
     --rfc-3339=TIMESPEC output date and time in RFC 3339 format.
                           TIMESPEC='date', 'seconds', or 'ns' for
                           date and time to the indicated precision.
                           Date and time components are separated by
                           a single space: 2006-08-07 12:34:56-06:00
                           set time described by STRING
 -s, --set=STRING
                         print or set Coordinated Universal Time (UTC)
 -u, --utc, --universal
              display this help and exit
     --version output version information and exit
```

uptime:

Tell how long the system has been running

uptime gives a one line display of the following information. The current time, how long the system has been running, how many users are currently logged on, and the system load averages for the past 1, 5, and 15 minutes

```
Options:
-p, --pretty show uptime in pretty format
-h, --help display this help and exit
```

```
-s, --since system up since
-V, --version output version information and exit
```

hostname

Show or set the system's host name

```
Program options:
```

```
-a, --alias alias names
-A, --all-fqdns all long host names (FQDNs)
-b, --boot set default hostname if none available
-d, --domain DNS domain name
-f, --fqdn, --long long host name (FQDN)
-F, --file read host name or NIS domain name from given file
-i, --ip-address addresses for the host name
-I, --all-ip-addresses all addresses for the host
-s, --short short host name
-y, --yp, --nis NIS/YP domain name
```

Description:

This command can get or set the host name or the NIS domain name. You can also get the DNS domain or the FQDN (fully qualified domain name). Unless you are using bind or NIS for host lookups you can change the FQDN (Fully Qualified Domain Name) and the DNS domain name (which is part of the FQDN) in the /etc/hosts file

uname

This command will give you system information. It is one of the important command that should be used every time you login to a Linux/Unix machine.

```
Usage: uname [OPTION]...

Print certain system information. With no OPTION, same as -s.

-a, --all print all information, in the following order, except omit -p and -i if unknown:

-s, --kernel-name print the kernel name
-n, --nodename print the network node hostname
-r, --kernel-release print the kernel release
-v, --kernel-version print the kernel version
-m, --machine print the machine hardware name
-p, --processor print the processor type or "unknown"
-i, --hardware-platform print the hardware platform or "unknown"
-o, --operating-system print the operating system
--help display this help and exit
--version output version information and exit
```

which

```
Shows the full path of (shell) commands

Usage: /usr/bin/which [options] [--] COMMAND [...]
```

Write the full path of COMMAND(s) to standard output.

```
--version, -[vV] Print version and exit successfully.

--help, Print this help and exit successfully.

--skip-dot Skip directories in PATH that start with a dot.

--skip-tilde Skip directories in PATH that start with a tilde.

--show-dot Don't expand a dot to current directory in output.

--show-tilde Output a tilde for HOME directory for non-root.

--tty-only Stop processing options on the right if not on tty.

--all, -a Print all matches in PATH, not just the first

--read-alias, -i Read list of aliases from stdin.

--skip-alias Ignore option --read-alias; don't read stdin.

--read-functions Read shell functions from stdin.

--skip-functions Ignore option --read-functions; don't read stdin.
```

cal and bc

cal command is simply for calendar and bc is for calculator