

Installation de Proxmox


Pour installer Proxmox, il est nécessaire de disposer d'une clé USB afin de créer une *clé bootable*. Pour cela, on utilise le logiciel **Rufus**, qui permet de générer une clé de démarrage à partir d'une image ISO.

1. Téléchargement de l'image ISO :

Rendez-vous sur le site officiel de **Proxmox** et téléchargez la dernière version de l'ISO disponible.

2. Création de la clé bootable avec Rufus :

- Lancez Rufus.
- Sélectionnez votre clé USB comme *périphérique*.
- Dans la section *Type de démarrage*, choisissez **Image disque / ISO**, puis importez l'ISO de Proxmox.
- Cliquez sur **Démarrer** et attendez la création complète de la clé bootable.



3. Démarrage du serveur sur la clé USB :

- Branchez la clé USB sur le serveur et connectez également un écran.
- Allumez le serveur et appuyez sur la touche **F12** pour accéder au **Boot Menu**.
- Choisissez votre clé USB
- L'interface graphique d'installation de Proxmox s'affiche alors.

4. Configuration de Proxmox :

- Suivez les étapes d'installation et configurez les paramètres réseau.
- Attribuez une **adresse IP**, un **nom d'hôte**, et définissez un mot de passe (*adminadmin*).

5. Connexion au serveur Proxmox :

Une fois l'installation terminée, reliez le serveur à votre PC via un câble RJ45. Sur le PC hôte, ouvrez un navigateur et accédez à l'adresse IP configurée pour Proxmox afin de vous connecter à l'interface web d'administration.

Procédure d'installation Proxmox

1. Démarrage

- Reboot de la machine
- Appuyer sur **F11 (HP) / F12 (DELL)**
- Sélectionner **UEFI (clé USB)**

2. Installation Proxmox





END USER LICENSE AGREEMENT (EULA)

END USER LICENSE AGREEMENT (EULA) FOR PROXMOX VIRTUAL ENVIRONMENT (PROXMOX VE)

By using Proxmox VE software you agree that you accept this EULA, and that you have read and understand the terms and conditions. This also applies for individuals acting on behalf of entities. This EULA does not provide any rights to Support Subscriptions Services as software maintenance, updates and support. Please review the Support Subscriptions Agreements for these terms and conditions. The EULA applies to any version of Proxmox VE and any related update, source code and structure (the Programs), regardless of the the delivery mechanism.

1. License. Proxmox Server Solutions GmbH (Proxmox) grants to you a perpetual, worldwide license to the Programs pursuant to the GNU Affero General Public License V3. The license agreement for each component is located in the software component's source code and permits you to run, copy, modify, and redistribute the software component (certain obligations in some cases), both in source code and binary code forms, with the exception of certain binary only firmware components and the Proxmox images (e.g. Proxmox logo). The license rights for the binary only firmware components are located within the components. This EULA pertains solely to the Programs and does not limit your rights under, or grant you rights that supersede, the license terms of any particular component.
2. Limited Warranty. The Programs and the components are provided and licensed "as is" without warranty of any kind, expressed or implied, including the implied warranties of merchantability, non-infringement or fitness for a particular purpose. Neither Proxmox nor its affiliates warrants that the functions contained in the Programs will meet your requirements or that the operation of the Programs will be entirely error free, appear or perform precisely as described in the accompanying documentation, or comply with regulatory requirements.
3. Limitation of Liability. To the maximum extent permitted under applicable law, under no

Abort

I agree

- Option : *filesystem* -> **ext4**
- Changer la **langue**
- Renseigner :
 - **Mot de passe** : adminadmin
 - **Adresse mail** : equipe1btssio@gmail.com

3. Configuration réseau



Management Network Configuration

Please verify the displayed network configuration. You will need a valid network configuration to access the management interface after installing.

After you have finished, press the Next button. You will be shown a list of the options that you chose during the previous steps.

- **IP address (CIDR):** Set the main IP address and netmask for your server in CIDR notation.
- **Gateway:** IP address of your gateway or firewall.
- **DNS Server:** IP address of your DNS server.

Management Interface	● enp0s3 - 08:00:27:09:06:4b (e1000) ▼	
Hostname (FQDN)	proxmox.local	
IP Address (CIDR)	192.168.1.201	/ 24
Gateway	192.168.1.1	
DNS Server	192.168.1.1	

Abort Previous Next

- **DNS** : 80.10.246.2 ou 8.8.8.8

4. Finalisation :

