

[Back](#)

COPADO | GIT BRANCH-MASTER TO MAIN

KB0100369 - [Latest Version](#)

☆☆☆☆☆ 1 views

Switching between master and main - Overview

All new source code repositories created on GitHub will be named "main" instead of "master" as part of the company's effort to remove unnecessary references to slavery and replace them with more inclusive terms.

There is no actual difference between main and master, it's just the name of the default branch.

How to change the branch from Master to Main?

Steps:

Step 1 – Move the master branch to 'main'

Step 2 – Push 'main' to remote repo.

Step 3 – Point HEAD to 'main' branch.

Step 4 – Change default branch to 'main' on GitHub site.

Step 5 – Delete 'master' branch on the remote repo.


Detailed steps can be referred here – [How to configure your default branch from 'master' to 'main'](https://humanaprod.service-now.com/asc?id=esc_kb_article&sysparm_article=KB0056463) (https://humanaprod.service-now.com/asc?id=esc_kb_article&sysparm_article=KB0056463).

Impacts in Copado / Azure

The name change impacts Copado in certain areas,

2.1 Git Repos in Azure

The Git repos created for each org has the master branch, this needs to be changed to main



2.2 Git Snapshots in Copado

The Git snapshots which were created with master branch needs to be re-created with main branch 1

2.3 Org credentials

Org Credentials needs to be validated again on changing branch to main

2.4 Pipeline

In Pipeline the main branch needs to be updated



Revised by Regin Kanagappa
Last modified 3 months ago

Leave

Pipeline

B2B Pipeline

Related

Details

Pipeline Name

B2B Pipeline

Active

☒

Git Repository

[B2B Production](#)

Main Branch

master

2.5 Pipeline Connections

The destination branch needs to be replaced with main

Pipeline Connection

DFS-000023

DFS-000023

Pipeline

[B2B Pipeline](#)

Source Environment

[B2B_Staging](#)

Destination Environment

[B2B_Production](#)

Branch

arcstaging

Fields Updated By Co

Sync Merge State

Needs recalculating

Sync Pull State

Needs recalculating

Destination Branch

master