



Ubuntu Server环境准备

1. VMware虚拟机配置


第一步：选择创建新的虚拟机




第二步：选择自定义配置




第三步：设置硬件兼容性为Workstation 17.x




第四步：选择稍后安装操作系统



第五步：选择客户机操作系统为Linux,Ubuntu 64位




第六步：设置虚拟机名称与位置，如Ubuntu Server24.04




第七步：处理器配置，设置为2颗2核




第八步：设置虚拟机内存大小为4096MB



第九步：使用NAT网络地址转换




第十步：选择I/O控制器类型LSI Logic




第十一步：选择磁盘类型为SCSI




第十二步：创建新虚拟磁盘



第十三步：指定磁盘容量为100G




第十四步：指定磁盘文件



单击下一步，完成最终设置



2. 下载Ubuntu Server24.04镜像



Ubuntu Server: Ubuntu长期支持(LTS)版本, LTS意为"长期支持", 一般为5年。LTS版本将提供免费安全和维护更新至 2029年4月。

推荐系统配置说明:

Ubuntu 24.04 LTS

下载专为桌面PC和笔记本精心打造的Ubuntu长期支持(LTS)版本。LTS意为"长期支持", 一般为5年。LTS版本将提供免费安全和维护更新至 2029年4月。

[Ubuntu 24.04 LTS发布说明](#)

推荐的系统配置要求:

- ✓ 双核2 GHz处理器或更高
- ✓ 4 GB系统内存
- ✓ 25 GB磁盘存储空间
- ✓ 可访问的互联网
- ✓ 光驱或USB安装介质

[下载 24.04](#)

如需其他版本的Ubuntu, 请参考Ubuntu桌面的[更多信息](#)



第一步: 获取Ubuntu Server

<https://releases.ubuntu.com/24.04/>

Ubuntu 24.04.1 (Noble Numbat)

Select an image

Ubuntu is distributed on four types of images described below.

Desktop image

The desktop image allows you to try Ubuntu without changing your computer at all, and at your option to install it permanently later. This type of image is what most people will want to use. You will need at least 1024MiB of RAM to install from this image.

64-bit PC (AMD64) desktop image

Choose this if you have a computer based on the AMD64 or EM64T architecture (e.g., Athlon64, Opteron, EM64T Xeon, Core 2). Choose this if you are at all unsure.

Server install image

The server install image allows you to install Ubuntu permanently on a computer for use as a server. It will not install a graphical user interface.

64-bit PC (AMD64) server install image

Choose this if you have a computer based on the AMD64 or EM64T architecture (e.g., Athlon64, Opteron, EM64T Xeon, Core 2). Choose this if you are at all unsure.


下载后如下图所示

今天




amd64表示的是该安装包是为基于AMD64架构的64位系统设计的。AMD64，也被称为"x86-64"或"x64"，是64位微处理器架构及其相应指令集的一种，它是Intel x86架构的扩展。尽管该名称中包含“AMD”，但它不仅适用于AMD的处理器，也适用于支持该架构的其他处理器，包括Intel的64位处理器。

3. 加载Ubuntu Server




4. Ubuntu Server系统安装


选择安装语言




单击继续选择不更新



确认语言后，选择Done




键盘配置




设置Ubuntu Server (minimized)


可以通过移动上下方向键实现




Network configuration网络配置




设置代理地址




注意设置镜像地址，设置为<https://mirrors.tuna.tsinghua.edu.cn/ubuntu>




设置磁盘存储



默认使用整个磁盘，即虚拟机硬盘大小（开始配置的100G），也可以选择自定义分区。此处，我们默认即可。选择Done，回车。



然后单击Continue继续



设置用户名称

注意系统信息填写：


Your name: 用户账号（简写）

Your Server name: 主机名称


Pick a username: 用户账号（完整）

Choose a password: 用户密码


Confirm your password: 再次输入密码，确认密码




选择Skip for now, 单击Done




安装OpenSSH server




选择要安装的软件



设置完成后，选择reboot now，如下图所示：



看到下面界面：真机拔掉U盘、如果是虚拟机则直接回车



使用刚才发送的账号和密码进行登录

```
Ubuntu 24.04.1 LTS polaris-server tty1
polaris-server login: [ 145.850097] Bluetooth: hci0: unexpected cc 0x0c12 length: 2 < 3
[ 145.850352] Bluetooth: hci0: Opcode 0xec12 failed: -38
polaris-server login: polaris
Password:
Welcome to Ubuntu 24.04.1 LTS (GNU/Linux 6.8.0-41-generic x86_64)

 * Documentation:  https://help.ubuntu.com
 * Management:    https://landscape.canonical.com
 * Support:       https://ubuntu.com/pro

This system has been minimized by removing packages and content that are
not required on a system that users do not log into.

To restore this content, you can run the 'unminimize' command.

The programs included with the Ubuntu system are free software;
the exact distribution terms for each program are described in the
individual files in /usr/share/doc/*/copyright.

Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by
applicable law.

To run a command as administrator (user "root"), use "sudo <command>".
See "man sudo_root" for details.

polaris@polaris-server:~$
```