# **Bug Reports**

Example

### **Table of contents**

1.	MOBILE APPLICATION	3
2.	WEB APPLICATION	5
•	DESITOR APPLICATION	-

## 1. Mobile Application

### **View Issue Details**

ID:	Category:	Severity:	Reproducibility:	Date Submitted:	Last Update:
37223	Functional	minor	always	2013-03-06 16:44	2013-03-11 05:12

Reporter: Platform: iPhone4

Assigned To: OS:

Priority: normal
Status: assigned
Product Version: 12.5
Product Build: #3
Resolution: open

Projection: none

ETA: none Fixed in Version:

**Target Version:** 

Summary: No invitation to application is received by a user

**Description:** No e-mail is received by a user after invitation has been sent in mobile app

Steps To 1. Launch mobile app

Reproduce: 2. Log in

3. Tap icon in top left corner to open left menu

4. Select Account Settings


5. Tap Edit button in Connect block

6. Enter necessary info into Enter email of your friend you would like to invite block

7. Tap Send

8. Check email you've sent invitation to

Actual result: No invitation is received Expected result: Invitation is received



## 2. Web Application

#### **View Issue Details**

ID:	Category:	Severity:	Reproducibility:	Date Submitted:	Last Update:
37223	Localization	minor	always	2013-03-06 16:44	2013-03-11 05:12

Reporter: Platform: Windows

Assigned To: OS:

Priority: normal OS Version: 7

Status: assigned Product Version: 2
Product Build: #34 Resolution: open

Projection: none

ETA: none Fixed in Version: Target Version:

Summary: Error message in Gift Card block is not translated into German

Description: Error message in Gift Card block on Payment Info step is not translated into German

Steps To 1. Go to the front end

Reproduce: 2. Log in as registered user

- 3. Add any product to the cart
- 4. Click Shopping Bag/Proceed to Cart
- 5. Change language to German
- 6. Proceed to Payment Info step
- 7. Enter any word into Gift Card Code (GESCHENKKARTEN-CODE) field in Gift Card (GESCHENKKARTE) block
- 8. Click Einlosen


Actual result: Error message "You've entered WRONG or NOT active Gift certificate code 'fdgsvd' ." is not translated into German

Expected result: Error message is translated into German

Environment:

Win7, FF11, Chrome19

Attached Files:



### 3. Desktop Application

#### **View Issue Details**

ID:	Category:	Severity:	Reproducibility:	Date Submitted:	Last Update:
-----	-----------	-----------	------------------	-----------------	--------------

37223	System/application	major	always	2013-03-06 16:44	2013-03-11 05:12
	crashes				

Reporter: Platform: Windows

Assigned To: OS:
Priority: normal OS Version: XP

Status: assigned Product Version: 1.2
Product Build: A12 Resolution: open

Projection: none

ETA: none Fixed in Version:

Target Version:

**Summary:** Error after saving changes to form that has been deleted

Description: Error after saving changes to form that has been deleted

**Steps To** 1. Open project with locked evaluation form. Open form in Designer. **Reproduce:** 2. Open Project Explorer and delete project that is currently in use.

3. Click on 'Clear all items' in toolbar. Press 'Yes'.

4. Click on 'Import from Project' in toolbar. Select any form. Press 'Ok'.

5. Click on 'Yes' in dialog message about saving changes.

Actual result:

Error occurs (see screenshot and log file).

Expected result:

User can see correct message that form was deleted

#### **Attached Files:**

