



Common Component

Badge

Banner

Bottom Navigation

Bottom Sheet

Buttons

Box Button

Capsule Button

Floating Action Button

Icon button

Text Button

Chips

Controls

Dialog

Empty

Text Inputs

List Header

Search Bar

Page Indicator

Popup

Profile

Progress Indicator

Spinner

Tabs

Top Navigation

Video Player

Contents Component

Card

Image Grid

List

Chatroom Component


Flex Message

Box Button

The Box Button is the most general button in the form of a box.

It is placed in the content area or the bottom area of the screen to be used as the button for executing important actions on the screen.

Anatomy



1. Button container

This shows the form of the button.

You can distinguish the button's attribute with the color applied to the button's background.

2. Button label area

This shows the button's content.

You can apply the text, icon, and the text+icon format using the center alignment by default.

States

Solid Button

Active



The user can select the button.

Inactive



The user cannot select the button.




Pressed



This is a status in which a user is pressing the button to execute an action.




You can notify the progress status inside the button when a user has

Loading			pressed the button. This is used when a button is highly related to switching, such as download and save.
Outline Button			
Active			The user can select the button.
Inactive			The user cannot select the button.
Pressed			This is a status in which a user is pressing the button to execute an action.
Loading			You can notify the progress status inside the button when a user has pressed the button. This is used when a button is highly related to switching, such as download and save.

On/Off states

On			These buttons are turned ON because the user has tapped them. Users can turn off the buttons by re-tapping once again.
Off			These buttons are turned OFF, yet they are able to be selected.



General actions

Solid Green and Outline Gray buttons can trigger independent actions when used by itself. However, if you want to use them with on/off features, Solid buttons are only for turned-on state while Outline ones are only for turned-off state.

Destructive actions


Red buttons can trigger independent actions only by Solid Green. Outline Green cannot be used independently. When red buttons are used

Red buttons can trigger independent actions only by Solid type. Outline types cannot be used independently. When red buttons are used to show on/off states, Solid buttons are for turned-on state and Outline buttons are for turned-off state.

Types

The type is classified according to the box button's form and usage.

[Request Components New Spec Up](#)



- The basic box button form has a background filled with primary green.
- Red buttons are used to execute a destructive action, such as deletion.
- Outline type buttons have an outline that doesn't fill up the button's background with color.
- Outline types are used as an action button with a lower priority than the solid button.

Sizes

The Box Button is provided in various sizes as shown below to fit in various environments. (Refer to the design template)

XSmall



Small



Medium



Large




XXXX





Usage

Horizontal Button usage




- Primary action and secondary action buttons can be aligned parallel.
- The primary action button is placed on the right.






- If the primary action is a destructive action, use a red button indicating error.
- Using the red button, the user can think again whether the task is a mistake before selecting the final action. (Examples of destruction action: Delete, Replace, Remove, etc)




Do

Use a left/right horizontal button as shown in the example when guiding a stepped process.




Don't

The primary action must be placed on the right when you provide a left/right horizontal button in the bottom area.



Do


Use an outline button for placing a button with equal importance, even if it is not a primary action, in the bottom area.



Don't

Since green and red buttons are primary buttons, only one button can be placed per screen.

Vertical Button usage





Connect more easily with a single link

Start a video meeting with whomever you want
by simply sharing a meeting link.

Please note that meeting links are only valid for 90 days
upon creation. When you join a meeting or send a message
in the meeting chat, your LINE display name and profile
photo will be visible to other participants.

Create meeting

- Use a single button at the bottom of the screen as shown below.
- This button is the most important CTA as it is the primary action on the screen.

Button

Button

When using an up/down vertical alignment on the primary action and the secondary action, place the primary button at the top.

OK

Cancel

Learn more

Get unlimited
sticker

Caution

When arranging single buttons vertically, consider the length of the label displayed on the button. If the labels are short and concise, such as OK, Cancel, a horizontal arrangement may be more appropriate.


Don't

Consider the label length when applying a left/right horizontal button. You must select the button's alignment considering the situation where the label is long or translated into many languages. In the case of example, a vertical alignment with a spacious label area.

9:41




Skip



Do


You can apply box buttons and text buttons as shown in the example.

Sticky Button usage




- Sticky Buttons are fixed at the bottom of the screen and can always be accessed in the same position regardless of the scroll.
- It is placed in a layer above the scrolled content to have the highest hierarchy on the screen except for dialogues and sheets.

Active & disabled state





- The button is disabled before entering the information, and becomes enabled after the information is entered.
- There is no response even after pressing the button in a disabled state, and it proceeds to the next step if you press a button that is in an enabled state.



- If the button state has changed, provide an indication of such changes inside the button using a text label or icon.
- Purchased and downloaded stickers cannot be repurchased or re-downloaded. Therefore, indicate the status inside the button using text in order for the status to be recognized even when the button is disabled.


Contents usage






- It can be used by aligning many buttons in a column. (Excluding extra large buttons)
- In case multiple buttons are being provided in the same column as a set, using just one most important solid button is recommended.

List usage



Use a toggle type button to turn the feature on/off from the list. (Examples of destruction action: Delete, Replace, Remove, etc)

Empty usage




- When it is an empty state without any created content, you can apply box buttons in the center area as shown below.
- Use messages and button labels that can help users with creating content.

Placement


Box Buttons are placed in the content area or the bottom area of the screen to be used as the button for executing important actions on the screen.

Contents area



Apply buttons based on the purpose of the content and their surrounding components.

Bottom area



- This button placed in the screen's button area is used for the purpose of executing the most important action.
- Use one full-single button to fill up the screen's width or the double-button type to align two same sized buttons on both sides.

Capsule Button