



Common Component

Badge

Banner

Bottom Navigation

Bottom Sheet

Buttons

Chips

Controls

Checkbox

Checkmark

Radio Button

Switch

Slider

Dialog

Empty

Text Inputs

List Header

Search Bar

Page Indicator

Popup

Profile

Progress Indicator

Spinner

Tabs

Top Navigation

Video Player

Contents Component

Card

Image Grid

List


Chatroom Component

Flex Message

Checkbox

The checkbox is a selection control used to select elements. Multiple selections are available only for the checkbox amongst selection controls.

Anatomy




1. Background area

Indicate whether an item is selected as the background.

2. Icon / Number area


If selected, a check icon or number will be displayed.

If used in combination with Radio control or to select an option, the Hint check icon is included.



Do

If used to select an option, the Hint check icon will be included.



Don't

If not used to select an option, the Hint check icon will not be used.

States

	Default	Pressed	Disabled
Unselected			
Unselected(Overlay)			
Selected	  	  	  

- The overlay type is used for an unselected checkbox on the background image.
- The numbox can have a number up to three digits.

Types

If the number of selected elements is important, use the numbox (Number box), and if the selected content itself is important, use the checkbox.

Check Type

Light

Dark

Overlay

Controls

Type

☒ Check


☐ Number

Check    In general, icons are displayed for checked elements.

Number




The number is displayed instead of check icons.



Do

If the number of selected elements is important, use the numbox.




Don't

The numbox is not appropriate for Friends Picker.

Usage

Use the checkbox and numbox in the following manner.

List (Vertical)



Place the checkbox on the right side of the list by default, and place it on the left side if there is a UI element on the right.



List

Further details regarding List are available on List.

Card Collection




When used together with content, such as an image, place it on the top right. You may use either the checkbox or numbox as needed.




Card


Further details regarding the card are available on the list.

Select Option






Display the checkbox hint inside of the checkbox to indicate it as a checkbox.



Used for selecting options in Bottom Sheets or Popup.

Placement


On The List



Request design QA

Place the list on the far right side of the list content with 16pt margin. As the margin is not included in the component, design QA is required.


On The Contents



Request design QA

If the image, etc. is placed above the content, it may be placed with 8pt margin on the top right. As the margin is not included in the component, design QA is required.


Single as a selection option



When used as a standalone checkbox for selection options, place it on the left side of the corresponding options.

Design spec

Design spec



Basically, Check Type and Number Type are in the same size. However, if the number becomes 3 digits long for the Number Type, the value of the width will change. As this component cannot be customized, the design QA for the component itself is not required.

Checkmark