



Buttons

Action Button

Floating Action Button

Icon Button

Contents

Avatar

Tag

Image Grid

Skeleton

Video Player

Indicators

Badge

Page Controller

Page Indicator

Progress Indicator

Inputs

Checkbox

Chip

Radio Button

Slider

Stepper

Switch

Text Area

Text Input

Pulldown

Navigations

Tab

Tab - Expanded Tab List

Side Drawer

Footer

Top Navigation


Segmented Control

Bottom Navigation

LIFF View

LIFF (LINE Front-end Framework) is a modal view used in the LINE app, and it supports various view types. Full-flex view is recommended for the family service, but sub window is recommended for certain cases.

Anatomy



1. Top Navigation (LUI Header)
2. Native Close Button
3. Sheet
4. Dimmer

Element Patterns and Types




Overlays

Popup
Snackbar
Toast Overlay
Tooltip
Bottom Sheet
Pulldown Menu


Systems

LIFF View



Full-flex view is used on top of the LINE app, and sub window is used on top of the full-flex layer for the family service.


Full-flex



In full-flex view, the close button on the right (2) is native and cannot be modified in the web. It is placed on the topmost layer.

Top Navigation (1) is implemented in the web, and you can select options based on the guide.

Sub Window




The native close button (2) in sub window can be an icon or text.

It can be placed either at the top right or left.

Top navigation uses the same top navigation UI (1) regardless of OS.

Refer to the [top navigation](#) for more information.




There are 3 view types based on their height for sub window.
The height for each view type is as follows.


	Compact	Tall View	Full View
Height	50%	80%	100%

Behavior

Open / Close Window


Full-flex





Called when the service button is selected in the LINE App.
It is closed when a user taps the close button on the top right.
Only slide in/out transitions are possible, and motion values cannot be modified.

Sub Window




Called from the LINE App or full-flex view.
It is closed when a user taps the close button on the top right.
Only slide in/out transitions are possible, and motion values cannot be modified.

Usage

Full-flex

When using the full-flex view, you should pay attention to the native close button on the top right. The color or position of this button cannot be changed, and it is always located on the topmost layer. It should be designed to make this button clearly visible, and you should also make sure that users do not easily tap the close button by mistake.

Popup on Full Flex





When a pop-up is called from the full-flex view, the dimmer is placed on the entire screen. The close button on the top right is located on the dimmer layer. When a user taps this close button, it closes the entire service. When using a pop-up in the LIFF browser, you should pay attention to the pop-up size to ensure that users do not easily tap the close button by mistake.

Light / Dark Mode

Full-flex view supports the dark mode. As for the dark mode, the close button is provided in white. In this case, the top Navigation should also be aligned with the respective modes.


Solid Background





When the background is either white or black, the background color of the top Navigation should be changed according to mode change.

Transparent Background




Background color can be transparent.

When the background of the top navigation is transparent, you should use a dark background color for the entire page to ensure the visibility of elements on the page.

Use with Scrollable Sheet

Transparent Background






Your browser does not support the HTML5 video element.

When using a solid background color, A) the background color of the top navigation should be kept transparent regardless of scroll or B) the background color of the top navigation can be changed accordingly.

Background Image



Your browser does not support the HTML5 video element.

When the background of the top navigation is transparent and the layer below has images, you need to carefully select background images as the color of elements cannot be changed.

When using a banner, you need to make the top of the image bright or dark to ensure the visibility of elements.


When changing a page or scrolling the bottom sheet, you can A) change the background of the top navigation from transparent to a solid color or B) blur the background.

Sub Window

Sub window is used to provide a modal screen in the full-flex view.
Take heed of the following.


- The use of sub window should be limited to transition the focus from the existing content to the new content.
e.g. Search, take a photo, write a post, scan QR code or edit photo
- Only simple tasks should be performed on the sub window, and users should be able to return to the main window during or immediately after the task is completed.
e.g. Share


Search



Consider using the sub window when using the entire screen for search.


Add & Edit





Use the sub window when returning to the main window after completing an additional task or editing.
Text button can be placed at the top right in the sub window.
Also, the close button can be provided as text.

Share



Use the sub window when returning to the main window after sharing content.
Text button can be placed at the top right in the sub window.

