



Common Component

[Badge](#)[Banner](#)[Bottom Navigation](#)[Bottom Sheet](#)[Buttons](#)[Chips](#)[Controls](#)[Dialog](#)[Empty](#)[Text Inputs](#)[List Header](#)[Search Bar](#)[Page Indicator](#)

Popup

[Profile](#)[Progress Indicator](#)[Spinner](#)[Tabs](#)[Top Navigation](#)[Video Player](#)

Contents Component

[Card](#)[Image Grid](#)[List](#)


Chatroom Component

[Flex Message](#)

Popup

Pop-ups are modal-type components that appear in front of app content to send important information to users or to request a user selection. An LINE Design System Popup is the custom UI pop-up of the LINE app, which is not a system UI pop-up for each OS.

Anatomy



1. Popup surface area

This is the background area of a pop-up. The height of this area varies depending on the amount of content.

2. Contents area

This is an area where the pop-up content, such as text (title, description) or images are indicated.

The center alignment is used by default. For the rest, you can freely configure content according to the purpose and usage of the pop-up.

3. Option area (Optional)

Optional elements, such as progress indicator or pagination, may be provided.

4. Button area

This is an area where the button is placed. A button to dismiss the pop-up must be provided.


If the task of pop-up gets completed along with the dismissal, use one default button (e.g., Confirm).

If the button includes a user's approval or a specific action in addition to the simple dismissal feature, provide a different action button through a default button.

5. Scrim area

This is a background area buried under the pop-up. The pop-up can be emphasized using a dark background.

The handling method when this area is tapped may vary depending on the characteristics of the OS.




Caution


Based on iOS, the pop-up is not closed even if the scrim area is touched by default. You must take precautions to avoid damaging the user experience although this may change depending on where the pop-up is provided.

Types

Because the top section of a pop-up is designed as an area that can be customized according to the purpose, the types are classified as below depending on the bottom button placement. Light mode (default) and dark mode are supported for the pop-up design.


Vertical button type





- This is a pop-up type that can easily emphasize the action button.
- Action buttons must be provided with a button to dismiss the pop-up. Refer to vertical 2-button and 3-button.
- You can provide a single button to dismiss a pop-up instantly when selected after exposing images and text as a simple pop-up for information.
(vertical 1-button)


Simple type



- This is a type mainly used for basic alert pop-ups.
- An action button and a button to dismiss the pop-up are provided side-by-side, or a single button is provided.
- It is ideal to explain the details of alert using brief text in the contents area.
(vertical 1-button)
- You can customize the content area by including images or other elements inside the area according to the purpose and the situation of the pop-up.
(e.g., progress bar)


Do & Don't






Do

You can also customize a simple-type pop-up by including images or other elements inside the content area according to the purpose and the usage.




Do

You can configure as text without image in a vertical button type.




Caution

When selecting the type, it is necessary to consider the amount of the content area. In case of the example, a simple type is recommended.




Caution

In case of placing three buttons vertically, check once again whether the buttons are absolutely necessary.




Caution

When selecting the type, it is necessary to consider the amount of text in the button. You must avoid the situation where the button text is exposed by getting cut off. In case of the example, a vertical button type is recommended.



Don't


A button to close or dismiss the pop-up must be located at the designated button area inside the surface area.



Don't

Do not expose more than one pop-up at once. The next pop-up should be exposed after resolving the current pop-up.

Promotion popup




- LINE Design System promotion pop-ups are mostly used for the purpose of exposing the promotion details right after entering the related screen so that users can focus their attention.
- You can customize the pop-up surface area's background color and the content area according to the service.

- A pop-up can be provided by emphasizing the deep link to the page to check detailed information while providing the promotion related information briefly but as the most effective message.
- It is recommended to provide the Close button to dismiss the pop-up at the lowest section to match the rest of the LINE Design System pop-up experience.

Action

A pop-up action is displayed with the details indicated in the content area or the action button label, and the user must be able to clearly recognize the action that must be selected.

Action button arrangement



Affirmative actions

An affirmative action is an action to be accomplished by the app or the user. If this action button is selected, the process of the details specified on the pop-up will continue. It is provided along with the Cancel button to dismiss the pop-up in most cases, and placed on the right or at the top of the Cancel button. A destructive action, such as "Delete" or "Exit," may be included in an affirmative action.

Dismissive actions

Dismissive action is an action to dismiss or cancel a pop-up. If this action button is selected, the screen is restored to the one before the pop-up was exposed or returned to the previous step of the process. This button is placed on the left or at the bottom of an affirmative action.


Action button labels

Labels indicated on action buttons must play a role of helping users confirm a specific action without any misunderstanding. Therefore, it is important to apply the button labels so that clear recognition of the function becomes possible.


Checklist

Use labels as shortly and briefly as possible, within one or two words if possible.	✓
Use a specific action-oriented phrase for the buttons to execute an action.	✓
Use a consistent label in case of the same or similar features within the LINE Messenger app.	✓
Securing enough space must be taken into consideration to avoid problems in applying multi-language because LINE is a global app.	✓

Do & Don't




Do
A destructive action, such as Delete, can be an affirmative action depending on the situation.



Do
An action button can be disabled until the selection is complete. At this time, the dismissive action button will not be disabled.


Usage

Profile




This is an example of applying a profile in the pop-up content area.


Pagination



You can apply pagination in the pop-up content area to swipe the content.


Rating






You can apply the UI element to get star points in the pop-up content area.

Input




You can apply the UI element to get input in the pop-up content area.

Scroll




Same as the portrait mode.


Two buttons - Horizontal buttons



Same as the portrait mode.


Two buttons - Vertical buttons





- The button layout is same as the portrait mode if switched to the landscape mode.
- However, the button layout will be changed if the surface area of the pop-up exceeds the maximum height value.

Three buttons



- The button layout is same as the portrait mode if switched to the landscape mode.
- However, the button layout will be changed if the surface area of the pop-up exceeds the maximum height value.