



Common Component

Badge

Banner

Bottom Navigation

Bottom Sheet

Buttons

Chips

Controls

Dialog

Snackbar

Toast Overlay

Tooltip

Empty

Text Inputs

List Header

Search Bar

Page Indicator

Popup

Profile

Progress Indicator

Spinner

Tabs

Top Navigation

Video Player

Contents Component

Card

Image Grid

List


Chatroom Component

Flex Message


Snackbar

Snackbar components can be used to inform users of the results of the process executed by an app. The snackbar type exposed at the bottom is used by default. Snackbars are provided only at the bottom for Android. Use the OS default to provide snackbars at the top.

Anatomy



Bottom type



Top type

1. Title/Text area

The feedback content is displayed.

2. Action button area (Optional)

You can display the details of action using a text button.

3. Image area (Optional)

Icons, profiles, and images can be placed here.

The image area does not operate as a specific function or button.

4. Icon

The entire snackbar area is an icon playing a role of affordance for a thing called a link.

The icon does not operate as a specific function or a button.

5. Image area

Icons, profiles, and images are placed here.

6. Title/Text area

Notification or the content of the feedback is displayed.
You can display up to one line for the title and display the text up to two lines.

7. Close button area

The Close button is located in the Top type.

Types

Divided into Bottom Type and Top Type based on the location where the snackbar appears.

Bottom Type

Common



Controls

Type

- ☒ Icon Button
- ☐ Text Button


Background Area

- ☒ Basic
- ☐ Dim

Text Area


- ☒ Title + Description
- ☐ Title + Description 2Line
- ☐ Description 1Line
- ☐ Description 2Line

- In general, it is used as feedback for actions taken by the user.
- You can provide additional actions by including a button in the right area. However, do not place the Close button there.
- Within the component area, the corresponding action area is included, except the area on the right.
- The entire area of the Text Only type provides only information on feedback, not for any actions.



Don't


You cannot provide the X button as an action.



Do

You can provide actions related to the processes executed in an app.


Top Type



- Top type is recommended for use only in chat room environments, and LDS review is required when using in other environments.
- It has been designed by putting chat experience without interference as the first priority, and it disappears after being exposed from the top of the screen.
- You can make it disappear immediately by tapping the X button or moving the component up.

Difference between Snackbar and Toast

Snack Bar



- The entire area operates as a link by default, and providing a specific action is also possible.
- It is located at the bottom or top of the screen.


Toast Overlay




- Providing actions other than simple feedback is impossible.
- It is located at the center or bottom of the screen.

Usage


Bottom Type - text area






- You can include a message sent to users in the text area.
- You can expose up to one line of title and two lines of description, and it can be used in the form of up to three lines with a combination of one line of title and 2 lines of description.

Bottom Type - action button area




- You can provide an action button on the right using an icon or a text button.
- If you do not provide a specific action button, the entire snackbar area will function as a link. If selected, the screen can be redirected to the related page.



Do


You can guide to select using a subtext.



Don't


If an action button is provided, the screen is not redirected even after tapping the left text area.

Bottom Type - image area






- An image related to the message details can be included on the left, but the image itself does not operate as a specific function or button.
- If the snackbar is tapped after providing a guide on the action using the message area, the screen can be redirected to the related page.
- In case of using the pictogram type, display the icons related to the item.



Don't


You cannot provide a Text button on the right if an image is included on the left.

Top type - feedback




- The feedback type can provide only brief messages and cannot include an action button.
- If the component area is tapped, the screen can be redirected to the relevant detailed page.

Top type - Chat notification



- Configure the text area as a method of combining the title and description (Title: friends name, Description: message content)
- If the component area is tapped, the screen is be redirected to the chatroom to check the message.
- Configure as shown in the image on the right side of the example if the message preview is turned off based on the notification settings.


Dim Background Usage




The background of snackbar includes a blur effect by default. In exceptional cases where it is difficult to apply the blur effect due to development issues, you may select dimmed BG in overrides.

Interaction

General



Exposed for three seconds and disappears automatically.




Don't

As the Snackbar location can be contextually changed on each screen if the screen is switched, the Snackbar must become dependent on the screen and disappear at the same time.

Placement


Based on the location where Snackbar appears, the component type and UX rules are different.

Bottom type



Placement	Place at the lowest position with a margin of 15pt. (Sketch Component Symbol contains a margin of 15pt) Place by leaving a space of 15pt when it is placed together with other components fixed to the bottom of the screen. For iPhone X resolution, place it with a margin of 0 based on the home indicator.
Design Guide	Consider whether important bottom navigation or a floating action button exists and place it above that object to prevent any overlap. (The location may change depending on the context of the screen.) Design QA is required on this.

Top type



Placement	Place by leaving a margin of 43pt on top. (Based on portrait) Move down the location of the existing component so the snackbar can be placed at the designated location when it appears in a state of exposing another component.
Design Guide	Its location cannot be changed and no design QA is requested for its location.

