

Loading Bronze Layer

```
/*
=====
== Create The Bronze Layer ==
=====
*/

USE master;
GO

DROP DATABASE IF EXISTS TestDataWarehouse;
GO

CREATE DATABASE TestDataWarehouse;
GO

USE TestDataWarehouse;
GO

CREATE SCHEMA bronze;
GO

CREATE SCHEMA silver;
GO

CREATE SCHEMA gold;
GO

-----

IF OBJECT_ID('bronze.crm_cust_info', 'U') IS NOT NULL
    DROP TABLE bronze.crm_cust_info;
GO

CREATE TABLE bronze.crm_cust_info (
    cst_id          INT,
    cst_key         NVARCHAR(50),
    cst_firstname   NVARCHAR(50),
    cst_lastname    NVARCHAR(50),
    cst_marital_status NVARCHAR(50),
    cst_gndr        NVARCHAR(50),
    cst_create_date DATE
);
GO

IF OBJECT_ID('bronze.crm_prd_info', 'U') IS NOT NULL
    DROP TABLE bronze.crm_prd_info;
GO

CREATE TABLE bronze.crm_prd_info (
    prd_id          INT,
    prd_key         NVARCHAR(50),
    prd_nm          NVARCHAR(50),
    prd_cost        INT,
    prd_line        NVARCHAR(50),
    prd_start_dt    DATETIME,
    prd_end_dt      DATETIME
);
GO
```

```
IF OBJECT_ID('bronze.crm_sales_details', 'U') IS NOT NULL
    DROP TABLE bronze.crm_sales_details;
GO
```

```
CREATE TABLE bronze.crm_sales_details (
    sls_ord_num NVARCHAR(50),
    sls_prd_key NVARCHAR(50),
    sls_cust_id INT,
    sls_order_dt INT,
    sls_ship_dt INT,
    sls_due_dt INT,
    sls_sales INT,
    sls_quantity INT,
    sls_price INT
);
GO
```

```
IF OBJECT_ID('bronze.erp_loc_a101', 'U') IS NOT NULL
    DROP TABLE bronze.erp_loc_a101;
GO
```

```
CREATE TABLE bronze.erp_loc_a101 (
    cid NVARCHAR(50),
    cntry NVARCHAR(50)
);
GO
```

```
IF OBJECT_ID('bronze.erp_cust_az12', 'U') IS NOT NULL
    DROP TABLE bronze.erp_cust_az12;
GO
```

```
CREATE TABLE bronze.erp_cust_az12 (
    cid NVARCHAR(50),
    bdate DATE,
    gen NVARCHAR(50)
);
GO
```

```
IF OBJECT_ID('bronze.erp_px_cat_g1v2', 'U') IS NOT NULL
    DROP TABLE bronze.erp_px_cat_g1v2;
GO
```

```
CREATE TABLE bronze.erp_px_cat_g1v2 (
    id NVARCHAR(50),
    cat NVARCHAR(50),
    subcat NVARCHAR(50),
    maintenance NVARCHAR(50)
);
GO
```

```
-----
CREATE OR ALTER PROCEDURE bronze.load_bronze AS
BEGIN
```

```
    DECLARE @start_time DATETIME, @end_time DATETIME, @batch_start_time DATETIME,
    @batch_end_time DATETIME;
```

```
    BEGIN TRY
```

```
        SET @batch_start_time = GETDATE();
```

```

TRUNCATE TABLE bronze.crm_cust_info;

SET @start_time = GETDATE();
PRINT '-----';
-----';
PRINT 'Load Data Into Table: bronze.crm_cust_info';
PRINT '-----';
-----';
BULK INSERT bronze.crm_cust_info
FROM 'D:\02 projects\06 DataWarehouseProject\Datasets\source_crm\cust_info.csv'
WITH (
    FIRSTROW = 2,
    FIELDTERMINATOR = ',',
    TABLOCK
);
SET @end_time = GETDATE();
PRINT 'Loading Duration: ' + CAST(DATEDIFF(MILLISECOND, @start_time, @end_time)
AS NVARCHAR) + ' Milliseconds';
PRINT '>> -----';

TRUNCATE TABLE bronze.crm_prd_info;

SET @start_time = GETDATE();
PRINT '-----';
-----';
PRINT 'Load Data Into Table: bronze.crm_prd_info';
PRINT '-----';
-----';
BULK INSERT bronze.crm_prd_info
FROM 'D:\02 projects\06 DataWarehouseProject\Datasets\source_crm\prd_info.csv'
WITH (
    FIRSTROW = 2,
    FIELDTERMINATOR = ',',
    TABLOCK
);
SET @end_time = GETDATE();
PRINT 'Load Duration: ' + CAST( DATEDIFF(MILLISECOND, @start_time, @end_time) AS
NVARCHAR) + ' Milliseconds';
PRINT '>> -----';

TRUNCATE TABLE bronze.crm_sales_details;

PRINT '-----';
-----';
PRINT 'Load Data Into Table: bronze.crm_sales_details';
PRINT '-----';
-----';

SET @start_time = GETDATE();
BULK INSERT bronze.crm_sales_details
FROM 'D:\02 projects\06
DataWarehouseProject\Datasets\source_crm\sales_details.csv'
WITH (
    FIRSTROW = 2,

```

```

        FIELDTERMINATOR = ',',
        TABLOCK
    );
    SET @end_time = GETDATE();
    PRINT 'Loading Duration: ' + CAST(DATEDIFF(MILLISECOND, @start_time, @end_time)
AS NVARCHAR) + ' Milliseconds';
    PRINT '>> -----';

    TRUNCATE TABLE bronze.erp_cust_az12;

    PRINT '-----';
    PRINT 'Load Data Into Table: bronze.erp_cust_az12';
    PRINT '-----';

    SET @start_time = GETDATE();
    BULK INSERT bronze.erp_cust_az12
    FROM 'D:\02 projects\06 DataWarehouseProject\Datasets\source_erp\CUST_AZ12.csv'
    WITH (
        FIRSTROW = 2,
        FIELDTERMINATOR = ',',
        TABLOCK
    );
    SET @end_time = GETDATE();
    PRINT 'Loading Duration: ' + CAST(DATEDIFF(MILLISECOND, @start_time, @end_time)
AS NVARCHAR) + ' Milliseconds';
    PRINT '>> -----';

    TRUNCATE TABLE bronze.erp_loc_a101;

    PRINT '-----';
    PRINT 'Load Data Into Table: bronze.erp_loc_a101';
    PRINT '-----';

    SET @start_time = GETDATE();
    BULK INSERT bronze.erp_loc_a101
    FROM 'D:\02 projects\06 DataWarehouseProject\Datasets\source_erp\LOC_A101.csv'
    WITH (
        FIRSTROW = 2,
        FIELDTERMINATOR = ',',
        TABLOCK
    );
    SET @end_time = GETDATE();

    PRINT 'Loading Duration: ' + CAST(DATEDIFF(MILLISECOND, @start_time, @end_time)
AS NVARCHAR) + ' Milliseconds';
    PRINT '>> -----';

    TRUNCATE TABLE bronze.erp_px_cat_g1v2;

    PRINT '-----';
    PRINT 'Load Data Into Table: bronze.erp_px_cat_g1v2';

```

```

PRINT '-----';

SET @start_time = GETDATE();
BULK INSERT bronze.erp_px_cat_g1v2
FROM 'D:\02 projects\06
DataWarehouseProject\Datasets\source_erp\PX_CAT_G1V2.csv'
WITH (
    FIRSTROW = 2,
    FIELDTERMINATOR = ',',
    TABLOCK
)
SET @end_time = GETDATE();

PRINT 'Loading Duration: ' + CAST(DATEDIFF(MILLISECOND, @start_time, @end_time)
AS NVARCHAR) + ' Milliseconds';
PRINT '>> -----';

SET @batch_end_time = GETDATE();
PRINT 'Loading Bronze Layer Duration: ' + CAST(DATEDIFF(MILLISECOND,
@batch_start_time, @batch_end_time) AS NVARCHAR) + ' Milliseconds';
END TRY

BEGIN CATCH
    PRINT '=====';
    PRINT 'ERROR OCCURED DURING LOADING BRONZE LAYER';
    PRINT 'Error Message: ' + ERROR_MESSAGE();
    PRINT 'Error Message: ' + CAST(ERROR_NUMBER() AS NVARCHAR);
    PRINT 'Error Message: ' + CAST(ERROR_STATE() AS NVARCHAR);
    PRINT '=====';
END CATCH

END
GO

-- execute stored procedure
EXEC bronze.load_bronze;

-----

```