

主符號表

編號	宣告類別	符號	位址	型態	初始值	符號註解
1	VAR	ALM_Active	N/A [Auto]	BOOL	N/A	
2	VAR	ALM_Conveyor_Comm_Time	T3	TIMER	N/A	
3	VAR	ALM_Conveyor_Initialize_Tim	T1	TIMER	N/A	
4	VAR	ALM_Rst	N/A [Auto]	BOOL	N/A	
5	VAR	Bowl_Dispenser_Busy	N/A [Auto]	BOOL	N/A	
6	VAR	Bowl_Dispenser_Cmd	N/A [Auto]	BOOL	N/A	
7	VAR	Bowl_Dispenser_Cmd_HMItoP	N/A [Auto]	BOOL	N/A	
8	VAR	Bowl_Dispenser_Cmd_Run	N/A [Auto]	BOOL	N/A	
9	VAR	Conveyor_Initialize	N/A [Auto]	BOOL	N/A	
10	VAR	Conveyor_Initialize_Done	N/A [Auto]	BOOL	N/A	
11	VAR	Conveyor_Run	N/A [Auto]	BOOL	N/A	
12	VAR	Conveyor_Speed_WR	D108	WORD	N/A	
13	VAR	EMC	N/A [Auto]	BOOL	N/A	
14	VAR	EMC_Active	N/A [Auto]	BOOL	N/A	
15	VAR	Err_Active	N/A [Auto]	BOOL	N/A	
16	VAR	Err_HMI_CommTimeout	N/A [Auto]	BOOL	N/A	
17	VAR	HMI_CMD_AckIndex_BUF	N/A [Auto]	WORD	N/A	[PLC Internal] HMI 命令 AckIndex 暫存，給 PRG
18	VAR	HMI_CMD_ResponseCode_BUF	N/A [Auto]	INT	N/A	[PLC Internal] HMI 命令 ResponseCode 暫存，給
19	VAR	HMI_Robot_ActionNo	D1010	INT	N/A	HMI Robot動作編號
20	VAR	HMI_Robot_CutNo	D1012	INT	N/A	HMI 鑷切編號
21	VAR	HMI_Robot_NoodleCabinetNo	D1011	INT	N/A	HMI 鑷櫃編號
22	VAR	HMI_Robot_OutputCabinetNo	D1013	INT	N/A	HMI 出鑷櫃編號
23	VAR	HMItoPLC_EMC	D1004.0	BOOL	N/A	
24	VAR	HMItoPLC_StepMask	D1014	INT	N/A	HMI 半自動選取 Step Bit Mask
25	VAR	HMItoPLC_UnitCabinetNo	D1022	INT	N/A	
26	VAR	HMItoPLC_UnitFirmnessNo	D1023	INT	N/A	
27	VAR	HMItoPLC_UnitID	D1020	DINT	N/A	
28	VAR	Initialize_Done	N/A [Auto]	BOOL	N/A	
29	VAR	IPC_CommandCode	N/A [Auto]	WORD	N/A	準備發送的任務代碼
30	VAR	IPC_CommandRecipeNo	N/A [Auto]	WORD	N/A	準備發送的配方
31	VAR	IPC_CommandTrigger	N/A [Auto]	BOOL	N/A	發送任務觸發訊號
32	VAR	IPC_CommStatus	D1209.0	BOOL	N/A	IPC 通訊狀態：0=Offline、1=Online
33	VAR	IPC_PreCaptureThenFirst	N/A [Auto]	BOOL	N/A	
34	VAR	IPCtoPLC_Busy	D1302	WORD	N/A	IPC 執行中
35	VAR	Machine_Mode	D1109	WORD	N/A	0=Manual、1=Semi、2=Auto
36	VAR	NashRobot_Down0	N/A [Auto]	NashRobot_Down	N/A	
37	VAR	NashRobot_Initial_0	N/A [Auto]	NashRobot_Initial	N/A	
38	VAR	NoodleBasket_1	N/A [Auto]	DUT_NoodleBasket	N/A	
39	VAR	NoodleBasket_2	N/A [Auto]	DUT_NoodleBasket	N/A	
40	VAR	NoodleBasket_3	N/A [Auto]	DUT_NoodleBasket	N/A	
41	VAR	Noodlebasket1_Down	N/A [Auto]	BOOL	N/A	
42	VAR	Noodlebasket1_Up	N/A [Auto]	BOOL	N/A	
43	VAR	Noodlebasket2_Down	N/A [Auto]	BOOL	N/A	
44	VAR	Noodlebasket2_Up	N/A [Auto]	BOOL	N/A	
45	VAR	Noodlebasket3_Down	N/A [Auto]	BOOL	N/A	
46	VAR	Noodlebasket3_Up	N/A [Auto]	BOOL	N/A	
47	VAR	PLCtoHMI_EMC	D1108.0	BOOL	N/A	
48	VAR	PLCtoHMI_RobotManualAckb	D1121	WORD	N/A	Robot單動命令回覆序號
49	VAR	PLCtoHMI_RobotManualAlarm	D1123	INT	N/A	Robot單動異常代碼
50	VAR	PLCtoHMI_RobotManualResul	D1122	INT	N/A	Robot單動結果碼
51	VAR	PLCtoHMI_RobotManualStatus	D1120	INT	N/A	Robot單動狀態
52	VAR	PLCtoIPC_RequestValid	D1203	WORD	N/A	PLC 任務有效旗標
53	VAR	Robot_Exchange_AlarmCode	D3092	INT	N/A	Robot交換FB異常代碼
54	VAR	Robot_Exchange_Finish	D3091.1	BOOL	N/A	Robot交換流程完成
55	VAR	Robot_Initialize_Done	N/A [Auto]	BOOL	N/A	
56	VAR	Robot_Manual_ActionNo	D3080	INT	N/A	送給Robot的動作編號
57	VAR	Robot_Manual_CommandIndex	D3093	WORD	N/A	Robot單動命令序號
58	VAR	Robot_Manual_CutNo	D3082	INT	N/A	送給Robot的鑷切編號
59	VAR	Robot_Manual_NoodleCabinet	D3081	INT	N/A	送給Robot的鑷櫃編號
60	VAR	Robot_Manual_NoodleTypeNo	D3084	INT	N/A	送給Robot的鑷種編號，固定為1
61	VAR	Robot_Manual_OutputCabinet	D3083	INT	N/A	送給Robot的出鑷櫃編號
62	VAR	Robot_Manual_ParameterOK	D3091.0	BOOL	N/A	Robot單動參數檢查結果
63	VAR	Robot_Manual_Permitt	D3091.3	BOOL	N/A	Robot手動操作允許
64	VAR	Robot_Manual_StartReq	D3091.2	BOOL	N/A	Robot單動啟動要求
65	VAR	Robot_Manual_Step	D3090	INT	N/A	Robot單動流程步驟
66	VAR	SemiAuto_Running	D1110.5	BOOL	N/A	半自動流程執行中
67	VAR	SemiAuto_StartReq	N/A [Auto]	BOOL	N/A	半自動啟動脈波
68	VAR	SemiAuto_StepMask	N/A [Auto]	WORD	N/A	本次要執行的 Step Mask
69	VAR	UnitFIFO	N/A [Auto]	DUT_UnitFIFO	N/A	