



RenkoKings

SIMPLE & CLEAR ENTRIES

Cosmik Z-TP Trader Manual

1. Parameters

1.1. Offset

- "Offset: Unit": This parameter has 2 modes: Tick and ninZaATR.
 - **Tick** mode: Applicable to Tick and Renko charts.
 - **ninZaATR** mode: Applicable to all charts excluding Tick and Renko... (Minute, Range, Second, Volume, Heiken Ashi...).

When operating in ninZaATR mode, the system will automatically present an additional parameter: "Offset: ninZaATR Period". This parameter is crucial for specifying the period of ninZaATR.

- "Offset: Multiplier Trend": Impact the placement of the Trend Vector line relative to the price. A larger value moves the Trend Vector line farther from the price, while a smaller value brings it closer.
- "Offset: Multiplier Stop": Determine the placement of the Trailing Stop line in relation to the price. A larger value pushes the Trailing Stop line farther from the price, while a smaller value brings it closer, making the trend more responsive to changes.

*Note: Adjusting these parameters ("Multiplier Trend" & "Offset: Multiplier Stop"), will help in fine-tuning signal areas and trend signals.

1.2. MFI

- "MFI: Period": The period of the Money Flow Index oscillator.
- "MFI: Threshold High": The threshold value of the MFI oscillator indicating overbought market conditions.
- "MFI: Threshold Low": The threshold value of MFI indicating oversold market conditions.

1.3. RSI

- "RSI: Period": The period of the Relative Strength Index oscillator.
- "RSI: Smooth": The smooth coefficient used in calculating RSI.
- "RSI: Plot": Select the value representing the RSI oscillator: RSI value or Avg value.
- "RSI: Threshold High": The threshold value of the RSI oscillator indicating overbought market conditions.
- "RSI: Threshold Low": The threshold value of RSI indicating oversold market conditions.

1.4. Stochastic

- "Stoch: Period D": The period of the %D value in the Stochastic oscillator.
- "Stoch: Period K": The period of the %K value in the Stochastic oscillator.
- "Stoch: Smoothing Method": The method used for Stochastic smoothing (can choose from 11 popular moving-average types).
- "Stoch: Smoothing Period": The period used for Stochastic smoothing.
- "Stoch: Plot": Select the value representing the Stochastic oscillator: %D value or %K value.
- "Stoch: Threshold High": The threshold value of the Stochastic oscillator indicating overbought market conditions.
- "Stoch: Threshold Low": The threshold value of Stochastic indicating oversold market conditions.

1.5. Safe Reversal Period


"Safe Reversal Period": Define the number of candles within the signal search range after the conclusion of the overlap area of the 3 indicators (MFI, RSI & Stochastic).

For example, setting the "Safe Reversal Period" parameter to 3 means that after the conclusion of the Overbought/Oversold zones overlap of MFI, RSI & Stochastic, the system will search for a signal in the next 3 candles.

1.6. Signal


- "Signal: Quantity Per Trend": Define the maximum number of trading signals within a trend phase.

For example, if the "Signal: Quantity Per Trend" parameter is set to 4, the system will generate a maximum of 4 buy/sell signals in an up/down trend.



- "Signal: Quantity Per Flat": Specify the maximum number of signals during a flat phase of the Trend Vector line.

For example, if the "Signal: Quantity Per Flat" parameter is set to 2, the system will generate a maximum of 2 signals in each flat phase of the Trend Vector.




1.7. Level

- "Level: Qualifying Flat Age (Bars)": Define the formation of Support/Resistance levels based on the horizontal period (Flat) of the Trailing Stop line, calculated in the number of bars.

For example, setting the "Level: Qualifying Flat Age (Bars)" parameter to 5 implies that a Support/Resistance level is formed after the Trailing Stop line remains horizontal for at least 5 candles.



- Level: Broken On Body Touch




If this mode is enabled, Support/Resistance levels will be considered concluded upon touching any candle body.

If this mode is disabled:

- A Support level concludes when a candle closes below that level.
- A Resistance level concludes when a candle closes above that level.

2. Smart Level

Moreover, the Smart Level Thickness mode ensures that Support/Resistance levels formed over an extended period are thicker than newly formed ones, making it easier for you to distinguish between them. The system automatically adjusts the thickness of these levels over time.



To adjust the thickness of Support/Resistance levels, use the following parameters:

24	Smart Level Thickness: Enabled	▼
25	Smart Level Thickness: Step	0.01
26	Smart Level Thickness: Thinnest	1
27	Smart Level Thickness: Thickest	5

- "Smart Level Thickness": Enable/Disable the Smart Level Thickness feature.
- "Smart Level Thickness: Step": Determine the step at which the thickness of Support/Resistance levels increases over time as the number of candles they have passed through grows.
- "Smart Level Thickness: Thinnest": Set the minimum thickness of Support/Resistance levels when they are initially formed.
- "Smart Level Thickness: Thickest": Define the maximum thickness that Support/Resistance levels can reach.

3. NinjaScripts Signals

You can rely on the signals below to build your own strategy:

- **Signal_Trend**: 2 = uptrend strong, 1 = uptrend weak, -2 = downtrend strong, -1 = downtrend weak
- **Signal_Trade**: 1 = bullish, -1 = bearish, 0 = no signal

Below is the example condition for this indicator based on the **Signal_Trade**:

If Signal_Trade equal to 1, you can enter long here.

Conversely, if Signal_Trade equal to -1, you can enter short here.

Please follow the link below to find more information about Strategy Builder.

<https://youtu.be/mtMNjOQtQE>