

KingDOM\$ Trader Manual

Dear Trader,

With this document, you now have access to **KingDOM\$, our 1st semi-automated trading system built for strategy-driven traders who rely on the DOM**. We hope you enjoy using KingDOM\$. This manual is here to help you make the most of it.



Important notes for a safe start with KingDOM\$

1. KingDOM\$ is not a complete trading system

KingDOM\$ is both a system that helps traders monitor pending buy and sell orders currently present in the market, and a smart indicator that provides trade entry signals.

Since KingDOM\$ operates as an intelligent entry indicator, traders are advised to combine it with technical analysis - such as identifying support and resistance zones, supply and demand areas, or using additional indicators - to define potential trading zones and enhance entry effectiveness.

2. Start trading on a Simulation Account before going live


Spend at least 1 - 2 weeks trading on a SIM account, or continue until you're confident in the system's operation and consistently achieving your target profitability before moving to a live account. This step is essential.



A. Key components

KingDOM\$ consists of 4 main components displayed on the chart:

1. Total Demand (Accumulated Bid Volume) & Total Supply (Accumulated Ask Volume)
2. Balance Bar
3. Control Panel
4. Buy/ Sell Wall Info Board




1. Total Demand (Accumulated Bid Volume) & Total Supply (Accumulated Ask Volume)

1.1. Total Demand (Accumulated Bid Volume)


This is displayed as a green-shaded area on the chart. The green zone represents the accumulated volume of pending buy orders at each price level.

Total Demand refers to the total number of contracts accumulated within a price range, starting from the current Bid price. This forms an accumulated demand curve, which reflects the level of buying interest at different price points.




1.2. Total Supply (Accumulated Ask Volume):

This is displayed as an orange-shaded area on the chart. The orange zone represents the accumulated volume of pending sell orders at each price level. Total Supply refers to the total number of contracts accumulated within a price range, starting from the current Ask price. This forms an accumulated supply curve, which reflects the level of selling interest at different price points.



1.3. Buy Wall: A Buy Wall refers to the accumulated volume (number of contracts) of pending buy orders at a specific price level, starting from the current Bid price. When displayed on the Total Demand area, it forms a vertical green “wall” on the chart.

1.4. Sell Wall: A Sell Wall refers to the accumulated volume (number of contracts) of pending sell orders at a specific price level, starting from the current Ask price. When displayed on the Total Supply area, it forms a vertical pink “wall” on the chart.



Trading principle based on Buy Wall & Sell Wall:

- *Look for buy opportunities when the Buy Wall is significantly larger than the Sell Wall.*
- *Look for sell opportunities when the Sell Wall is significantly larger than the Buy Wall.*


2. Balance Bar: Displays the relative ratio between Total Demand and Total Supply.



- The green section on the left side of the bar represents the current percentage of Total Demand.
- The pink section on the right side of the bar represents the current percentage of Total Supply.

The Balance Bar helps traders quickly visualize the relative strength between Total Demand and Total Supply in real time.

3. Control Panel: This is the main interface that allows traders to access various functions, such as placing manual orders or activating Long/Short mode for automated entries. It also lets users select the number of contracts, choose order types, select the trading account, apply ATM strategies, and perform actions like Cancel or Close orders.



- **"LONG" Button**

When activated, the system will automatically place a Buy order when a bullish signal appears.

- **"SHORT" Button**

When activated, the system will automatically place a Sell order when a bearish signal appears.

- **"Contract Quantity Selection"**

Below the LONG and SHORT activation buttons, you can select the desired number of contracts for trading. By default, the system sets this between 1 and 4 contracts, but you can adjust it in the settings.

- **"Ref.Price"**

The price from which we apply the offset.

- Close_SignalBar": Uses the Close price of the signal bar as the reference.
- "Open_SignalBar": Uses the Open price of the signal bar as the reference.
- "High_SignalBar": Uses the High price of the signal bar as the reference.
- "Low_SignalBar": Uses the Low price of the signal bar as the reference.
- "Median_SignalBar": Uses the average of the High and Low prices of the signal bar as the reference.
- "Typical_SignalBar": Uses the average of the High, Low, and Close prices of the signal bar as the reference.

- **"Order: Type"**

Select among many types of order:

- MKT: Market order.
- STP: Pending Stop order.
- SLM: Pending Stop-Limit order.
- LMT: Pending Limit order.
- MIT: Pending Market-If-Touched order.
- **"Reference Price: Offset Value"**: The offset (from the reference price) for the KingDOM\$ system to calculate the actual order price. The offset is measured in (in Ticks unit)

Example: Consider a Buy order with offset = 2 ticks.

- Order type = LMT/MIT: actual order price is 2 ticks BELOW the reference price.
- Order type = SLM/STP: actual order price is 2 ticks ABOVE the reference price.

- **"ATM Strategy"**

When ATM module is enabled, ATM strategy selection in Chart Trader is ignored.

ATM module is intended for selection only; please create, edit, delete ATM strategies in Chart Trader.

After you create, edit, delete ATM strategies in Chart Trader, you must refresh your chart for KingDOM\$ to synchronize the indices.

- **"Account Selection"**

You can select the trading account directly from the Control Panel. After selecting an account, press F5 to synchronize the system with the chosen account.


- **"CANCEL" Button**

Click to cancel all pending orders. Executed orders will not be affected.

- **"CLOSE" Button**

Click to close all pending orders as well as active positions.

4. Buy/Sell Wall Info Board: This board displays real-time information about Buy Walls and Sell Walls. Only walls that meet the user-defined minimum ratio difference (Buy-Sell Wall Ratio) will be displayed.



Example: If the user sets the minimum ratio difference between the Buy Wall and Sell Wall to 3x, the Buy/Sell Wall Info Board will display only those walls that meet this condition.

By referencing the **Buy/Sell Wall Info Board**, traders can quickly assess which side - buyers or sellers - is currently dominant, and use that information to decide whether to enter a trade.

- If Sell Wall information is continuously highlighted in pink on the info board, it indicates that selling pressure is consistently present and dominating the buying side
→ In this case, you should look for sell opportunities.

- If Buy Wall information is continuously highlighted in green on the info board, it indicates that buying pressure is consistently present and dominating the selling side
→ In this case, you should look for buy opportunities.

You can adjust the number of Buy/Sell Wall pairs shown on the Buy/Sell Wall Info Board by modifying the **Number Bar: Quantity** setting. This parameter determines how many of the most recent Buy and Sell Wall pairs will be displayed - provided they meet the required conditions.

B. Parameters

▼ Parameters

Depth

10

Buy-Sell Wall: Depth

5

Buy-Sell Wall: Ratio

3

Min Order Gap: Enable


✓

Min Order Gap: Seconds

60

1. Depth

- "Depth": Indicates the number of consecutive price levels included in each Total Demand and Total Supply zone.



Example: If you set the **Depth = 10**, it means KingDOM\$ will display the accumulated volume of pending buy and sell orders within the 10 nearest Bid price levels and 10 nearest Ask price levels.

You can adjust the Depth to 20, 30, 50, ... up to 100, depending on your preference for how much information you want displayed.

2. Buy-Sell Wall: Depth

- "Buy-Sell Wall: Depth": This parameter defines the position at which the Buy/Sell Walls are placed on the Total Demand and Total Supply zones.



Example: If **Buy-Sell Wall: Depth = 3**, the Buy Wall will be placed at the 3rd price level from the current Bid, and the Sell Wall will be placed at the 3rd price level from the current Ask.

Visually, whichever wall appears taller indicates the side currently holding the advantage.

3. Buy-Sell Wall: Ratio

- "Buy-Sell Wall: Ratio" is the parameter that defines the minimum required difference between the Buy Wall and Sell Wall. It specifies how many times larger one side must be compared to the other for the imbalance to be considered significant and displayed on the **Buy/Sell Wall Info Board**.

Note: Buy-Sell Wall: Depth and Buy-Sell Wall: Ratio are closely linked parameters used to assess the current imbalance between buyers and sellers.

*The larger the **Buy-Sell Wall: Depth** and the higher the **Buy-Sell Wall: Ratio**, the more meaningful and reliable the strength comparison between the buying and selling sides becomes.*

4. Min Order Gap


- When "**Enable**" is selected, the system enforces a minimum waiting period between two consecutive trades. This helps prevent excessive or overly frequent entries within a short time frame.
- When "**Disable**" is selected, no minimum time gap is applied, allowing the system to execute trades continuously without delay.

5. Min Order Gap: Second

- "Min Order Gap: Seconds" is the parameter used to define the minimum waiting period (in seconds) between two consecutive trades when Min Order Gap is enabled.

Example: If Min Order Gap: Seconds = 60, the system is only allowed to place trades at intervals of at least 60 seconds.

C. Session Management



The screenshot shows a 'Sessions Management' interface with a dark background. It lists three sessions, each with an 'Enabled' checkbox, a 'Start' time, and a 'Duration'. Blue arrows point from the labels to the input fields. The values are as follows:

Session	Enabled	Start	Duration
Time #1	☒	190000	40000
Time #2	☒	30000	40000
Time #3	☒	80000	40000

Time #1: Enable: Activating this ensures that the KingDOM\$ system only enters orders during the selected time frame.

Time #1: Start (190000) → 19 indicates the hour, 00 for minutes, and 00 for seconds.

Time #1: Duration: Setting this parameter to 40000 indicates that the KingDOM\$ system will search for and execute transactions from 19:00 ET to 23:00 ET. → Time #1: Duration = 4 hours.

Time #2: Enable: Activating this ensures that the KingDOM\$ system only enters orders during the selected time frame.

Time #2: Start (30000) → 3 indicates the hour, 00 for minutes, and 00 for seconds.

Time #2: Duration: Setting this parameter to 40000 indicates that the KingDOM\$ system will search for and execute transactions from 3:00 ET to 7:00 ET → Time #2: Duration = 4 hours.

Time #3: Enable: Activating this ensures that the KingDOM\$ system only enters orders during the selected time frame.

Note: For sessions to work, you need to active “Session Management: Enable”

Sessions Management	
Sessions Management: Enabled	☒
Time #1: Enabled	☒
Time #1: Start	190000
Time #1: Duration	40000
Time #2: Enabled	☒
Time #2: Start	30000
Time #2: Duration	40000
Time #3: Enabled	☒
Time #3: Start	80000
Time #3: Duration	40000

D. Money Management:

We have introduced the Money Management feature to assist traders in setting daily limits.

Money Management	
Enabled	☐
Mode	Based on Account Realized PnL
Max Daily Profit	5000
Max Daily Loss	5000

We provide two modes within this feature:

Money Management	
Enabled	☐
Mode	Based on Account Realized PnL Based on Account Realized PnL Based on Cumulative PnL
Max Daily Profit	
Max Daily Loss	


- **Based on Account Realized PnL**

If this mode is enabled, the KingDOM\$ will flatten the current account once the account's Realized PnL reaches the Daily Profit or Daily Loss threshold.

- **Based on Cumulative PnL**

If this mode is enabled, the KingDOM\$ will flatten the current account once the Cumulative PnL reaches the Daily Profit or Daily Loss threshold.

E. Trade Behavior



The Trade Mode setting allows users to choose how trades are executed, with 2 available modes:

- **Auto – Intelligent Automated Trading**

The system will automatically place a Buy order when it detects that the Buy Wall is at least n times larger than the Sell Wall, and a Sell order when the Sell Wall is at least n times larger than the Buy Wall. The required difference is determined by the Buy-Sell Wall Ratio you have configured.

- **Manual – Manual Trading with Visual Information**

KingDOM\$ provides detailed real-time information about Buy Walls and Sell Walls, allowing traders to make their own entry decisions based on personal analysis.

- If you observe that the current **Sell Wall** is significantly higher than the **Buy Wall**, and selling pressure continues to dominate the info board, this indicates that selling momentum is strong and the sellers are in control.

→ Based on this information, you should look for a **Sell** opportunity.

- If you observe that the current Buy Wall is significantly higher than the Sell Wall, and buying pressure continues to dominate the info board, this indicates that buying momentum is strong and the buyers are in control.

→ In this case, you should look for a **Buy** opportunity.

Track trade information to help traders:

- Review detailed Buy Wall / Sell Wall data at each executed entry point
- Evaluate the effectiveness of each entry
- Learn from past trades and refine trading strategies for better performance in the future

F. General

General	
Price Step: Unit	Tick
Trigger Mode	DoubleClick
Order: Type	MKT
Order: SLM Offset	0
Reference Price	Close_SignalBar
Reference Price: Offset Value	2
Reference Price: Offset Non-Negat...	☒
Quantity: Option 1	1
Quantity: Option 2	2
Quantity: Option 3	3
Quantity: Option 4	4
Round-Turn Commission (Ticks)	0
Connection Lost Message: Enabled	☒

1. **"Price Step: Unit"**: Users can select between "Tick" or "ForexPip"
2. **"Trigger Mode"**: Determines the user interaction required to execute manual trades within KingDOM\$. This setting allows customization of order-trigger behavior to match user preferences and reduce operational risk:
 - DoubleClick: Requires a double-click on the Buy or Sell button to execute an order - helps prevent accidental trades.
 - SingleClick: Enables order execution with a single click, allowing for faster operation when needed.
3. **"Order Type"**: This setting is explained in the Control Panel section.
4. **"Order: SLM Offset"**: The offset of Stop-Limit orders.
5. **"Ref.Price"**: Explained in the **Control Panel** section.
6. **"Reference Price: Offset Value"**: Also explained in the **Control Panel** section.
7. **"Reference Price: Offset Non-Negative"**: If checked, "Reference Price: Offset Value" is a positive value. In contract, "Reference Price" can be switched to negative value.


8. **"Quantity: Option 1 - Quantity: Option 4"**: These are options that allow you to predefine the desired number of contracts for order entry. The preset values will be displayed directly on the Control Panel, allowing you to quickly select the trade quantity with a single click instead of manually entering it each time.
9. **"Connection Lost Message: Enable"**: When enabled, the system will notify you if the internet connection is lost. If disabled, no notification will be displayed in case of an internet disconnection.

G. How to add indicators & systems to KingDOM\$

You can seamlessly incorporate your preferred indicators or trading systems into KingDOM\$ with just a few steps.


By adding external confirmation criteria, the reliability of trading signals is enhanced beyond what the default setup provides.

Step 1: Double-click the green vertical bar located at the far-left edge of the Control Panel. Then click on "Toggle".



Step 2: Select the indicators or trading systems you want to use as inputs for KingDOM\$.

Note: The indicators or systems you select must provide Dedicated NinjaScript Signals for KingDOM\$ to recognize and process the signals properly.




Example: In the picture above, we are using 2 indicators as inputs for KingDOM\$: **King Order Block** and **Easy Trend**.

This means:

- The system will automatically execute a **Buy order** only when the trend turns upward and the price pulls back to the Demand zone — provided that the Buy Wall is larger than the Sell Wall by at least the configured Ratio.
- The system will automatically execute a **Sell order** only when the trend turns downward and the price pulls back to the Supply zone — provided that the Sell Wall is larger than the Buy Wall by at least the configured Ratio.

H. Wall Count

This feature allows you to see how many times the Buy Wall and Sell Wall have appeared. Based on this information, you can gauge the absorption of Market orders.




When does KingDOM\$ record an imbalance between the Buy Wall and Sell Wall?

KingDOM\$ records an imbalance when the ratio between the Buy Wall and Sell Wall meets the predefined condition. Even if the Buy Wall remains consistently larger than the Sell Wall, the system still counts it as a single occurrence of imbalance — regardless of how many consecutive repetitions occur or how long it persists.

When the ratio no longer meets the condition, the system ends that occurrence. If the ratio meets the condition again, a new occurrence is recorded.

In most cases, you may notice that even when the candle is green, the Sell Wall appears more prominently than the Buy Wall.



To form a bullish candle, the Buy volume must exceed the Sell volume. This happens when a large number of **Buy Market** (Buy MKT) orders are executed — indicating strong aggressive buying.

However, KingDOM\$ reflects the volume of **pending (limit) orders** before the trade occurs, not the executed market orders.

When a bullish candle forms but the **Sell Pending (Sell Wall)** is larger than the **Buy Wall**, it indicates:

- A significant number of Buy Market orders are hitting the market.
- This buying pressure is being fully absorbed by Sell Limit orders.

Result: Even though the Sell Wall > Buy Wall, the price still rises because the aggressive buying overwhelms the supply.



To form a bearish candle, the Sell volume must exceed the Buy volume. This occurs when a large number of **Sell Market** (Sell MKT) orders are executed — indicating strong aggressive selling.

Meanwhile, KingDOM\$ reflects the volume of **pending (limit) orders** before the trade takes place.

When a bearish candle forms but the **Buy Pending (Buy Wall)** is larger than the **Sell Wall**, it indicates:

- A significant number of Sell Market orders have been triggered.
- This selling pressure is being absorbed by Buy Limit orders.

Result: Even though the Buy Wall > Sell Wall, the price still falls because the aggressive selling overwhelms the demand.