

Dokumentacija VyOS usmerjevalnika - startup11

May 7, 2026

1 Osnovne informacije

- **Ime naprave:** startup11-vyos
- **Domena:** startup11.local
- **Uporabnik:** vyos (prijava prek SSH ključa)

2 Omrežni vmesniki

Vmesnik	Opis	IPv4	IPv6
eth0	javni internet	88.200.24.241/25	2001:1470:fffd:a8::2/64
eth1	DMZ	192.168.11.1/24	2001:1470:fffd:a9::1/64
eth2	interna LAN	10.11.0.1/24	2001:1470:fffd:aa::1/64
eth3	IPv6-only	–	fd11:11:11::1/64

3 Default usmeritve (static routes)

```
set protocols static route 0.0.0.0/0 next-hop 88.200.24.129
set protocols static route6 ::/0 next-hop 2001:1470:fffd:a8::1
```

4 NAT (IPv4)

```
# Interna LAN (10.11.0.0/24) -> javni internet
set nat source rule 100 outbound-interface name 'eth0'
set nat source rule 100 source address '10.11.0.0/24'
set nat source rule 100 translation address 'masquerade'

# DMZ (192.168.11.0/24) -> javni internet
set nat source rule 110 outbound-interface name 'eth0'
set nat source rule 110 source address '192.168.11.0/24'
set nat source rule 110 translation address 'masquerade'
```

5 DMZ strežniki (vsi v omrežju 192.168.11.0/24)

5.1 Pregled strežnikov

Ime strežnika	IP naslov	OS	Uporabniško ime
sk11-dmz-linux-01	192.168.11.101	Linux	zanzan01
sk11-dmz-linux-02	192.168.11.102	Linux	zanzan02
sk11-dmz-linux-03	192.168.11.103	Linux	zanzan03
sk11-dmz-linux-04	192.168.11.104	Linux	zanzan04
sk11-dmz-linux-05	192.168.11.105	Linux	zanzan05
sk11-dmz-windows	192.168.11.110	Windows	Administrator

5.2 Splošno geslo

123NajboljseGeslo456!
