


Steps to Create EC2 Instance in AWS (Amazon)

Follow the below steps to create an EC2 instance in AWS (Amazon):

Step 1: Login and Navigate to EC2 Dashboard

- Log in to your AWS Management Console.
- From the **Services** menu, choose **EC2** under the **Compute** section.
- Under **Resources**, click **Instances (Running)** to view running instances (if any).



Under Resources >> Click on "Instances running" -- It will show if any EC2 instances are running or not.

Step 2: Launch a New Instance

- Click **Launch Instance**.
- On the "Launch an Instance" page, enter a name for your instance (e.g., my-first-ec2-server).
- You'll now configure your server settings.

Launch an instance [Info](#)

Amazon EC2 allows you to create virtual machines, or instances, that run on the AWS Cloud. Quickly get started by following the simple steps below.

Name and tags [Info](#)

Name

e.g. My Web Server

[Add additional tags](#)

Naming instance

Step 3: Choose Amazon Machine Image

- Select an **Amazon Machine Image** (AMI), which is the OS for your server.
- For beginners, choose **Amazon Linux 2**, **Ubuntu**, or **Windows**, depending on your needs.
- AMIs come preconfigured with OS and some software like templates.

Free tier eligible

Summary

Create key pair

×

Key pairs allow you to connect to your instance securely.

Enter the name of the key pair below. When prompted, store the private key in a secure and accessible location on your computer. **You will need it later to connect to your instance.** [Learn more](#) 

Key pair name

Enter key pair name

The name can include upto 255 ASCII characters. It can't include leading or trailing spaces.

Private key file format

☒ .pem

For use with OpenSSH

☐ .ppk

For use with PuTTY

Cancel

Create key pair

Creating key pair

Step 6: Network and Storage Configuration

- 1. Network Settings:** Use the default VPC and subnet unless you have specific networking needs.
- 2. Firewall (Security Group):** Allow **SSH (port 22)** for Linux or **RDP (port 3389)** for Windows.
- 3. Storage Settings:**
 - Free Tier allows up to **30 GB of General Purpose SSD (gp2)**.
 - Keep default (8 GB) or increase as needed.

▼ **Configure storage** [Info](#)

Advanced

1x 30 GiB gp2 ▼ Root volume (Not encrypted)

Free tier eligible customers can get up to 30 GB of EBS General Purpose (SSD) or Magnetic storage

×

Add new volume

The selected AMI contains more instance store volumes than the instance allows. Only the first 0 instance store volumes from the AMI will be accessible from the instance

0 x File systems [Edit](#)

Step 7: Review and Launch

- Review all configurations to ensure they are **Free Tier eligible**.
- Click **Launch Instance**.
- You will see a confirmation page. Click **View Instances** to see your new server being initialized.

▼ Root volume (Not encrypted)

p to 30 GB of EBS General Purpose (SSD) or Magnetic storage

×

re volumes than the instance allows. Only the first 0 instance store
n the instance

[Edit](#)

New security group

[Storage \(volumes\)](#)

1 volume(s) - 30 GiB

Free tier:

In your first year includes 750 hours of t2.micro (or t3.micro in the Regions in which t2.micro is unavailable) instance usage on free tier AMIs per month, 30 GiB of EBS storage, 2 million I/Os, 1 GB of snapshots, and 100 GB of bandwidth to the internet.

×

Cancel

Launch instance