

Introduction

Windows

Android

iOS / iPadOS

Routers

NAS

- FreeNAS
- ASUSTOR
- QNAP
- Synology
- Western Digital

IoT

FreeBSD

Upgrading ZeroTier

Glossary

ASUSTOR

Install

!

DOWNLOAD

Latest ZeroTier package: <https://download.zerotier.com/dist/asustor>

Manually install:

- App Central -> Management (bottom left) -> Manual Install.

Enable SSH

Enable remote access via SSH:

- Services -> Terminal

```
ssh admin@local-ip
```

ZeroTier CLI

There is no GUI for NAS packages, only a CLI:

```
Usage: zerotier-cli [-switches] <command/path> [<args>]

Available switches:
-h                - Display this help
-v                - Show version
-j                - Display full raw JSON output
-D<path>          - ZeroTier home path for parameter auto-detect
-p<port>          - HTTP port (default: auto)
-T<token>         - Authentication token (default: auto)

Available commands:
info              - Display status info
listpeers         - List all peers
listnetworks      - List all networks
join <network>    - Join a network
leave <network>   - Leave a network
set <network> <setting> - Set a network setting
listmoons         - List moons (federated root sets)
orbit <world ID> <seed> - Join a moon via any member root
deorbit <world ID>   - Leave a moon
```

Upgrading ZeroTier

To upgrade ZeroTier you will need to uninstall the current version of the package and install the desired version. If you wish to preserve your identity you should back up the `identity.secret` file located in `/var/lib/zerotier-one`.

!

NEXT STEPS

Click [here](#) to create your network and start adding devices.

Tags: [platform-specific](#) [asustor](#) [nas](#) [installation](#)

Install

Enable SSH

ZeroTier CLI

Upgrading ZeroTier

Product

- Download [↗](#)
- ZeroTier Central [↗](#)
- Pricing
- Security

Documentation

- Getting Started
- This is ZeroTier
- Guides
- FAQ

Community & Support

- Discussion Forum [↗](#)
- GitHub [↗](#)
- Contact Support [↗](#)

Company

- About [↗](#)
- Blog [↗](#)
- Careers [↗](#)
- Privacy Policy [↗](#)