



Hide or Delete Nodes

Account

Home & Office

Remote Desktop

Network File Sharing

Host a Website

Video Streaming with OBS

USB Device Sharing with VirtualHere

Pi-Hole

Networking

Enterprise

Developer Tools

OS / Platform Notes

FAQ & Troubleshooting

Glossary



Guides

Home & Office

Network File Sharing

Network File Sharing

ZeroTier creates a secure virtual network between devices, allowing seamless file sharing whether you're on Windows, macOS, or Linux. Here's how to share files step-by-step.

Prerequisites

- A working ZeroTier network with 2 or more devices, per the [ZeroTier Quickstart Guide](#)

Step 1: Enable File Sharing

Choose your platform and follow the OS-specific file sharing setup instructions:

Windows

MacOS

Linux

Windows

- Open **Control Panel > Network and Sharing Center**.
- Click **Change advanced sharing settings**.
- Enable: **Network discovery** and **File and printer sharing**
- Right-click the folder to share -> **Properties** -> **Sharing** tab -> **Share...** or **Advanced Sharing...**

Step 2: Transfer Files

Once sharing is enabled:

- Windows to Mac/Linux:** Open `\\<ZeroTier IP>\SharedFolder` in File Explorer.
- Mac to Windows/Linux:** Use Finder → **Connect to Server** with `smb://<ZeroTier IP>`.
- Linux to Others:** Use file browser (as Mac) or CLI with `smbclient`, `scp`, or mount the share.

Optional: Use SFTP Instead (All Platforms)

If you prefer SSH-based transfer:

- Install an SSH server on the host device.
- Connect using an SFTP client like [FileZilla](#) or `scp`.

Example:

```
scp file.txt user@192.168.x.x:/path/to/destination
```

Tags:

beginner

tutorial

beginner

Product

[Download](#)

[ZeroTier Central](#)

[Pricing](#)

[Security](#)

Documentation

[Getting Started](#)

[This is ZeroTier](#)

[Guides](#)

[FAQ](#)

Community & Support

[Discussion Forum](#)

[GitHub](#)

[Contact Support](#)

Company

[About](#)

[Blog](#)

[Careers](#)

[Privacy Policy](#)