



Hide or Delete Nodes

Account

Home & Office

Remote Desktop

Network File Sharing

Host a Website

Video Streaming with OBS

USB Device Sharing with VirtualHere

Pi-Hole

Networking

Enterprise

Developer Tools

OS / Platform Notes

FAQ & Troubleshooting

Glossary



Guides



Home & Office



Network File Sharing

Network File Sharing

ZeroTier creates a secure virtual network between devices, allowing seamless file sharing whether you're on Windows, macOS, or Linux. Here's how to share files step-by-step.

Prerequisites

- A working ZeroTier network with 2 or more devices, per the [ZeroTier Quickstart Guide](#)

Step 1: Enable File Sharing

Choose your platform and follow the OS-specific file sharing setup instructions:

Windows

MacOS

Linux

macOS

- Open `System Settings -> General -> Sharing`.
- Enable **File Sharing**.
- Add folders and configure user permissions.

Use [Apple's File Sharing Guide](#) for more information.

Step 2: Transfer Files

Once sharing is enabled:

- Windows to Mac/Linux:** Open `\\<ZeroTier IP>\SharedFolder` in File Explorer.
- Mac to Windows/Linux:** Use Finder → `Connect to Server` with `smb://<ZeroTier IP>`.
- Linux to Others:** Use file browser (as Mac) or CLI with `smbclient`, `scp`, or mount the share.

Optional: Use SFTP Instead (All Platforms)

If you prefer SSH-based transfer:

- Install an SSH server on the host device.
- Connect using an SFTP client like [FileZilla](#) or `scp`.

Example:

```
scp file.txt user@192.168.x.x:/path/to/destination
```

Tags:

beginner

tutorial

beginner

Prerequisites

Step 1: Enable File Sharing

Windows

macOS

Linux

Step 2: Transfer Files

Optional: Use SFTP Instead (All Platforms)

Product

Download [↗](#)

ZeroTier Central [↗](#)

Pricing

Security

Documentation

Getting Started

This is ZeroTier

Guides

FAQ

Community & Support

Discussion Forum [↗](#)

GitHub [↗](#)

Contact Support [↗](#)

Company

About [↗](#)

Blog [↗](#)

Careers [↗](#)

Privacy Policy [↗](#)