

Getting Started

Quickstart Guide

What is ZeroTier?

OS and Device Compatibility

Awesome ZeroTier Things

This is ZeroTier

Guides

OS / Platform Notes

FAQ & Troubleshooting

Glossary

 > Getting Started > OS and Device Compatibility

OS and Device Compatibility

ZeroTier is lightweight, portable, and compatible across all major platforms and architectures. It typically consumes less than 16 MB of memory, only about 1 MB of storage, and even has a **low-bandwidth mode** for IoT applications. It supports `32-bit ARM (arm32)`, `64-bit ARM (arm64)`, `32-bit Intel (x86)`, `64-bit Intel (x64/amd64)`, MIPS, and `s390x`. You can run it on **Linux**, **macOS**, **Windows**, **iOS/iPadOS**, **Android**, and **FreeBSD**. You can run it on **Routers**, **Network Attached Storage**, and we **have solutions** for when you can't install ZeroTier on a small IoT sensor.

We generally adhere to manufacturer life-cycles for feature support of each platform but will attempt to backport important security updates to versions for older operating systems where possible.

- Our most recent client can still be run on tiny single-board computers like the original Raspberry Pi made over a decade ago and all versions of ZeroTier are backwards compatible.
- ZeroTier is currently single-threaded so devices with more than two cores typically will not offer significant performance gains. Future versions of ZeroTier will introduce multithreading.
- While ZeroTier will operate on very low-power hardware (e.g. a single core 32-Bit ARM running at 600Mhz without AES hardware acceleration (AES-NI)), its performance will suffer.

We recommend the following for a happy ZeroTier experience: `>=1GHz` CPU with at least `2` cores, and `AES-NI`.

 ARM

If you're planning on embedding ZeroTier in a product such as a router, network attached storage or some other IoT application we see that our partners have a better experience with `64-bit ARM` as opposed to `32-bit ARM` since the core speeds are typically higher and the chips are more likely to have `AES-NI`.

 GETTING STARTED

Click [here](#) to create your network and start adding devices.

Tags: **beginner** **installation**

Product

- Download 
- ZeroTier Central 
- Pricing
- Security

Documentation

- Getting Started
- This is ZeroTier
- Guides
- FAQ

Community & Support

- Discussion Forum 
- GitHub 
- Contact Support 

Company

- About 
- Blog 
- Careers 
- Privacy Policy 