



- Android >
- iOS / iPadOS >
- Routers ▾

Router Config Tips

Corporate Firewalls

Teltonika Networks

MikroTik

OpenWRT

OPNsense

Ubiquiti

Route between ZeroTier and Physical Networks
- NAS >
- InT >
- FreeBSD >
- FAQ & Troubleshooting

Ubiquiti

Create directory to persist across firmware upgrades

```
mkdir -p /config/data/firstboot/install-packages/
```

Download

MIPS64 ARM64 ARM32

ER-4, ER-6P, ER-12, ER-12P, ERLite-3, ERPoe-5, ER-8, ERPro-8, EP-R8, USG, USG-Pro, USG-XG-8

```
curl https://download.zerotier.com/dist/ubiquiti/zerotier-one_mips64.deb --output /config/data/firstboot/install-packages/zerotier-one.deb
```

Note: The package must be placed and kept in `/config/data/firstboot/install-packages/` so that your device can automatically re-install ZeroTier upon firmware upgrade.

Install

```
sudo dpkg -i /config/data/firstboot/install-packages/zerotier-one.deb
```

Starting and stopping

Note: the service will start automatically on system boot.

```
sudo systemctl status|start|stop zerotier-one.service
```

Uninstall

```
sudo dpkg -r zerotier-one
sudo rm -rf /config/data/firstboot/install-packages/zerotier-one.deb
sudo rm -rf /config/zerotier-one
```



TIP

Please report bugs or compatibility issues [here](#).

More information about routing between physical and virtual ZeroTier networks can be found [here](#)



NEXT STEPS

Click [here](#) to create your network and start adding devices.

Tags: [ubiquiti](#) [router](#) [installation](#)

Create directory to persist across firmware upgrades

Download

Install

Starting and stopping

Uninstall

Product

- Download [↗](#)
- ZeroTier Central [↗](#)
- Pricing
- Security

Documentation

- Getting Started
- This is ZeroTier
- Guides
- FAQ

Community & Support

- Discussion Forum [↗](#)
- GitHub [↗](#)
- Contact Support [↗](#)

Company

- About [↗](#)
- Blog [↗](#)
- Careers [↗](#)
- Privacy Policy [↗](#)