


Lecture Notes

2026/03/06

We provide two ways to access Linux environments.

- Importing a preinstalled Ubuntu VM image in VMware on your computer. (“VM” stands for “Virtual Machine.”)
- Logging in to a remote server on campus.




How to install Ubuntu on VMware on your own

- If you cannot use our preinstalled Ubuntu VM image for some reason (e.g., you are using macOS)...

- Download Ubuntu 22.04.5 LTS ISO at <https://repo.huaweicloud.com/ubuntu-releases/22.04.5/ubuntu-22.04.5-desktop-amd64.iso> and feed it to VMware.



VMware prompt upon load of Ubuntu VM image



Why did my Ubuntu fail to start in VMware v16?



- The Ubuntu VM image was created on VMware v16.2.5 and hence requires VMware v16.2 or higher, preferably v16.2.5.


Why did my Ubuntu become sluggish all of a sudden?

- Possible cause: Ubuntu may be running unattended upgrades.

```
4 [|||||100.0%] 8 [|||||100.0%]
Mem[|||||4.90G/7.56G] Tasks: 195, 160 kthr; 2 running
Swp[|||||53.2M/7.45G] Load average: 1.38 1.32 1.25
Uptime: 20:14:34

PID USER      PRI  NI  VIRT   RES   SHR  S  CPU% MEM%   TIME+  Command
13397 root        39   19  216M  114M  71172 R 101.1 1.5 42:02.88 /usr/bin/python3 /usr/bin/unattended-up
3712  jb          20    0  2201M 215M  87460 S  2.0  2.8  2:27.34 /usr/bin/comviz
2891  root        20    0   438M  114M  46792 S  3.3  1.5  3:56.02 /usr/lib/xorg/Xorg vt2 -displayfd 3 -au
15574 jb          20    0  31880  5140  3544  R  2.0  0.1  0:02.90 htop
2901  root       -51    0     0     0     0  S  0.7  0.0  0:41.76 irq/129-nvidia
1830  debian-to   20    0   104M  44132 8816  S  0.0  0.6  0:08.33 /usr/bin/tor --defaults-torrc /usr/shar
5248  jb          20    0  2035M  248M  83604 S  0.0  3.2  1:15.57 /usr/lib/chromium-browser/chrom
3719  jb          20    0   420M  7868  5844  S  0.0  0.1  0:03.73 /usr/bin/ibus-daemon --replace
9850  root        20    0     0     0     0  I  0.0  0.0  0:00.38 kworker/u16:60
381   root        0   -20     0     0     0  I  0.0  0.0  0:00.54 kworker/3:1H
```

- Solution:
Set “Automatically Check for Updates” to “Never” in “Software & Updates” and reboot.



The config file of SSH

```
# Please save this file to
# ~/.ssh/config                (Linux)
# or
# %userprofile%\ssh\config     (Windows).
Host fdme-linux 10.134.141.31
  HostName 10.134.141.31
  HostKeyAlgorithms +ssh-rsa,ssh-dss
  StrictHostKeyChecking accept-new
Host fdme-linux2 10.134.141.32
  HostName 10.134.141.32
  HostKeyAlgorithms +ssh-rsa,ssh-dss
  KexAlgorithms +diffie-hellman-group-exchange-sha1,diffie-hellman-group14-sha1,diffie-hellman-group1-sha1
  MACs +hmac-md5,hmac-sha1,hmac-sha1-96,hmac-md5-96
  StrictHostKeyChecking accept-new
Host fdme-linux3 10.134.141.33
  HostName 10.134.141.33
  HostKeyAlgorithms +ssh-rsa,ssh-dss
  KexAlgorithms +diffie-hellman-group-exchange-sha1,diffie-hellman-group14-sha1,diffie-hellman-group1-sha1
  MACs +hmac-md5,hmac-sha1,hmac-sha1-96,hmac-md5-96
  StrictHostKeyChecking accept-new
Host fdme-linux7 10.134.141.38
  HostName 10.134.141.38
  HostKeyAlgorithms +ssh-rsa,ssh-dss
  StrictHostKeyChecking accept-new
Host dell2900d 10.134.143.32
  HostName 10.134.143.32
  HostKeyAlgorithms +ssh-rsa,ssh-dss
  KexAlgorithms +diffie-hellman-group-exchange-sha1,diffie-hellman-group14-sha1,diffie-hellman-group1-sha1
  MACs +hmac-md5,hmac-sha1,hmac-sha1-96,hmac-md5-96
  StrictHostKeyChecking accept-new
Host dell2900c 10.134.143.34
  HostName 10.134.143.34
  HostKeyAlgorithms +ssh-rsa,ssh-dss
  StrictHostKeyChecking accept-new
```

Available on eLearning

Typically “/home/<username>/.ssh/config” on Ubuntu

Typically “C:\Users\<username>\.ssh\config” on Windows


Connecting to a server on campus in cmd.exe

```
D:\soft>ssh 10.134.141.37 -l me211
Unable to negotiate with 10.134.141.37 port 22: no
matching host key type found. Their offer: ssh-rsa,
ssh-dss

D:\soft>copy config "%USERPROFILE%\ssh\"
1 file(s) copied.

D:\soft>ssh 10.134.141.37 -l me211
Warning: Permanently added '10.134.141.37' (RSA) to
the list of known hosts.
me211@10.134.141.37's password:
Last login: Thu Mar 5 22:22:20 2026 from 10.230.37
.240
fdme-linux7:/user/students/me211>[3]
```


How do I disable automatic screen lock so as to avoid frequent password input?



How do I switch between input methods?

Note: The top-right language icon will appear only when typing is allowed, e.g., in a text editor.

