
### 数据库设计:



## 用户表:

Name varchar[20]

Password varchar[20]

Gender integer //女 0; 男 1

Email varchar[30]

Name	password	gender	email
aa	*****	0	1234567788@163.com
bb	*****	1	1122334455@qq.com

# 项目表:

Pid integer

Property integer

Pname varchar[20]

Establisher varchar[20]

Pid	property	pname	establisher
-----	----------	-------	-------------

123	1	aa	SS
456	0	zz	xx

#### 项目成员及权限表:

Pid integer

Membername varchar[20]

Authority interger

pid	membername	authority
1122	asd	7367
3344	ZXC	3452

#### 项目目录表:

Pid integer

Node carchar[50]

Parentnode varchar[50]

Property interger//1 代表是文件夹 0 代表不是文件夹

Text mediumtext

pid	node	parentnode	property	text
156656	Fbgr4	Ver3	1	docx
556776	5tgef3	Sde23	1	txt

## 接口设计:

用户命令处理接口:

定义 status 类为返回类型,包含状态码,路由的 url 和异常说明 登录:

请求(Post / accounts / {name})

Post 请求报文:

{"user\_password":" "}

响应报文:

若成功,则返回:

{"code":"200"

"data":"{"name":""

```
}"
若错误,则返回相应的错误码,
客户端错误状态码:
401: 没登录
406: 用户请求格式不可得
服务端错误状态码(同适用于所有错误返回):
500: 服务器无法解析 ASP 代码
data 里跟错误附加信息
以上错误报文以下接口均一样,以下不再赘述,只描述成功时 data
里具体的数据内容与特殊功能下的错误状态码
注册:
请求 (POST / accounts)
Post 请求报文:
  {"user_name":""
  ,"user_password":""
  ,"user gender":" "
  ,"user_email":" "
  ,"user_signature":""
  ,"user_company":""
  ,"user location":""}
 响应报文:
            正确 状态码 201data
    {"user name":""
     ,"user_password":""
     ,"user_gender":" "
     ,"user_email":" "
     ,"user_signature":""
     ,"user_company":""
     ,"user location":""}
错误则返回相应的状态码及错误原因:
     422: 用户名已被占用,验证错误
个人信息管理
请求 (GET / datamanagers / {name}.
     GET 请求报文:
 无
```

```
响应报文:
   正确 状态码 200data 为
     {"user_name":" "
     ,"user_password":" "
      ,"user gender":" "
      ,"user_email"=" "
     ,"user_signature":""
      ,"user_company":""
      ,"user_location":""}
   失败则返回错误的状态码及错误原因
PATCH / datamanagers / {name}
请求报文: 若不需要更改某一项更改为空即可
     {"user_name":" "
     ,"user_password":" "
     ,"user_gender":" "
      ,"user email"=" "
     ,"user_signature":""
      ,"user_company":""
     ,"user location":""}
响应报文:
   成功 状态码 201data 为
     {"user name":" "
      ,"user_password":" "
     ,"user_gender":" "
      ,"user_email"=" "
     ,"user_signature":""
     ,"user_company":""
      ,"user_location":""}
   失败则返回错误的状态码及错误原因
     422: 更改后用户名重复,
文档存储数据库访问接口:
4.工程管理:
4.1 新建工程: POST / projectsettings
post 请求报文:
  {
      "project_pname"=" "
```

```
,"project_describe"=" "
,"project_property"=" "
  }
响应报文:
  成功 状态码 201data 为
     {
        "pid"=" "
        ,"project_pname"=" "
        ,"project_establisher"=" "
        ,"project_describe"=" "
                       ,"project_property"=" "
   失败则返回错误的状态码及错误原因
  4.2 查看某一工程配置: GET/ projectsettings /{pid}
get 请求报文:无
响应报文
  成功 状态码 200data 为
     {"pid"=" "
     ,"project_pname"=" "
     ,"project_describe"=" "
     ,"project_property"=" "
     ,"project_establisher"=" "
     ,"content":[{"project_member"=" "
     ,project_authority=" "}....]}
   失败 则返回错误的状态码及错误原因
     404: 项目不存在
     403: 无权限
  4.3 工程配置更改 PATCH / projectsettings / {pid}
        patch 请求报文: 若不需要更改某一项更改为空即可
           {"project_pname"=" "
,"project_describe"=" "
,"project_property"=" "
     ,"content":[{"member_name"=" "
     ,project_authority=" "}....]}
响应报文
   成功 状态码 201data 为
```

```
{"pid"=" "
,"project_pname"=" "
     ,"project_describe"=" "
,"project_property"=" "
     ,"content":[{"project_member"=" "
      ,project_authority=" "}···.]}
   失败则返回错误的状态码及错误原因
      403: 无权限
     404: 项目不存在
     406: 格式不正确
  4.4 查看用户参与的所有工程: GET / projectsettings /user
      aet 请求报文:无
      响应报文: 状态码 200data 为
"projects": ["pid"=""
,"project_pname"=" "
,"project_establisher"=" "
,"project_describe"=" "
,"project_property"=" "
,"content":[{"member name"="
,project_authority=" "}....]}
,···.]
}
      失败则返回错误的状态码及错误原因
     404: 项目不存在
   4.5 添加权限
post /projectsettings/{pid}/user/{name}
post 请求报文:
{
    "project_authority":""
成功状态码 201
data 为
{
    "pid":"",
    "membername":"",
```

```
"project_authority":""
}
失败则返回错误的状态码及错误原因
    403: 无权限
    406: 格式不正确
  4.6 删除工程
  DELETE/ projectsettings /{pid}
delete 请求报文:无
响应报文
  成功 状态码 204data 为
     {
    "pid"=" "
  失败 则返回错误的状态码及错误原因
    404: 项目不存在
    403: 无权限
  4.7 删除权限
delete /projectsettings/{pid}/user/{name}
delete 请求报文: 空
成功状态码 204
data 为
{
   "pid":"",
   "membername":"",
}
失败则返回错误的状态码及错误原因
    406:格式不正确
    403: 无权限
5 文档管理:
注意: fname 均为当前文件/文件夹的名字, path 为所在文件夹的完
整路径, 所有文件的根目录均为 root
5.1 查看文档: GET / filemanagers / {fname} / project / {pid} /
file?path=...
get 请求报文:无
GET 响应报文:
成功
```

```
{"file_text":" "
,"fname":""
,"path":""
,"pid":""}
错误的状态码及错误原因:
  404:数据库中无该项目
  403: 无权限
  406:格式不正确
5.2 修改文档: PATCH / filemanagers / {fname} / project / {pid} /
file?path=...
PATCH 请求报文:
  {"file_text":" "}
响应报文:
  成功 状态码 201
Data
{"fname":""
,"path":""
,"pid":""
,"file_text":" "}
   失败则返回错误的状态码及错误原因:
     403: 无权限
     404:数据库中无该文档
     406: 格式不正确
5.3 新建文档: POST / filemanagers / {fname} / project / {pid} /
file?path=...
POST 请求报文:
  {"file_property"=" "
  ,"file_text"=" "}
响应报文:
  成功: 状态码 201data 为
  {"pid":""
,"path"="
     ,"file_fname"=" "
```

```
,"file_property"=" "
     ,"file_text"=" "}
  失败则返回错误的状态码及错误原因:
     403: 无权限
     404:数据库中无该项目
     406:格式不正确
5.4 删除文档: DELETE / filemanagers / {fname} / project / {pid} /
file?path=...
DELETE 请求报文: 空
响应报文:
    成功状态码 204
{"fname":""
,"path":""
,"pid":""}
    失败则返回错误的状态码及错误原因:
     403: 无权限
     404:数据库中无该文档
     406: 格式不正确
6 目录管理:
注意: fname 均为当前文件/文件夹的名字, path 为所在文件夹的完
整路径
6.1 查看目录下所有文件: GET menus / project / {pid} /
path?path=...
由于技术原因、此处的 url 暂无法实现 restful 风格
GET 请求报文:无
响应报文:
     成功则返回状态码 200 data 为
"path":""
,"pid":""
,"files": [{"file_fname":" "
,"file_property":" ","path":"","pid":""},....]
```

## 失败则返回错误的状态码及错误原因:

404: 无该文件 406: 格式不正确 6.2 文档重命名:

6.2 文档重命名: PATCH / menus / {fname} / project / {pid} /

filepaths?path=...

PATCH 请求报文:不需要修改则为空

{"file\_fname=" "}

响应报文:

成功则返回状态码 201 data 为

{"fname="

,"path":"" ,"pid":""}

失败则返回错误的状态码及错误原因:

404: 无该项目

403: 无权限

406: 格式不正确