

CPSC 410 - Operating Systems I

Chapter I: Computer System Overview


Keith Perkins

Original slides by Dr. Roberto A. Flores

Chapter 1 Topics


- Basic Elements
 - Processor, main memory, I/O modules, system bus
- Microprocessors
 - General purpose, graphics, digital signal, system on chip
- Instructions
 - Execution, fetch & execute (F&E), instruction register
- Interrupts
 - Types, flow of control, F&E&I, multiple interrupts
- Memory
 - Hierarchy, principle of locality, cache
- I/O Techniques
 - Programmed, interrupt-driven, direct memory access
- Symmetric multi-processors
 - Advantages, organization, multi-core

- Processor
 - aka CPU
 - Central Processing Unit
 - Controls execution of instructions
 - Performs data processing




Memory

- aka primary/main memory, RAM
 - Random Access Memory
- Stores instructions & data
- Volatile
 - Contents are lost when the computer is shut down




I/O Modules

- aka device drivers
- Move data between the computer and external devices:
 - storage (e.g. hard drive)
 - communications equipment
 - terminals
- Have buffers to push/pull data



System bus

- Means of communication among processors, memory
 & I/O modules
- Its speed limits computer performance
 - Known as the....



System bus

Means of communication

von Neumman Bottleneck

- Data & Code must pass through the bus (the bottleneck)
- Physical & Intellectual barrier*

CPU

^{*} Backus (1978) "Can Programming Be Liberated from the von Neumann Style?" Communications of the ACM, Vol. 28, Num. 8


Chapter 1 Topics

- Basic Elements
 - Processor, main memory, I/O modules, system bus
 - Microprocessors
 - General purpose, graphics, digital signal, system on chip
- Instructions
 - Execution, fetch & execute (F&E), instruction register
- Interrupts
 - Types, flow of control, F&E&I, multiple interrupts
- Memory
 - Hierarchy, principle of locality, cache
- I/O Techniques
 - Programmed, interrupt-driven, direct memory access
- Symmetric multi-processors
 - Advantages, organization, multi-core

Microprocessors


General Purpose

- It brought about PC & handheld computing
- 1 processor or more (cores) on a single chip
- Graphical Processing Units (GPU)



Intel 4004, wikipedia.org

- Efficient computation on arrays of data, e.g., math & physics simulations (for games), large spreadsheets
- Digital Signal Processors (DSP)
 - Streaming audio or video signals; en/decoding (codecs)
- System on a Chip (SoC)
 - Embedded systems (handheld)
 - CPU, GPU, DSP, memory in one chip




Chapter 1 Topics

- Basic Elements
 - Processor, main memory, I/O modules, system bus
- Microprocessors
 - General purpose, graphics, digital signal, system on chip
- Instructions
 - Execution, fetch & execute (F&E), instruction register
- Interrupts
 - Types, flow of control, F&E&I, multiple interrupts
- Memory
 - Hierarchy, principle of locality, cache
- I/O Techniques
 - Programmed, interrupt-driven, direct memory access
- Symmetric multi-processors
 - Advantages, organization, multi-core

Instructions

- A program is a set of instructions stored in memory
- CPU instruction cycle (fetch & execute)
 - program counter (PC) has address of next instruction
 - processor reads (fetches) an instruction from memory
 - instruction stored in instruction register (IR)
 - program counter increments address
 - processor executes instruction; repeat until forever




program counter (PC) has address of next instruction processor <u>fetches</u> instruction from memory instruction stored in instruction register (IR) program counter increments address processor executes instruction; repeat until forever

1 load AC from memory2 store store AC to memory5 add to AC from memory

Instructions

• Example





Chapter 1 Topics


- Basic Elements
 - Processor, main memory, I/O modules, system bus
- Microprocessors
 - General purpose, graphics, digital signal, system on chip
- Instructions
 - Execution, fetch & execute (F&E), instruction register
 - Interrupts
 - Types, flow of control, F&E&I, multiple interrupts
- Memory
 - Hierarchy, principle of locality, cache
- I/O Techniques
 - Programmed, interrupt-driven, direct memory access
- Symmetric multi-processors
 - Advantages, organization, multi-core

- Interrupt normal sequencing of the processor
- Provided to improve processor utilization
 - I/O devices are slower than CPU
 - CPU must pause to wait for device (wasteful use)
- Common types
 - Program: Errors (/0, illegal instruction, memory access)
 - Timer: Processor timer (used for regular basic tasks)
 - I/O: Signal transfer completion (with/without errors)
 - Hardware: Power failure...


- Fetch & Execute & Interrupt
 - Same as before, plus an Interrupt Stage









Simple Interrupt Processing



- What happens when CPU is disrupted by an interrupt?
 - Finish executing instruction N
 - { interrupt }
 - store registers, PC (size M) in control stack @ T
 - update stack pointer to T-M
 - execute interrupt instruction
 @ Y until finishing @ Y+L
 - load back top of control stack
 - continue executing @ N+1




- What happens when CPU is disrupted by an interrupt?
 - Finish executing instruction N
 - { interrupt }
 - store registers, PC (size M) in control stack @ T
 - update stack pointer to T-M
 - execute interrupt instruction
 @ Y until finishing @ Y+L
 - load back top of control stack
 - continue executing @ N+1




- Multiple overlapping interrupts
 - An interrupt happens when another is being handled
 - 1. Disable interrupts (when handling an interrupt)
 - 2nd interrupt waits until 1st interrupt is handled
 - Strictly sequential
 - 2. Use a priority scheme
 - Interrupts can interrupt interrupt-handling...
 - ...but only if they have a higher priority; otherwise they wait
 - Hierarchical (by priority)

- Multiple overlapping interrupts
 - (approach 1) Interrupts disabled



- Multiple overlapping interrupts
 - (approach 2) Priority Scheme




Chapter 1 Topics

- Basic Elements
 - Processor, main memory, I/O modules, system bus
- Microprocessors
 - General purpose, graphics, digital signal, system on chip
- Instructions
 - Execution, fetch & execute (F&E), instruction register
- Interrupts
 - Types, flow of control, F&E&I, multiple interrupts
- Memory
 - Hierarchy, principle of locality, cache
- I/O Techniques
 - Programmed, interrupt-driven, direct memory access
- Symmetric multi-processors
 - Advantages, organization, multi-core

- Major (conflicting) constraints
 - speed (access time), amount, cost
 - Memory must keep up with CPU (speed)
 - Faster access time = greater cost
 - Memory must satisfy data volumes (amount)
 - Greater capacity = smaller cost = slower access speed

Hierarchy going down

- cost decreases
- capacity increases
- access time increases
- frequency of access by CPU decreases
 - really? how does it happen?



Principle of Locality


- Why does frequency of access by CPU decrease?
 - Memory references (i.e., data) needed by CPU (i.e., the current set of instructions in a program) tend to cluster
 - e.g. array "a" being read in a loop
 - Data gets naturally clustered so that the percentage of accesses to each successively lower level is substantially less than that of the level above
- Eventually a set of data is replaced by another, but it's less frequent proportionally to the use within a set, which makes overhead bearable.

Performance Example

- 2 levels
 - T1 @ 0.1µs (1kb)
 - T2 @ 1μs (100kb)

faster but scarce

slower but plenty



- Performance Example
 - 2 levels
 - T1 @ 0.1μs (1kb) faster but scarce
 - T2 @ 1μs (100kb) slower but plenty
 - What's the average access time if...
 - 95% of data in T1 and 5% in T2?

Performance Example

- 2 levels
 - T1 @ 0.1μs (1kb) faster but scarce
 - T2 @ 1µs (100kb) slower but plenty
- What's the average access time if...
 - 95% of data in T1 and 5% in T2?
 - $0.95 * 0.1 \mu s + 0.05 * (0.1 \mu s + 1 \mu s) = 0.15 \mu s$
 - 5% of data in T1 and 95% in T2?

Looks in L1 first then L2


Performance Example

- 2 levels
 - T1 @ 0.1μs (1kb) faster but scarce
 - T2 @ 1μs (100kb) slower but plenty
- What's the average access time if...
 - 95% of data in T1 and 5% in T2?
 - $0.95 * 0.1 \mu s + 0.05 * (0.1 \mu s + 1 \mu s) = 0.15 \mu s$
 - 5% of data in T1 and 95% in T2?
 - $0.05 * 0.1 \mu s + 0.95 * (0.1 \mu s + 1 \mu s) = 1.05 \mu s$
 - It's to our advantage to have frequently accessed data in faster memory locations


reason why caches exist

Cache

- Exploits the Principle of Locality
- Controlled by hardware (i.e., it is invisible to OS)
- Principles
 - Contains a copy of a portion of main memory
 - CPU checks cache for data
 - if found: use data
 - if not found: reads block of data from memory (where data is) and copies it into cache



<u>Me</u>mory



- Conta
- CPU c
 - if four
 - if not for copies i

In practice: several levels are common

Word Transfer

CPU

Cache

Slow


Main Memory

data is) and

Cache Design

- Cache size
 - Even small caches decrease access times
- Cache block
 - Unit of data exchanged between cache and memory
 - Too small: less data than needed (overhead: constant exchanges).
 - Too large: more data than needed (overhead: storing unused data).
- Mapping function
 - Finds location in cache of a newly read block
 - If space needed, an existing block is replaced

Cache block load/replacement



- Cache Design (2)
 - Replacement algorithm
 - Least Recently Used (LRU) Algorithm
 - Write policy
 - Indicates when a block is written back to memory
 - A) each time it is updated (with a new value)
 - Adds unnecessary writing overhead
 - B) each time it is replaced (with another block)
 - Minimizes write operations
 - Leaves memory in an obsolete state
 - ...which interferes with multi-processor operations accessing memory e.g., another program, buffered I/O, DMA

Chapter 1 Topics

- Basic Elements
 - Processor, main memory, I/O modules, system bus
- Microprocessors
 - General purpose, graphics, digital signal, system on chip
- Instructions
 - Execution, fetch & execute (F&E), instruction register
- Interrupts
 - Types, flow of control, F&E&I, multiple interrupts
- Memory
 - Hierarchy, principle of locality, cache
 - I/O Techniques
 - Programmed, interrupt-driven, direct memory access
- Symmetric multi-processors
 - Advantages, organization, multi-core

* When the processor encounters an instruction relating to I/O, it executes that instruction by issuing a command to the appropriate I/O module

Three techniques are possible for I/O operations:

Programme d I/O Interrupt-Driven I/O Direct
Memory
Access (DMA)

What does the CPU do when finding an I/O (read/write) instruction?

- 1) Programmed I/O
 - CPU waits for completion of command and periodically checks the status of the I/O module until it determines the instruction is complete
 - 1. CPU sends I/O command to I/O module
 - If writing, CPU transfers data.
 - 2. CPU waits until I/O module completes command.
 - If reading, CPU transfers data
 - 3. CPU resumes execution
 - Extreme Inefficiency!

Remember the 1 sec verses 16 weeks example?

What does the CPU do when finding an I/O (read/write) instruction?

- 2) Interrupt-driven I/O
 - CPU keeps executing while I/O command is completed
 - 1. CPU sends I/O command to I/O module
 - If writing, CPU transfers data.
 - 2. CPU resumes execution.
 - 3. I/O module triggers an interrupt when command is done
 - If reading, CPU transfers data
 - 4. CPU resumes execution
 - No wait, but CPU still transfers data

- 2) Interrupt-driven I/O Drawbacks
 - Transfer rate is limited by the speed with which the processor can service a device
 - The processor is tied up in managing an I/O transfer since a number of instructions must be executed for each I/O transfer

What does the CPU do when finding an I/O (read/write) instruction?

- 3) Direct Memory Address (DMA)
 - Performed by a separate module on the system bus (DMA)
 - CPU keeps executing while I/O command is completed by DMA module
 - 1. CPU sends I/O command, memory address (where data is read or written), data size and I/O module to DMA
 - 2. CPU resumes execution.
 - 3. I/O module triggers an interrupt when command is done (including data transfer)
 - 4. CPU resumes execution
 - No wait & CPU doesn't transfer data (may have bus contention though)

3) Direct Memory Address (DMA)


- Transfers the entire block of data directly to and from memory without going through the processor
 - processor is involved only at the beginning and end of the transfer
 - processor executes more slowly during a transfer when processor access to the bus is required
- More efficient than interrupt-driven or programmed I/O
- But DMA module uses bus, so CPU might have to wait

Chapter 1 Topics

- Basic Elements
 - Processor, main memory, I/O modules, system bus
- Microprocessors
 - General purpose, graphics, digital signal, system on chip
- Instructions
 - Execution, fetch & execute (F&E), instruction register
- Interrupts
 - Types, flow of control, F&E&I, multiple interrupts
- Memory
 - Hierarchy, principle of locality, cache
- I/O Techniques
 - Programmed, interrupt-driven, direct memory access
 - Symmetric multi-processors
 - Advantages, organization, multi-core

Symmetric Multi-Processors

- A stand-alone computer system with:
 - 2+ similar processors:
 - capable of performing the same functions
 - which (physically):
 - are interconnected by a bus
 - share memory & I/O devices
 - are controlled by an OS that
 - provides interaction between processors and their programs (at the job, task, file, and data levels)



Symmetric Multi-Processors

Advantages


- Performance
 - can yield greater performance (if OS can handle work in parallel)
- Availability
 - failure of one processor does not halt the machine
- Scaling
 - additional processors result in a range of products of different price and performance

Symmetric Multi-Processors

Multi-Core

- 2+ processors (cores) in 1 micro-chip
 - each core has all components of an independent processor (including 2 or 3 cache levels)
- Intel Core i7
 - 4-8 cores
 - 8 Mb L3 cache
 - Intel Iris Pro GPI





Chapter 1 Topics

struction register

, multiple interrupts

- Basic Elements
 - Processor, main memory, I/O modules, system bus
- Microprocessors
 - General purpose, graphics, digital
 system on chip
- Instructions
 - Execution, fetch & execut
- Interrupts
 - Types, flow of con*
- Memory
 - Hierarchy, principle locality, cache
- I/O Techniques
 - Programmed, interrupt-driven, direct memory access
- Symmetric multi-processors
 - Advantages, organization, multi-core