Blis

0.94

Generated by Doxygen 1.8.9.1

Thu Oct 8 2015 22:51:24

## **Contents**

1	Hier	archical	Index		1
	1.1	Class I	Hierarchy		1
2	Clas	s Index			13
	2.1	Class I	_ist		13
3	File	Index			15
	3.1	File Lis	t		15
4	Clas	s Docu	mentation	1	17
	4.1	BlisBra	nchObject	tBilevel Class Reference	17
	4.2	BlisBra	nchObject	tInt Class Reference	17
		4.2.1	Detailed	Description	18
		4.2.2	Construc	ctor & Destructor Documentation	18
			4.2.2.1	BlisBranchObjectInt	18
			4.2.2.2	BlisBranchObjectInt	18
			4.2.2.3	BlisBranchObjectInt	19
			4.2.2.4	BlisBranchObjectInt	20
			4.2.2.5	BlisBranchObjectInt	20
			4.2.2.6	~BlisBranchObjectInt	20
		4.2.3	Member	Function Documentation	20
			4.2.3.1	operator=	20
			4.2.3.2	clone	20
			4.2.3.3	branch	20
			4.2.3.4	print	21
			4.2.3.5	getDown	21
			4.2.3.6	getUp	21
			4.2.3.7	encodeBlis	
			4.2.3.8	decodeBlis	21

iv CONTENTS

		4.2.3.9	encode	21
		4.2.3.10	decode	21
4.3	BlisBra	ınchStrate	egyBilevel Class Reference	21
	4.3.1	Detailed	Description	22
	4.3.2	Construc	ctor & Destructor Documentation	22
		4.3.2.1	BlisBranchStrategyBilevel	22
		4.3.2.2	BlisBranchStrategyBilevel	22
		4.3.2.3	~BlisBranchStrategyBilevel	22
		4.3.2.4	BlisBranchStrategyBilevel	23
	4.3.3	Member	Function Documentation	23
		4.3.3.1	clone	23
		4.3.3.2	createCandBranchObjects	23
		4.3.3.3	betterBranchObject	23
4.4	BlisBra	ınchStrate	egyMaxInf Class Reference	23
	4.4.1	Detailed	Description	24
	4.4.2	Construc	ctor & Destructor Documentation	24
		4.4.2.1	BlisBranchStrategyMaxInf	24
		4.4.2.2	BlisBranchStrategyMaxInf	24
		4.4.2.3	~BlisBranchStrategyMaxInf	24
		4.4.2.4	BlisBranchStrategyMaxInf	24
	4.4.3	Member	Function Documentation	24
		4.4.3.1	clone	24
		4.4.3.2	createCandBranchObjects	25
		4.4.3.3	betterBranchObject	25
4.5	BlisBra	ınchStrate	egyPseudo Class Reference	25
	4.5.1	Detailed	Description	26
	4.5.2	Construc	ctor & Destructor Documentation	26
		4.5.2.1	BlisBranchStrategyPseudo	26
		4.5.2.2	BlisBranchStrategyPseudo	26
		4.5.2.3	~BlisBranchStrategyPseudo	26
		4.5.2.4	BlisBranchStrategyPseudo	26
	4.5.3	Member	Function Documentation	26
		4.5.3.1	setRelibility	26
		4.5.3.2	clone	26
		4.5.3.3	betterBranchObject	26
		4.5.3.4	createCandBranchObjects	27
4.6	BlisBra	ınchStrate	egyRel Class Reference	27

CONTENTS

	4.6.1	Detailed	Description	7
	4.6.2	Construc	tor & Destructor Documentation	8
		4.6.2.1	BlisBranchStrategyRel	8
		4.6.2.2	BlisBranchStrategyRel	8
		4.6.2.3	~BlisBranchStrategyRel	8
		4.6.2.4	BlisBranchStrategyRel	8
	4.6.3	Member	Function Documentation	8
		4.6.3.1	setRelibility	8
		4.6.3.2	clone	8
		4.6.3.3	betterBranchObject	8
		4.6.3.4	createCandBranchObjects	8
4.7	BlisBra	nchStrate	gyStrong Class Reference	9
	4.7.1	Detailed	Description	9
	4.7.2	Construc	tor & Destructor Documentation	9
		4.7.2.1	BlisBranchStrategyStrong	:9
		4.7.2.2	BlisBranchStrategyStrong	:9
		4.7.2.3	~BlisBranchStrategyStrong	0
		4.7.2.4	BlisBranchStrategyStrong	0
	4.7.3	Member	Function Documentation	0
		4.7.3.1	clone	0
		4.7.3.2	createCandBranchObjects	0
		4.7.3.3	betterBranchObject	0
4.8	BlisCo	nGenerato	or Class Reference	0
	4.8.1	Detailed	Description	3
	4.8.2	Construc	tor & Destructor Documentation	3
		4.8.2.1	BlisConGenerator	3
		4.8.2.2	BlisConGenerator	3
		4.8.2.3	BlisConGenerator	3
		4.8.2.4	~BlisConGenerator	3
	4.8.3	Member	Function Documentation	3
		4.8.3.1	operator=	3
		4.8.3.2	generateConstraints	3
		4.8.3.3	getModel	4
		4.8.3.4	setName	4
		4.8.3.5	name	4
		4.8.3.6	setStrategy	4
		4.8.3.7	strategy	4

vi CONTENTS

	4.8.3.8	setCutGenerationFreq	4
	4.8.3.9	cutGenerationFreq	4
	4.8.3.10	normal	4
	4.8.3.11	setNormal	5
	4.8.3.12	atSolution	5
	4.8.3.13	setAtSolution	5
	4.8.3.14	whenInfeasible	5
	4.8.3.15	setWhenInfeasible	5
	4.8.3.16	generator	5
	4.8.3.17	numConsGenerated	5
	4.8.3.18	addNumConsGenerated	5
	4.8.3.19	numConsUsed	5
	4.8.3.20	addNumConsUsed	6
	4.8.3.21	time	6
	4.8.3.22	addTime	6
	4.8.3.23	calls	6
	4.8.3.24	addCalls	6
	4.8.3.25	noConsCalls	6
	4.8.3.26	addNoConsCalls	6
4.8.4	Member	Data Documentation	6
	4.8.4.1	model	6
	4.8.4.2	generator	7
	4.8.4.3	strategy	7
	4.8.4.4	cutGenerationFrequency	7
	4.8.4.5	name	7
	4.8.4.6	normal	7
	4.8.4.7	atSolution	
	4.8.4.8	whenInfeasible	7
	4.8.4.9	numConsGenerated	7
	4.8.4.10	numConsUsed	8
	4.8.4.11	time	8
	4.8.4.12	calls	8
	4.8.4.13	noConsCalls	8
BlisCo	nstraint Cla	ass Reference	8
4.9.1	Detailed	Description	9
4.9.2	Construc	tor & Destructor Documentation	
	4.9.2.1	BlisConstraint	9

4.9

CONTENTS vii

		4.9.2.2	BlisConstraint	 39
		4.9.2.3	BlisConstraint	 40
		4.9.2.4	BlisConstraint	 40
		4.9.2.5	~BlisConstraint	 40
		4.9.2.6	BlisConstraint	 40
	4.9.3	Member I	Function Documentation	 40
		4.9.3.1	encodeBlis	 40
		4.9.3.2	decodeBlis	 40
		4.9.3.3	createOsiRowCut	 40
		4.9.3.4	hashing	 40
		4.9.3.5	violation	 40
		4.9.3.6	encode	 40
		4.9.3.7	decode	 41
4.10	BlisHeu	ıristic Clas	ss Reference	 41
	4.10.1	Detailed I	Description	 42
	4.10.2	Construct	ctor & Destructor Documentation	 42
		4.10.2.1	BlisHeuristic	 42
		4.10.2.2	BlisHeuristic	 43
		4.10.2.3	~BlisHeuristic	 43
		4.10.2.4	BlisHeuristic	 43
	4.10.3	Member I	Function Documentation	 43
		4.10.3.1	setModel	 43
		4.10.3.2	setStrategy	 43
		4.10.3.3	setHeurCallFrequency	 43
		4.10.3.4	clone	 43
		4.10.3.5	name	 43
		4.10.3.6	addNumSolutions	 44
		4.10.3.7	numSolutions	 44
		4.10.3.8	addTime	 44
		4.10.3.9	time	 44
		4.10.3.10	addCalls	 44
		4.10.3.11	calls	 44
		4.10.3.12	2 noSolCalls	 44
		4.10.3.13	3 addNoSolCalls	 44
	4.10.4	Member I	Data Documentation	 44
		4.10.4.1	strategy	 45
		4.10.4.2	numSolutions	 45

viii CONTENTS

		4.10.4.3 tin	me			 	 	 	 		 45
		4.10.4.4 ca	alls			 	 	 	 		 45
		4.10.4.5 no	oSolsCalls			 	 	 	 		 45
4.11	BlisHeu	ırRound Clas	s Reference			 	 	 	 		 45
	4.11.1	Detailed Des	scription			 	 	 	 		 46
	4.11.2	Constructor	& Destructor	Documen	tation .	 	 	 	 		 46
		4.11.2.1 BI	lisHeurRound			 	 	 	 		 46
		4.11.2.2 BI	lisHeurRound			 	 	 	 		 46
		<b>4.11.2.3</b> ∼	BlisHeurRour	id		 	 	 	 		 46
		4.11.2.4 BI	lisHeurRound			 	 	 	 		 47
	4.11.3	Member Fur	nction Docume	entation		 	 	 	 		 47
		4.11.3.1 se	etModel			 	 	 	 		 47
	4.11.4	Member Dat	ta Documenta	tion		 	 	 	 		 47
		4.11.4.1 m	atrix			 	 	 	 		 47
		4.11.4.2 m	atrixByRow_			 	 	 	 		 47
		4.11.4.3 se	eed			 	 	 	 		 47
4.12	BlisMes	ssage Class I	Reference .			 	 	 	 		 47
	4.12.1	Detailed Des	scription			 	 	 	 		 48
4.13	BlisMod	del Class Ref	erence			 	 	 	 		 48
	4.13.1	Detailed Des	scription			 	 	 	 		 56
	4.13.2	Constructor	& Destructor	Documen	tation .	 	 	 	 		 56
		4.13.2.1 BI	lisModel			 	 	 	 		 56
		4.13.2.2 ~	BlisModel .			 	 	 	 		 56
	4.13.3	Member Fur	nction Docume	entation		 	 	 	 		 56
		4.13.3.1 cr	eateObjects			 	 	 	 		 56
		4.13.3.2 gu	utsOfDestructo	or		 	 	 	 		 56
		4.13.3.3 re	adInstance .			 	 	 	 		 57
		4.13.3.4 im	nportModel .			 	 	 	 		 57
		4.13.3.5 re	adParameters	·		 	 	 	 		 57
		4.13.3.6 w	riteParameter	s		 	 	 	 		 57
		4.13.3.7 cr	eateRoot			 	 	 	 		 57
		4.13.3.8 se	etupSelf			 	 	 	 		 57
		4.13.3.9 pr	reprocess			 	 	 	 		 57
		4.13.3.10 pc	ostprocess .			 	 	 	 		 58
		4.13.3.11 se	etSolver			 	 	 	 		 58
		4.13.3.12 ge	etSolver			 	 	 	 		 58
		4.13.3.13 sc	olver			 	 	 	 		 58

CONTENTS ix

4.13.3.14 resolve	58
4.13.3.15 setActiveNode	58
4.13.3.16 setSolEstimate	58
4.13.3.17 getNumStrong	58
4.13.3.18 addNumStrong	58
4.13.3.19 getNumBranchResolve	59
4.13.3.20 setNumBranchResolve	59
4.13.3.21 getObjCoef	59
4.13.3.22 getColLower	59
4.13.3.23 getColUpper	59
4.13.3.24 getNumCols	59
4.13.3.25 getNumRows	59
4.13.3.26 varLB	59
4.13.3.27 conLB	59
4.13.3.28 startVarLB	60
4.13.3.29 startConLB	60
4.13.3.30 tempVarLBPos	60
4.13.3.31 getLpObjValue	
4.13.3.32 getLpSolution	60
4.13.3.33 getNumSolutions	60
4.13.3.34 getNumHeurSolutions	60
4.13.3.35 incumbent	60
4.13.3.36 storeSolution	60
4.13.3.37 getCutoff	61
4.13.3.38 setCutoff	61
4.13.3.39 feasibleSolutionHeur	61
4.13.3.40 feasibleSolution	
4.13.3.41 userFeasibleSolution	61
4.13.3.42 branchStrategy	61
4.13.3.43 setBranchingMethod	61
4.13.3.44 setBranchingMethod	61
4.13.3.45 numObjects	62
4.13.3.46 setNumObjects	62
4.13.3.47 objects	62
4.13.3.48 objects	62
4.13.3.49 setSharedObjectMark	62
4.13.3.50 clearSharedObjectMark	62

x CONTENTS

4.13.3.51 deleteObjects	. 62
4.13.3.52 addObjects	. 62
4.13.3.53 createIntgerObjects	. 62
4.13.3.54 getIntObjIndices	. 63
4.13.3.55 getNumIntObjects	. 63
4.13.3.56 getIntColIndices	. 63
4.13.3.57 checkInteger	. 63
4.13.3.58 addHeuristic	. 63
4.13.3.59 heuristics	. 63
4.13.3.60 numHeuristics	. 63
4.13.3.61 addCutGenerator	. 63
4.13.3.62 addCutGenerator	. 63
4.13.3.63 cutGenerators	. 64
4.13.3.64 numCutGenerators	. 64
4.13.3.65 getMaxNumCons	. 64
4.13.3.66 setMaxNumCons	. 64
4.13.3.67 constraintPool	. 64
4.13.3.68 constraintPoolReceive	. 64
4.13.3.69 constraintPoolSend	
4.13.3.70 getNumOldConstraints	. 64
4.13.3.71 setNumOldConstraints	. 64
4.13.3.72 getOldConstraintsSize	. 65
4.13.3.73 setOldConstraintsSize	. 65
4.13.3.74 oldConstraints	. 65
4.13.3.75 setOldConstraints	. 65
4.13.3.76 delOldConstraints	. 65
4.13.3.77 getCutStrategy	. 65
4.13.3.78 setCutStrategy	. 65
4.13.3.79 getCutGenerationFrequency	. 65
4.13.3.80 setCutStrategy	. 65
4.13.3.81 getDenseConCutoff	. 66
4.13.3.82 setDenseConCutoff	. 66
4.13.3.83 getConRandoms	. 66
4.13.3.84 passInPriorities	. 66
4.13.3.85 priority	
4.13.3.86 modelLog	. 66
4.13.3.87 getNumNodes	. 66

CONTENTS xi

	4.13.3.88 getNumiterations	66
	4.13.3.89 getAveIterations	67
	4.13.3.90 addNumNodes	67
	4.13.3.91 addNumIterations	67
	4.13.3.92 blisMessageHandler	67
	4.13.3.93 blisMessages	67
	4.13.3.94 BlisPar	67
	4.13.3.95 nodeLog	67
	4.13.3.96 fathomAllNodes	67
	4.13.3.97 encodeBlis	67
	4.13.3.98 decodeBlis	68
	4.13.3.99 packSharedPseudocost	68
	4.13.3.10@packSharedConstraints	68
	4.13.3.101unpackSharedConstraints	68
	4.13.3.102packSharedVariables	68
	4.13.3.103unpackSharedVariables	68
	4.13.3.104registerKnowledge	68
	4.13.3.105encode	68
	4.13.3.10@decodeToSelf	68
	4.13.3.107packSharedKnowlege	68
	4.13.3.10&unpackSharedKnowledge	69
4.13.4	Member Data Documentation	69
	4.13.4.1 origLpSolver	69
	4.13.4.2 presolvedLpSolver	69
	4.13.4.3 lpSolver	69
	4.13.4.4 colMatrix	69
	4.13.4.5 varLB	69
	4.13.4.6 objSense	69
	4.13.4.7 numIntObjects	69
	4.13.4.8 inputVar	70
	4.13.4.9 incObjValue	70
	4.13.4.10 cutoff	
	4.13.4.11 cutofflnc	70
	4.13.4.12 branchStrategy	70
	4.13.4.13 numObjects	
	4.13.4.14 objects	
	4.13.4.15 sharedObjectMark	70

xii CONTENTS

	4.13.4.16 priority	. 70
	4.13.4.17 activeNode	. 71
	4.13.4.18 numStrong	. 71
	4.13.4.19 numBranchResolve	. 71
	4.13.4.20 numHeuristics	. 71
	4.13.4.21 heuristics	. 71
	4.13.4.22 cutStrategy	. 71
	4.13.4.23 numCutGenerators	. 71
	4.13.4.24 maxNumCons	. 71
	4.13.4.25 generators	. 71
	4.13.4.26 constraintPool	. 72
	4.13.4.27 oldConstraints	. 72
	4.13.4.28 oldConstraintsSize	. 72
	4.13.4.29 numOldConstraints	. 72
	4.13.4.30 conRandoms	. 72
	4.13.4.31 BlisPar	. 72
	4.13.4.32 blisMessageHandler	. 72
	4.13.4.33 blisMessages	. 72
	4.13.4.34 numNodes	. 72
	4.13.4.35 numlterations	. 73
	4.13.4.36 avelterations	. 73
	4.13.4.37 tempVarLBPos	. 73
	4.13.4.38 constraintPoolSend	. 73
	4.13.4.39 constraintPoolReceive	. 73
	4.13.4.40 isRoot	. 73
	4.13.4.41 boundingPass	. 73
	4.13.4.42 integerTol	. 73
	4.13.4.43 optimalRelGap	. 73
	4.13.4.44 optimalAbsGap	. 74
	4.13.4.45 currRelGap	. 74
	4.13.4.46 currAbsGap	. 74
	4.13.4.47 heurStrategy	. 74
	4.13.4.48 heurCallFrequency	. 74
	4.13.4.49 newCutPool	. 74
	4.13.4.50 leafToRootPath	. 74
4.14 B	lisNodeDesc Class Reference	. 74
4.	14.1 Detailed Description	. 75

CONTENTS xiii

4.14.2	Constructor & Destructor Documentation
	4.14.2.1 BlisNodeDesc
	4.14.2.2 BlisNodeDesc
	4.14.2.3 ~BlisNodeDesc
4.14.3	Member Function Documentation
	4.14.3.1 setBasis
	4.14.3.2 getBasis
	4.14.3.3 setBranchedDir
	4.14.3.4 getBranchedDir
	4.14.3.5 setBranchedInd
	4.14.3.6 getBranchedInd
	4.14.3.7 setBranchedVal
	4.14.3.8 getBranchedVal
	4.14.3.9 encodeBlis
	4.14.3.10 decodeBlis
	4.14.3.11 encode
	4.14.3.12 decode
4.15 BlisOb	jectInt Class Reference
4.15.1	Detailed Description
4.15.2	Constructor & Destructor Documentation
	4.15.2.1 BlisObjectInt
	4.15.2.2 BlisObjectInt
	4.15.2.3 ~BlisObjectInt
	4.15.2.4 BlisObjectInt
4.15.3	Member Function Documentation
	4.15.3.1 clone
	4.15.3.2 operator=
	4.15.3.3 infeasibility
	4.15.3.4 feasibleRegion
	4.15.3.5 createBranchObject
	4.15.3.6 preferredNewFeasible
	4.15.3.7 notPreferredNewFeasible
	4.15.3.8 resetBounds
	4.15.3.9 columnIndex
	4.15.3.10 breakEven
	4.15.3.11 setBreakEven
	4.15.3.12 pseudocost

xiv CONTENTS

	4.15.4	Member E	Data Documentation	 	 . 81
		4.15.4.1	columnIndex	 	 . 81
		4.15.4.2	originalLower	 	 . 81
		4.15.4.3	originalUpper	 	 . 81
		4.15.4.4	breakEven	 	 . 82
		4.15.4.5	pseudocost	 	 . 82
4.16	BlisPar	ams Class	Reference	 	 . 82
	4.16.1	Detailed D	Description	 	 . 83
	4.16.2	Member E	Enumeration Documentation	 	 . 83
		4.16.2.1	chrParams	 	 . 83
		4.16.2.2	intParams	 	 . 84
		4.16.2.3	dblParams	 	 . 84
		4.16.2.4	strParams	 	 . 85
		4.16.2.5	strArrayParams	 	 . 85
	4.16.3	Construct	tor & Destructor Documentation	 	 . 85
		4.16.3.1	BlisParams	 	 . 85
	4.16.4	Member F	Function Documentation	 	 . 85
		4.16.4.1	createKeywordList	 	 . 85
		4.16.4.2	setDefaultEntries	 	 . 85
		4.16.4.3	pack	 	 . 85
		4.16.4.4	unpack	 	 . 85
4.17	BlisPre	solve Class	ss Reference	 	 . 86
	4.17.1	Detailed D	Description	 	 . 86
4.18	BlisPse	eudocost C	Class Reference	 	 . 86
	4.18.1	Detailed E	Description	 	 . 87
	4.18.2	Construct	tor & Destructor Documentation	 	 . 87
		4.18.2.1	BlisPseudocost	 	 . 87
		4.18.2.2	BlisPseudocost	 	 . 87
	4.18.3	Member F	Function Documentation	 	 . 88
		4.18.3.1	setWeight	 	 . 88
		4.18.3.2	update	 	 . 88
		4.18.3.3	update	 	 . 88
		4.18.3.4	update	 	 . 88
		4.18.3.5	getUpCount	 	 . 88
		4.18.3.6	getUpCost	 	 . 88
		4.18.3.7	getDownCount	 	 . 88
		4.18.3.8	getDownCost	 	 . 88

CONTENTS xv

		4.18.3.9 getScore	38
		4.18.3.10 setScore	}9
		4.18.3.11 encodeTo	}9
		4.18.3.12 decodeFrom	}9
		4.18.3.13 encode	}9
		4.18.3.14 decode	}9
4.19	BlisSol	ution Class Reference	}9
	4.19.1	Detailed Description	)0
	4.19.2	Constructor & Destructor Documentation	)0
		4.19.2.1 BlisSolution	)0
		4.19.2.2 BlisSolution	)0
		4.19.2.3 ~BlisSolution	)0
	4.19.3	Member Function Documentation	)0
		4.19.3.1 print	)0
		4.19.3.2 encode	<del>)</del> 0
		4.19.3.3 decode	)1
4.20	BlisStro	ong Struct Reference	)1
	4.20.1	Detailed Description	)1
4.21	BlisTre	eNode Class Reference	)1
	4.21.1	Detailed Description	)2
	4.21.2	Constructor & Destructor Documentation	)2
		4.21.2.1 BlisTreeNode	)2
		4.21.2.2 BlisTreeNode	)2
		4.21.2.3 BlisTreeNode	)3
		4.21.2.4 ~BlisTreeNode	)3
	4.21.3	Member Function Documentation	)3
		4.21.3.1 init	)3
		4.21.3.2 createNewTreeNode	)3
		4.21.3.3 process	)3
		4.21.3.4 branch	)3
		4.21.3.5 selectBranchObject	)3
		4.21.3.6 chooseBranchingObject	)3
		4.21.3.7 generateConstraints	)4
		4.21.3.8 callHeuristics	)4
		4.21.3.9 getViolatedConstraints	)4
		4.21.3.10 applyConstraints	)4
		4.21.3.11 reducedCostFix	)4

xvi CONTENTS

	4.21.3.12 encode	94
	4.21.3.13 decode	94
4.22 BlisVa	riable Class Reference	94
4.22.1	Detailed Description	95
4.22.2	Member Function Documentation	95
	4.22.2.1 encodeBlis	95
	4.22.2.2 decodeBlis	95
	4.22.2.3 encode	95
	4.22.2.4 decode	96
Index		97

## Chapter 1

## **Hierarchical Index**

### 1.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

```
_EKKfactinfo[external]
AbcDualRowPivot[external]
  AbcDualRowDantzig[external]
  AbcDualRowSteepest[external]
AbcMatrix[external]
AbcMatrix2[external]
AbcMatrix3[external]
AbcNonLinearCost[external]
AbcPrimalColumnPivot[external]
  AbcPrimalColumnDantzig[external]
  AbcPrimalColumnSteepest [external]
AbcSimplexFactorization[external]
AbcTolerancesEtc [external]
AbcWarmStartOrganizer[external]
forcing constraint action::action[external]
doubleton_action::action[external]
tripleton action::action[external]
remove_fixed_action::action[external]
std::allocator< T >
ALPS_PS_STATS[external]
AlpsEncoded[external]
AlpsKnowledge[external]
  AlpsModel[external]
    BcpsModel[external]
      AlpsSolution[external]
    BcpsSolution[external]
      AlpsSubTree[external]
    BcpsSubTree[external]
  AlpsTreeNode[external]
    BcpsTreeNode[external]
```

2 Hierarchical Index

BcpsObject[external]
<pre>BcpsConstraint[external]</pre>
BlisConstraint
BcpsVariable [external]
BlisVariable
BlisObjectInt
BlisPseudocost
AlpsKnowledgeBroker[external]
AlpsKnowledgeBrokerMPI[external]
AlpsKnowledgeBrokerSerial [external]
AlpsKnowledgePool[external]
AlpsNodePool[external]
AlpsSolutionPool[external]
AlpsSubTreePool[external]
BcpsObjectPool[external]
BcpsConstraintPool[external]
BcpsVariablePool[external]
AlpsNodeDesc[external]
BcpsNodeDesc[external]
BlisNodeDesc
AlpsNodeSelection [external]
AlpsNodeSelectionBest [external]
AlpsNodeSelectionBreadth[external]
AlpsNodeSelectionDepth [external]
AlpsNodeSelectionEstimate[external]
AlpsNodeSelectionHybrid[external]
AlpsParameter[external]
AlpsParameterSet[external]
AlpsParams[external]
·
BlisParams
AlpsPriorityQueue< AlpsSubTree * > [external]
AlpsPriorityQueue< AlpsTreeNode * > [external]
AlpsStrLess[external]
AlpsTimer[external]
AlpsTreeSelection[external]
AlpsTreeSelection[external]
AlpsTreeSelectionBreadth [external]
AlpsTreeSelectionDepth[external]
AlpsTreeSelectionEstimate [external]
ampl info[external]
OsiSolverInterface::ApplyCutsReturnCode[external]
std::array< T >
std::auto_ptr< T >
<pre>auxiliary_graph[external]</pre>
std::basic_string< Char >
std::string
std::wstring
std::basic_string< char >
std::basic_string< wchar_t >
BcpsBranchObject[external]
BlisBranchObjectBilevel
·
BlisBranchObjectInt
BcpsBranchStrategy [external]

1.1 Class Hierarchy 3

BlisBranchStrategyBilevel
BlisBranchStrategyMaxInf
BlisBranchStrategyPseudo
BlisBranchStrategyRel
BlisBranchStrategyStrong
BcpsFieldListMod< T > [external]
BcpsFieldListMod double > [external]
BcpsFieldListMod <int>[external]</int>
BcpsObjectListMod [external]
std::bitset < Bits >
BitVector128[external]
BlisConGenerator
BlisHeuristic
BlisHeurRound
BlisStrong
<pre>blockStruct[external]</pre>
<pre>blockStruct3[external]</pre>
<pre>ClpNode::branchState[external]</pre>
CbcOrClpParam[external]
Cgl012Cut[external]
<pre>cgl_arc[external]</pre>
<pre>cgl_graph[external]</pre>
<pre>cgl_node[external]</pre>
Cg/BK[external]
CglCutGenerator[external]
CglAllDifferent[external]
Cg Clique[external]
CglFakeClique[external]
Cg DuplicateRow[external]
Cg FlowCover[external]
Cg GM [external]
Cg Gomory[external]
Cg Implication[external]
Cg KnapsackCover[external]
Cg LandP[external]
Cg LiftAndProject[external]
CglMixedIntegerRounding [external]
CglMixedIntegerRounding2[external]
Cg OddHole [external]
Cg Probing[external]
CglRedSplit[external]
CglRedSplit2[external]
CglResidualCapacity[external]
Cg SimpleRounding[external]
Cg Stored [external]
CglTwomir[external]
CglZeroHalf[external]
CglFlowVUB[external]
CglHashLink[external]
LAP::CglLandPSimplex[external]
CglMixIntRoundVUB[external]
CglMixIntRoundVUB2[external]
Cg Param[external]
CglGMlParam[external]
Ogiciini didii  Ealelial

4 Hierarchical Index

```
CglLandP::Parameters [external]
  CglRedSplit2Param[external]
   CglRedSplitParam [external]
CglPreProcess [external]
CglTreeInfo[external]
   CglTreeProbingInfo[external]
CglUniqueRowCuts[external]
CliqueEntry [external]
CglProbing::CliqueType [external]
ClpCholeskyBase[external]
   ClpCholeskyDense[external]
   ClpCholeskyMumps[external]
  ClpCholeskyTaucs[external]
  ClpCholeskyUfl[external]
  ClpCholeskyWssmp[external]
   ClpCholeskyWssmpKKT[external]
ClpCholeskyDenseC[external]
ClpConstraint[external]
   ClpConstraintLinear[external]
   ClpConstraintQuadratic[external]
ClpDataSave[external]
ClpDisasterHandler[external]
   OsiClpDisasterHandler[external]
ClpDualRowPivot[external]
   ClpDualRowDantzig[external]
   ClpDualRowSteepest [external]
ClpEventHandler[external]
  MyEventHandler[external]
ClpFactorization[external]
ClpHashValue[external]
ClpLsqr[external]
ClpMatrixBase [external]
   ClpDummyMatrix[external]
   ClpNetworkMatrix[external]
   ClpPackedMatrix[external]
     ClpDynamicMatrix[external]
        ClpDynamicExampleMatrix [external]
     ClpGubMatrix[external]
        ClpGubDynamicMatrix[external]
   ClpPlusMinusOneMatrix [external]
ClpModel[external]
   ClpInterior[external]
     ClpPdco[external]
     ClpPredictorCorrector[external]
  ClpSimplex[external]
     AbcSimplex[external]
        AbcSimplexDual[external]
        AbcSimplexPrimal[external]
     ClpSimplexDual[external]
     ClpSimplexOther[external]
     ClpSimplexPrimal[external]
        ClpSimplexNonlinear[external]
ClpNetworkBasis [external]
ClpNode[external]
```

1.1 Class Hierarchy 5

```
ClpNodeStuff[external]
ClpNonLinearCost [external]
ClpObjective [external]
   ClpLinearObjective [external]
   ClpQuadraticObjective [external]
ClpPackedMatrix2[external]
ClpPackedMatrix3[external]
ClpPdcoBase[external]
ClpPresolve[external]
ClpPrimalColumnPivot[external]
   ClpPrimalColumnDantzig[external]
   ClpPrimalColumnSteepest[external]
   ClpPrimalQuadraticDantzig[external]
ClpSimplexProgress [external]
ClpSolve [external]
ClpTrustedData[external]
CoinAbcAnyFactorization[external]
   CoinAbcDenseFactorization [external]
   CoinAbcTypeFactorization [external]
CoinAbcStack[external]
CoinAbcStatistics [external]
CoinAbsFltEq[external]
CoinArrayWithLength [external]
   CoinArbitraryArrayWithLength [external]
   CoinBigIndexArrayWithLength [external]
   CoinDoubleArrayWithLength [external]
   CoinFactorizationDoubleArrayWithLength[external]
   CoinFactorizationLongDoubleArrayWithLength[external]
   CoinIntArrayWithLength [external]
   CoinUnsignedIntArrayWithLength [external]
   CoinVoidStarArrayWithLength [external]
CoinBaseModel[external]
   CoinModel[external]
   CoinStructuredModel[external]
CoinBuild[external]
CoinDenseVector< T > [external]
CoinError[external]
   CglLandP::NoBasisError[external]
   CglLandP::SimplexInterfaceError[external]
CoinExternalVectorFirstGreater 2< class, class, class > [external]
CoinExternalVectorFirstGreater_3 < class, class, class, class > [external]
CoinExternalVectorFirstLess 2< class, class, class > [external]
CoinExternalVectorFirstLess 3< class, class, class, class > [external]
CoinFactorization [external]
CoinFileIOBase [external]
   CoinFileInput[external]
   CoinFileOutput[external]
CoinFirstAbsGreater 2< class, class > [external]
CoinFirstAbsGreater 3< class, class, class > [external]
CoinFirstAbsLess_2< class, class > [external]
CoinFirstAbsLess 3 < class, class, class > [external]
CoinFirstGreater_2< class, class > [external]
CoinFirstGreater 3< class, class, class > [external]
CoinFirstLess 2< class, class > [external]
```

6 Hierarchical Index

```
CoinFirstLess_3 < class, class, class > [external]
ClpHashValue::CoinHashLink[external]
CoinLplO::CoinHashLink[external]
CoinMpsIO::CoinHashLink[external]
CoinIndexedVector[external]
   CoinPartitionedVector[external]
  LAP::TabRow[external]
CoinLplO [external]
CoinMessageHandler[external]
   MyMessageHandler[external]
CoinMessages[external]
  AlpsMessage[external]
   BcpsMessage[external]
  BlisMessage . . . . . . .
                         CglMessage[external]
  ClpMessage[external]
  CoinMessage[external]
  LAP::LandPMessages [external]
  LAP::LapMessages [external]
CoinModelHash[external]
CoinModelHash2[external]
CoinModelHashLink[external]
CoinModelInfo2[external]
CoinModelLink[external]
CoinModelLinkedList[external]
CoinModelTriple [external]
CoinMpsCardReader[external]
CoinMpsIO[external]
CoinOneMessage [external]
CoinOtherFactorization [external]
   CoinDenseFactorization[external]
   CoinOslFactorization [external]
   CoinSimpFactorization[external]
CoinPackedMatrix[external]
CoinPackedVectorBase [external]
   CoinPackedVector[external]
   CoinShallowPackedVector[external]
CoinPair< S, T > [external]
CoinParam [external]
CoinPrePostsolveMatrix [external]
   CoinPostsolveMatrix[external]
   CoinPresolveMatrix [external]
CoinPresolveAction [external]
  do tighten_action[external]
  doubleton_action[external]
  drop_empty_cols_action[external]
  drop_empty_rows_action[external]
  drop zero coefficients action[external]
  dupcol_action[external]
  duprow3 action[external]
  duprow_action[external]
  forcing constraint action[external]
  gubrow action[external]
  implied free action[external]
```

1.1 Class Hierarchy 7

```
isolated_constraint_action[external]
   make fixed action[external]
   remove dual action[external]
   remove fixed action[external]
  slack_doubleton_action[external]
   slack singleton action[external]
   subst constraint action[external]
  tripleton action[external]
  twoxtwo action[external]
   useless_constraint_action[external]
CoinPresolveMonitor[external]
CoinRational [external]
CoinRelFltEq[external]
CoinSearchTreeBase [external]
   CoinSearchTree < class > [external]
CoinSearchTreeCompareBest[external]
CoinSearchTreeCompareBreadth [external]
CoinSearchTreeCompareDepth [external]
CoinSearchTreeComparePreferred[external]
CoinSearchTreeManager[external]
CoinSet[external]
   CoinSosSet[external]
CoinSnapshot[external]
CoinThreadRandom[external]
CoinTimer[external]
CoinTreeNode[external]
CoinTreeSiblings [external]
CoinTriple < S, T, U > [external]
CoinWarmStart[external]
   CoinWarmStartBasis [external]
      AbcWarmStart[external]
   CoinWarmStartDual[external]
   CoinWarmStartPrimalDual[external]
   CoinWarmStartVector < T > [external]
   CoinWarmStartVector< double > [external]
   CoinWarmStartVector < U > [external]
   CoinWarmStartVectorPair< T, U > [external]
CoinWarmStartDiff[external]
   CoinWarmStartBasisDiff[external]
   CoinWarmStartDualDiff[external]
   CoinWarmStartPrimalDualDiff[external]
   CoinWarmStartVectorDiff < T > [external]
   CoinWarmStartVectorDiff< double > [external]
   CoinWarmStartVectorDiff< U > [external]
   CoinWarmStartVectorPairDiff< T, U > [external]
CoinYacc[external]
std::complex
std::vector< T >::const iterator
std::forward list< T >::const iterator
std::unordered_multimap< K, T >::const_iterator
std::list< T >::const iterator
std::unordered multiset< K >::const iterator
std::multiset < K >::const iterator
std::wstring::const iterator
```

8 Hierarchical Index

```
OsiCuts::const_iterator[external]
std::multimap< K, T >::const iterator
std::basic string< Char >::const iterator
std::string::const iterator
std::deque\!<\mathsf{T}>::const\_iterator
std::map < K, T >::const iterator
std::unordered map< K, T>::const iterator
std::set< K >::const iterator
std::unordered set< K >::const iterator
std::wstring::const_reverse_iterator
std::deque< T >::const_reverse_iterator
std::unordered_set< K >::const_reverse_iterator
std::vector< T >::const reverse iterator
std::basic_string< Char >::const_reverse_iterator
std::map < K, T >::const reverse iterator
std::string::const_reverse_iterator
std::unordered map< K, T>::const reverse iterator
std::list< T >::const_reverse_iterator
std::forward list< T >::const reverse iterator
std::multimap< K, T >::const reverse iterator
std::unordered multimap< K, T >::const reverse iterator
std::set < K >::const reverse iterator
std::multiset< K >::const reverse iterator
std::unordered multiset< K >::const reverse iterator
cut[external]
cut list[external]
cutParams[external]
LAP::Cuts[external]
cycle[external]
cycle_list[external]
DeletePtrObject[external]
std::deque < T >
std::deque< int >
std::deque < StdVectorDouble >
DGG_constraint_t[external]
DGG data t[external]
DGG list t[external]
disaggregationAction [external]
dropped zero[external]
dualColumnResult[external]
edge[external]
EKKHlink[external]
std::error category
std::error code
std::error_condition
std::exception
   std::bad_alloc
   std::bad cast
   std::bad exception
   std::bad_typeid
   std::ios base::failure
   std::logic_error
      std::domain error
      std::invalid argument
```

1.1 Class Hierarchy 9

```
std::length_error
      std::out of range
   std::runtime error
      std::overflow error
      std::range_error
      std::underflow error
FactorPointers[external]
std::forward list< T >
glp prob[external]
Idiot[external]
IdiotResult[external]
ilp[external]
Info[external]
info_weak[external]
std::ios base
   basic_ios < char >
   basic_ios< wchar_t >
   std::basic_ios
      basic istream < char >
      basic istream< wchar t >
      basic ostream < char >
      basic_ostream< wchar_t >
      std::basic_istream
          basic ifstream < char >
          basic ifstream< wchar t >
          basic iostream < char >
          basic_iostream< wchar_t >
          basic_istringstream< char >
          basic_istringstream< wchar_t >
          std::basic_ifstream
             std::ifstream
             std::wifstream
          std::basic_iostream
             basic fstream < char >
             basic_fstream< wchar_t >
             basic stringstream < char >
             basic_stringstream< wchar_t >
             std::basic fstream
                 std::fstream
                 std::wfstream
             std::basic_stringstream
                 std::stringstream
                 std::wstringstream
          std::basic_istringstream
             std::istringstream
             std::wistringstream
          std::istream
          std::wistream
      std::basic ostream
          basic_iostream< char >
          basic_iostream< wchar_t >
          basic_ofstream < char >
          basic ofstream< wchar t>
          basic_ostringstream< char >
```

10 Hierarchical Index

```
basic_ostringstream< wchar_t >
         std::basic iostream
         std::basic ofstream
             std::ofstream
             std::wofstream
         std::basic ostringstream
             std::ostringstream
             std::wostringstream
         std::ostream
         std::wostream
      std::ios
      std::wios
std::unordered set< K >::iterator
std::deque< T >::iterator
OsiCuts::iterator[external]
std::unordered_multiset< K >::iterator
std::set< K >::iterator
std::vector< T >::iterator
std::wstring::iterator
std::list< T >::iterator
std::unordered map< K, T >::iterator
std::map{<}\ K,\ T>::iterator
std::unordered_multimap< K, T >::iterator
std::multimap< K, T >::iterator
std::forward list< T >::iterator
std::string::iterator
std::basic string< Char >::iterator
std::multiset< K >::iterator
std::list < T >
log_var[external]
std::map< K, T>
std::map < AlpsKnowledgeType, AlpsKnowledgePool * >
std::multimap< K, T>
std::multiset< K >
Options[external]
OsiAuxInfo [external]
   OsiBabSolver[external]
OsiBranchingInformation [external]
OsiBranchingObject[external]
   OsiTwoWayBranchingObject[external]
      OsiIntegerBranchingObject[external]
      OsiLotsizeBranchingObject [external]
      OsiSOSBranchingObject[external]
OsiChooseVariable [external]
   OsiChooseStrong[external]
OsiCut[external]
   OsiColCut[external]
   OsiRowCut[external]
      OsiRowCut2[external]
OsiCuts[external]
OsiHotInfo[external]
OsiObject[external]
   OsiObject2[external]
      OsiLotsize [external]
```

1.1 Class Hierarchy 11

```
OsiSimpleInteger[external]
      OsiSOS[external]
OsiPresolve [external]
   BlisPresolve . . . . . . . . . . . . . . . . . .
OsiPseudoCosts [external]
OsiRowCutDebugger[external]
OsiSolverBranch [external]
OsiSolverInterface [external]
   OsiClpSolverInterface [external]
   OsiCpxSolverInterface [external]
   OsiGlpkSolverInterface [external]
   OsiGrbSolverInterface [external]
   OsiMskSolverInterface[external]
   OsiSpxSolverInterface [external]
   OsiXprSolverInterface [external]
OsiSolverResult[external]
Outfo[external]
ClpSimplexOther::parametricsData[external]
parity ilp[external]
AbcSimplexPrimal::pivotStruct[external]
pool_cut[external]
pool_cut_list[external]
presolvehlink[external]
std::priority queue < T >
std::queue < T >
Coin::ReferencedObject[external]
std::basic_string< Char >::reverse_iterator
std::multiset < K >::reverse_iterator
std::forward list< T >::reverse iterator
std::set< K >::reverse iterator
std::unordered map< K, T>::reverse iterator
std::unordered_multimap< K, T >::reverse_iterator
std::deque< T >::reverse iterator
std::wstring::reverse_iterator
std::string::reverse iterator
std::map < K, T >::reverse iterator
std::unordered multiset< K >::reverse iterator
std::list< T >::reverse_iterator
std::vector< T >::reverse_iterator
std::unordered set< K >::reverse iterator
std::multimap< K, T >::reverse iterator
scatterStruct[external]
select_cut[external]
separation_graph[external]
std::set< K >
short_path_node[external]
std::smart ptr< T >
Coin::SmartPtr< T > [external]
std::stack< T >
symrec[external]
std::system_error
OsiUnitTest::TestOutcome [external]
OsiUnitTest::TestOutcomes [external]
std::thread
```

12 Hierarchical Index

```
TotalWorkload [external]
std::unique_ptr< T >
std::unordered_map< K, T >
std::unordered_multimap< K, T>
std::unordered_multiset < K >
std::unordered_set< K>
std::valarray< T >
LAP::Validator[external]
std::vector< T >
std::vector< AlpsTreeNode * >
std::vector< BcpsConstraint *>
{\it std::} {\it vector} {\it <} \, {\it BcpsVariable} \, * \, {\it >} \,
std::vector< ColumnSelectionStrategy >
std::vector< double >
std::vector< int >
{\it std::} {\it vector} {\it <} \, {\it RowSelectionStrategy} >
std::vector< std::pair< std::string, AlpsParameter >>
std::vector< std::string >
std::weak_ptr< T >
Κ
S
Τ
U
```

# **Chapter 2**

# **Class Index**

### 2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:	
BlisBranchObjectBilevel	17
BlisBranchObjectInt	17
BlisBranchStrategyBilevel	
This class implements maximum infeasibility branching	21
BlisBranchStrategyMaxInf	
This class implements maximum infeasibility branching	23
BlisBranchStrategyPseudo	
Blis branching strategy	25
BlisBranchStrategyRel	
Blis branching strategy	27
BlisBranchStrategyStrong	
This class implements strong branching	29
BlisConGenerator	
Interface between Blis and Cut Generation Library	30
BlisConstraint	38
BlisHeuristic	
Heuristic base class	41
BlisHeurRound	
Rounding Heuristic	45
BlisMessage	47
BlisModel	48
BlisNodeDesc	74
BlisObjectInt	77
BlisParams	82
BlisPresolve	
A interface to Osi/Coin Presolve	86
BlisPseudocost	86
BlisSolution	
This class contains the solutions generated by the LP solver (either primal or dual	89
BlisStrong	91
BlisTreeNode	
This is the class in which we are finally able to concretely define the bounding procedure $\dots \dots$	91

14 **Class Index** 

# **Chapter 3**

# File Index

### 3.1 File List

Here is a list of all documented files with brief descriptions:

lis.h	??
lisBranchObjectBilevel.h	??
lisBranchObjectInt.h	??
lisBranchStrategyBilevel.h	??
lisBranchStrategyMaxInf.h	??
lisBranchStrategyPseudo.h	??
lisBranchStrategyRel.h	??
lisBranchStrategyStrong.h	??
lisConfig.h	??
lisConGenerator.h	??
lisConstraint.h	??
lisHelp.h	??
lisHeuristic.h	??
lisHeurRound.h	??
lisLicense.h	??
lisMessage.h	??
lisModel.h	??
lisNodeDesc.h	??
lisObjectInt.h	??
lisParams.h	??
lisPresolve.h	??
lisPseudo.h	??
lisSolution.h	??
lisSubTree.h	??
lisTreeNode.h	??
lisVariable.h	??
onfig_blis_default.h	
onfig default.h	0.0

16 File Index

## Chapter 4

## **Class Documentation**

### 4.1 BlisBranchObjectBilevel Class Reference

Inheritance diagram for BlisBranchObjectBilevel:

### 4.2 BlisBranchObjectInt Class Reference

Inheritance diagram for BlisBranchObjectInt:

Collaboration diagram for BlisBranchObjectInt:

#### **Public Member Functions**

• BlisBranchObjectInt ()

Default constructor.

• BlisBranchObjectInt (BlisModel \*model, int varInd, int direction, double value)

Construct a branching object, which branching on variable varInd.

• BlisBranchObjectInt (BlisModel \*model, int varInd, int intScore, double dblScore, int direction, double value)

Construct a branching object, which branching on variable varInd.

• BlisBranchObjectInt (BlisModel \*model, int varInd, int direction, double lowerValue, double upperValue)

Create a degenerate branching object.

• BlisBranchObjectInt (const BlisBranchObjectInt &)

Copy constructor.

• BlisBranchObjectInt & operator= (const BlisBranchObjectInt &rhs)

Assignment operator.

virtual BcpsBranchObject \* clone () const

Clone.

virtual ∼BlisBranchObjectInt ()

Destructor.

• virtual double branch (bool normalBranch=false)

Set the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

virtual void print (bool normalBranch)

Print something about branch - only if log level high.

18 Class Documentation

const double \* getDown () const

Get down arm bounds.

const double \* getUp () const

Get upper arm bounds.

virtual AlpsReturnStatus encode (AlpsEncoded \*encoded) const

Pack to an encoded object.

virtual AlpsReturnStatus decode (AlpsEncoded &encoded)

Unpack a branching object from an encoded object.

#### **Protected Member Functions**

• AlpsReturnStatus encodeBlis (AlpsEncoded \*encoded) const

Pack Blis portion to an encoded object.

AlpsReturnStatus decodeBlis (AlpsEncoded &encoded)

Unpack Blis portion from an encoded object.

#### **Protected Attributes**

• double down\_ [2]

Down\_[0]: the lower bound of down arm; Down\_[1]: the upper bound of down arm;.

double up\_ [2]

Up\_[0]: the lower bound of upper arm; Up\_[1]: the upper bound of upper arm;.

### 4.2.1 Detailed Description

Definition at line 38 of file BlisBranchObjectInt.h.

### 4.2.2 Constructor & Destructor Documentation

4.2.2.1 BlisBranchObjectInt::BlisBranchObjectInt() [inline]

Default constructor.

Definition at line 53 of file BlisBranchObjectInt.h.

4.2.2.2 BlisBranchObjectInt::BlisBranchObjectInt (BlisModel \* model, int varInd, int direction, double value) [inline]

Construct a branching object, which branching on variable varInd.

### **Parameters**

	varInd	the index of integer variable in object set
di	irection	the direction of first branching: 1(up), -1(down)
	value	the fractional solution value of variable varInd

Definition at line 69 of file BlisBranchObjectInt.h.

4.2.2.3 BlisBranchObjectInt::BlisBranchObjectInt ( BlisModel \* model, int varInd, int intScore, double dblScore, int direction, double value ) [inline]

Construct a branching object, which branching on variable varInd.

20 Class Documentation

#### **Parameters**

varInd	the index of integer variable in object set
intScore	the integer score/goodness
dblScore	the double score/goodness
direction	the direction of first branching: 1(up), -1(down)
value	the fractional solution value of variable varInd

Definition at line 91 of file BlisBranchObjectInt.h.

4.2.2.4 BlisBranchObjectInt::BlisBranchObjectInt ( BlisModel \* model, int varInd, int direction, double lowerValue, double upperValue ) [inline]

Create a degenerate branching object.

Specifies a 'one-direction branch'. Calling branch() for this object will always result in lowerValue  $\leq$  x  $\leq$  upperValue. Used to fix a variable when lowerValue = upperValue.

Definition at line 113 of file BlisBranchObjectInt.h.

4.2.2.5 BlisBranchObjectInt::BlisBranchObjectInt ( const BlisBranchObjectInt & )

Copy constructor.

**4.2.2.6** virtual BlisBranchObjectInt::~BlisBranchObjectInt() [inline], [virtual]

Destructor.

Definition at line 141 of file BlisBranchObjectInt.h.

- 4.2.3 Member Function Documentation
- 4.2.3.1 BlisBranchObjectInt& BlisBranchObjectInt: operator= ( const BlisBranchObjectInt & rhs )

Assignment operator.

4.2.3.2 virtual BcpsBranchObject\* BlisBranchObjectInt::clone( ) const [inline], [virtual]

Clone.

Implements BcpsBranchObject.

Definition at line 136 of file BlisBranchObjectInt.h.

4.2.3.3 virtual double BlisBranchObjectInt::branch ( bool normalBranch = false ) [virtual]

Set the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

Returns change in guessed objective on next branch.

Implements BcpsBranchObject.

**4.2.3.4** virtual void BlisBranchObjectInt::print ( bool normalBranch ) [virtual]

Print something about branch - only if log level high.

Reimplemented from BcpsBranchObject.

4.2.3.5 const double\* BlisBranchObjectInt::getDown() const [inline]

Get down arm bounds.

Definition at line 152 of file BlisBranchObjectInt.h.

4.2.3.6 const double\* BlisBranchObjectInt::getUp ( ) const [inline]

Get upper arm bounds.

Definition at line 155 of file BlisBranchObjectInt.h.

4.2.3.7 AlpsReturnStatus BlisBranchObjectInt::encodeBlis ( AlpsEncoded \* encoded ) const [inline], [protected]

Pack Blis portion to an encoded object.

Definition at line 160 of file BlisBranchObjectInt.h.

4.2.3.8 AlpsReturnStatus BlisBranchObjectInt::decodeBlis ( AlpsEncoded & encoded ) [inline], [protected]

Unpack Blis portion from an encoded object.

Definition at line 176 of file BlisBranchObjectInt.h.

**4.2.3.9** virtual AlpsReturnStatus BlisBranchObjectInt::encode ( AlpsEncoded \* encoded ) const [inline], [virtual]

Pack to an encoded object.

Reimplemented from BcpsBranchObject.

Definition at line 193 of file BlisBranchObjectInt.h.

4.2.3.10 virtual AlpsReturnStatus BlisBranchObjectInt::decode ( AlpsEncoded & encoded ) [inline], [virtual]

Unpack a branching object from an encoded object.

Reimplemented from BcpsBranchObject.

Definition at line 203 of file BlisBranchObjectInt.h.

The documentation for this class was generated from the following file:

· BlisBranchObjectInt.h

# 4.3 BlisBranchStrategyBilevel Class Reference

This class implements maximum infeasibility branching.

```
#include <BlisBranchStrategyBilevel.h>
```

Inheritance diagram for BlisBranchStrategyBilevel:

Collaboration diagram for BlisBranchStrategyBilevel:

#### **Public Member Functions**

• BlisBranchStrategyBilevel ()

Bilevel Constructor.

BlisBranchStrategyBilevel (BlisModel \*model)

Bilevel Constructor.

virtual ∼BlisBranchStrategyBilevel ()

Destructor.

BlisBranchStrategyBilevel (const BlisBranchStrategyBilevel &)

Copy constructor.

virtual BcpsBranchStrategy \* clone () const

Clone a brancing strategy.

virtual int createCandBranchObjects (int numPassesLeft, double ub)

Create a set of candidate branching objects.

virtual int betterBranchObject (BcpsBranchObject \*thisOne, BcpsBranchObject \*bestSoFar)

Compare branching object thisOne to bestSoFar.

## 4.3.1 Detailed Description

This class implements maximum infeasibility branching.

Definition at line 32 of file BlisBranchStrategyBilevel.h.

### 4.3.2 Constructor & Destructor Documentation

4.3.2.1 BlisBranchStrategyBilevel::BlisBranchStrategyBilevel() [inline]

Bilevel Constructor.

Definition at line 42 of file BlisBranchStrategyBilevel.h.

4.3.2.2 BlisBranchStrategyBilevel::BlisBranchStrategyBilevel ( BlisModel \* model ) [inline]

Bilevel Constructor.

Definition at line 47 of file BlisBranchStrategyBilevel.h.

**4.3.2.3** virtual BlisBranchStrategyBilevel::~BlisBranchStrategyBilevel() [inline],[virtual]

Destructor.

Definition at line 52 of file BlisBranchStrategyBilevel.h.

4.3.2.4 BlisBranchStrategyBilevel::BlisBranchStrategyBilevel (const BlisBranchStrategyBilevel & )

Copy constructor.

### 4.3.3 Member Function Documentation

4.3.3.1 virtual BcpsBranchStrategy\* BlisBranchStrategyBilevel::clone() const [inline], [virtual]

Clone a brancing strategy.

Implements BcpsBranchStrategy.

Definition at line 58 of file BlisBranchStrategyBilevel.h.

4.3.3.2 virtual int BlisBranchStrategyBilevel::createCandBranchObjects (int numPassesLeft, double ub) [virtual]

Create a set of candidate branching objects.

Reimplemented from BcpsBranchStrategy.

4.3.3.3 virtual int BlisBranchStrategyBilevel::betterBranchObject ( BcpsBranchObject \* thisOne, BcpsBranchObject \* bestSoFar ) [virtual]

Compare branching object thisOne to bestSoFar.

If thisOne is better than bestObject, return branching direction(1 or -1), otherwise return 0. If bestSorFar is NULL, then always return branching direction(1 or -1).

Implements BcpsBranchStrategy.

The documentation for this class was generated from the following file:

· BlisBranchStrategyBilevel.h

# 4.4 BlisBranchStrategyMaxInf Class Reference

This class implements maximum infeasibility branching.

#include <BlisBranchStrategyMaxInf.h>

Inheritance diagram for BlisBranchStrategyMaxInf:

Collaboration diagram for BlisBranchStrategyMaxInf:

## **Public Member Functions**

• BlisBranchStrategyMaxInf ()

MaxInf Constructor.

BlisBranchStrategyMaxInf (BlisModel \*model)

MaxInf Constructor.

virtual ∼BlisBranchStrategyMaxInf ()

Destructor.

BlisBranchStrategyMaxInf (const BlisBranchStrategyMaxInf &)

Copy constructor.

virtual BcpsBranchStrategy \* clone () const

Clone a brancing strategy.

virtual int createCandBranchObjects (int numPassesLeft, double ub)

Create a set of candidate branching objects.

virtual int betterBranchObject (BcpsBranchObject \*thisOne, BcpsBranchObject \*bestSoFar)

Compare branching object thisOne to bestSoFar.

## 4.4.1 Detailed Description

This class implements maximum infeasibility branching.

Definition at line 32 of file BlisBranchStrategyMaxInf.h.

### 4.4.2 Constructor & Destructor Documentation

**4.4.2.1** BlisBranchStrategyMaxInf::BlisBranchStrategyMaxInf() [inline]

MaxInf Constructor.

Definition at line 42 of file BlisBranchStrategyMaxInf.h.

4.4.2.2 BlisBranchStrategyMaxInf::BlisBranchStrategyMaxInf(BlisModel\*model) [inline]

MaxInf Constructor.

Definition at line 47 of file BlisBranchStrategyMaxInf.h.

4.4.2.3 virtual BlisBranchStrategyMaxInf::~BlisBranchStrategyMaxInf() [inline], [virtual]

Destructor.

Definition at line 52 of file BlisBranchStrategyMaxInf.h.

4.4.2.4 BlisBranchStrategyMaxInf::BlisBranchStrategyMaxInf (const BlisBranchStrategyMaxInf & )

Copy constructor.

### 4.4.3 Member Function Documentation

4.4.3.1 virtual BcpsBranchStrategy\* BlisBranchStrategyMaxInf::clone() const [inline], [virtual]

Clone a brancing strategy.

Implements BcpsBranchStrategy.

Definition at line 58 of file BlisBranchStrategyMaxInf.h.

4.4.3.2 virtual int BlisBranchStrategyMaxInf::createCandBranchObjects (int numPassesLeft, double ub) [virtual]

Create a set of candidate branching objects.

Reimplemented from BcpsBranchStrategy.

4.4.3.3 virtual int BlisBranchStrategyMaxInf::betterBranchObject ( BcpsBranchObject \* thisOne, BcpsBranchObject \* bestSoFar ) [virtual]

Compare branching object thisOne to bestSoFar.

If thisOne is better than bestObject, return branching direction(1 or -1), otherwise return 0. If bestSorFar is NULL, then always return branching direction(1 or -1).

Implements BcpsBranchStrategy.

The documentation for this class was generated from the following file:

· BlisBranchStrategyMaxInf.h

# 4.5 BlisBranchStrategyPseudo Class Reference

Blis branching strategy.

#include <BlisBranchStrategyPseudo.h>

Inheritance diagram for BlisBranchStrategyPseudo:

Collaboration diagram for BlisBranchStrategyPseudo:

### **Public Member Functions**

BlisBranchStrategyPseudo ()

Default Constructor.

• BlisBranchStrategyPseudo (BlisModel \*model, int rel)

Useful Constructor.

virtual ∼BlisBranchStrategyPseudo ()

Destructor.

• BlisBranchStrategyPseudo (const BlisBranchStrategyPseudo &)

Copy constructor.

void setRelibility (int rel)

Set relibility.

virtual BcpsBranchStrategy \* clone () const

Clone a brancing strategy.

virtual int betterBranchObject (BcpsBranchObject \*thisOne, BcpsBranchObject \*bestSoFar)

Compare branching object thisOne to bestSoFar.

• int createCandBranchObjects (int numPassesLeft, double ub)

Create a set of candidate branching objects.

## 4.5.1 Detailed Description

Blis branching strategy.

This class implements pseudocost branching.

Definition at line 40 of file BlisBranchStrategyPseudo.h.

### 4.5.2 Constructor & Destructor Documentation

4.5.2.1 BlisBranchStrategyPseudo::BlisBranchStrategyPseudo( ) [inline]

Default Constructor.

Definition at line 51 of file BlisBranchStrategyPseudo.h.

4.5.2.2 BlisBranchStrategyPseudo::BlisBranchStrategyPseudo (BlisModel \* model, int rel ) [inline]

Useful Constructor.

Definition at line 57 of file BlisBranchStrategyPseudo.h.

4.5.2.3 virtual BlisBranchStrategyPseudo::~BlisBranchStrategyPseudo() [inline], [virtual]

Destructor.

Definition at line 64 of file BlisBranchStrategyPseudo.h.

4.5.2.4 BlisBranchStrategyPseudo::BlisBranchStrategyPseudo ( const BlisBranchStrategyPseudo & )

Copy constructor.

#### 4.5.3 Member Function Documentation

4.5.3.1 void BlisBranchStrategyPseudo::setRelibility (int rel) [inline]

Set relibility.

Definition at line 70 of file BlisBranchStrategyPseudo.h.

4.5.3.2 virtual BcpsBranchStrategy\* BlisBranchStrategyPseudo::clone( )const [inline], [virtual]

Clone a brancing strategy.

Implements BcpsBranchStrategy.

Definition at line 73 of file BlisBranchStrategyPseudo.h.

4.5.3.3 virtual int BlisBranchStrategyPseudo::betterBranchObject ( BcpsBranchObject \* thisOne, BcpsBranchObject \* bestSoFar ) [virtual]

Compare branching object thisOne to bestSoFar.

If thisOne is better than bestObject, return branching direction(1 or -1), otherwise return 0. If bestSorFar is NULL, then always return branching direction(1 or -1).

Implements BcpsBranchStrategy.

4.5.3.4 int BlisBranchStrategyPseudo::createCandBranchObjects (int numPassesLeft, double ub) [virtual]

Create a set of candidate branching objects.

Reimplemented from BcpsBranchStrategy.

The documentation for this class was generated from the following file:

· BlisBranchStrategyPseudo.h

# 4.6 BlisBranchStrategyRel Class Reference

Blis branching strategy.

#include <BlisBranchStrategyRel.h>

Inheritance diagram for BlisBranchStrategyRel:

Collaboration diagram for BlisBranchStrategyRel:

#### **Public Member Functions**

• BlisBranchStrategyRel ()

Default Constructor.

BlisBranchStrategyRel (BlisModel \*model, int rel)

Useful Constructor.

virtual ∼BlisBranchStrategyRel ()

Destructor.

BlisBranchStrategyRel (const BlisBranchStrategyRel &)

Copy constructor.

· void setRelibility (int rel)

Set relibility.

virtual BcpsBranchStrategy \* clone () const

Clone a brancing strategy.

virtual int betterBranchObject (BcpsBranchObject \*thisOne, BcpsBranchObject \*bestSoFar)

Compare branching object thisOne to bestSoFar.

int createCandBranchObjects (int numPassesLeft, double ub)

Create a set of candidate branching objects.

## 4.6.1 Detailed Description

Blis branching strategy.

This class implements reliability branching.

Definition at line 40 of file BlisBranchStrategyRel.h.

### 4.6.2 Constructor & Destructor Documentation

4.6.2.1 BlisBranchStrategyRel::BlisBranchStrategyRel( ) [inline]

Default Constructor.

Definition at line 51 of file BlisBranchStrategyRel.h.

4.6.2.2 BlisBranchStrategyRel::BlisBranchStrategyRel ( BlisModel \* model, int rel ) [inline]

Useful Constructor.

Definition at line 57 of file BlisBranchStrategyRel.h.

4.6.2.3 virtual BlisBranchStrategyRel::∼BlisBranchStrategyRel( ) [inline], [virtual]

Destructor.

Definition at line 64 of file BlisBranchStrategyRel.h.

4.6.2.4 BlisBranchStrategyRel::BlisBranchStrategyRel ( const BlisBranchStrategyRel & )

Copy constructor.

#### 4.6.3 Member Function Documentation

4.6.3.1 void BlisBranchStrategyRel::setRelibility (int rel) [inline]

Set relibility.

Definition at line 70 of file BlisBranchStrategyRel.h.

4.6.3.2 virtual BcpsBranchStrategy\* BlisBranchStrategyRel::clone()const [inline], [virtual]

Clone a brancing strategy.

Implements BcpsBranchStrategy.

Definition at line 73 of file BlisBranchStrategyRel.h.

4.6.3.3 virtual int BlisBranchStrategyRel::betterBranchObject ( BcpsBranchObject \* thisOne, BcpsBranchObject \* bestSoFar ) [virtual]

Compare branching object thisOne to bestSoFar.

If thisOne is better than bestObject, return branching direction(1 or -1), otherwise return 0. If bestSorFar is NULL, then always return branching direction(1 or -1).

Implements BcpsBranchStrategy.

4.6.3.4 int BlisBranchStrategyRel::createCandBranchObjects (int numPassesLeft, double ub) [virtual]

Create a set of candidate branching objects.

Reimplemented from BcpsBranchStrategy.

The documentation for this class was generated from the following file:

· BlisBranchStrategyRel.h

# 4.7 BlisBranchStrategyStrong Class Reference

This class implements strong branching.

#include <BlisBranchStrategyStrong.h>

Inheritance diagram for BlisBranchStrategyStrong:

Collaboration diagram for BlisBranchStrategyStrong:

### **Public Member Functions**

• BlisBranchStrategyStrong ()

Strong Constructor.

BlisBranchStrategyStrong (BlisModel \*model)

Strong Constructor.

virtual ∼BlisBranchStrategyStrong ()

Destructor.

BlisBranchStrategyStrong (const BlisBranchStrategyStrong &)

Copy constructor.

virtual BcpsBranchStrategy \* clone () const

Clone a brancing strategy.

• virtual int createCandBranchObjects (int numPassesLeft, double ub)

Create a set of candidate branching objects.

virtual int betterBranchObject (BcpsBranchObject \*thisOne, BcpsBranchObject \*bestSoFar)

Compare branching object thisOne to bestSoFar.

## 4.7.1 Detailed Description

This class implements strong branching.

Definition at line 57 of file BlisBranchStrategyStrong.h.

#### 4.7.2 Constructor & Destructor Documentation

4.7.2.1 BlisBranchStrategyStrong::BlisBranchStrategyStrong() [inline]

Strong Constructor.

Definition at line 67 of file BlisBranchStrategyStrong.h.

4.7.2.2 BlisBranchStrategyStrong::BlisBranchStrategyStrong(BlisModel\*model) [inline]

Strong Constructor.

Definition at line 72 of file BlisBranchStrategyStrong.h.

4.7.2.3 virtual BlisBranchStrategyStrong::~BlisBranchStrategyStrong() [inline], [virtual]

Destructor.

Definition at line 78 of file BlisBranchStrategyStrong.h.

4.7.2.4 BlisBranchStrategyStrong::BlisBranchStrategyStrong (const BlisBranchStrategyStrong & )

Copy constructor.

#### 4.7.3 Member Function Documentation

4.7.3.1 virtual BcpsBranchStrategy\* BlisBranchStrategyStrong::clone() const [inline], [virtual]

Clone a brancing strategy.

Implements BcpsBranchStrategy.

Definition at line 84 of file BlisBranchStrategyStrong.h.

4.7.3.2 virtual int BlisBranchStrategyStrong::createCandBranchObjects (int numPassesLeft, double ub) [virtual]

Create a set of candidate branching objects.

Reimplemented from BcpsBranchStrategy.

4.7.3.3 virtual int BlisBranchStrategyStrong::betterBranchObject ( BcpsBranchObject \* thisOne, BcpsBranchObject \* bestSoFar ) [virtual]

Compare branching object thisOne to bestSoFar.

If thisOne is better than bestObject, return branching direction(1 or -1), otherwise return 0. If bestSorFar is NULL, then always return branching direction(1 or -1).

Implements BcpsBranchStrategy.

The documentation for this class was generated from the following file:

• BlisBranchStrategyStrong.h

## 4.8 BlisConGenerator Class Reference

Interface between Blis and Cut Generation Library.

#include <BlisConGenerator.h>

Collaboration diagram for BlisConGenerator:

**Public Member Functions** 

### **Constructors and destructors**

BlisConGenerator ()

Default constructor.

BlisConGenerator (BlisModel \*model, CglCutGenerator \*generator, const char \*name=NULL, Blis
 — CutStrategy strategy=BlisCutStrategyAuto, int cutGenerationFrequency\_=1, bool normal=true, bool at
 — Solution=false, bool infeasible=false)

Useful constructor.

BlisConGenerator (const BlisConGenerator &)

Copy constructor.

BlisConGenerator & operator= (const BlisConGenerator &rhs)

Assignment operator.

virtual ∼BlisConGenerator ()

Destructor.

#### **Generate Constraints**

virtual bool generateConstraints (BcpsConstraintPool &conPool)

Generate cons for the client model.

### Gets and sets

BlisModel \* getModel ()

Set the client model.

void setModel (BlisModel \*m)

Set the model.

void refreshModel (BlisModel \*model)

Refresh the model.

void setName (const char \*str)

return name of generator.

• std::string name () const

return name of generator.

void setStrategy (BlisCutStrategy value)

Set the con generation strategy.

• BlisCutStrategy strategy () const

Get the con generation interval.

void setCutGenerationFreq (int freq)

Set the con generation strategy.

int cutGenerationFreq () const

Get the con generation interval.

bool normal () const

Get whether the con generator should be called in the normal place.

void setNormal (bool value)

Set whether the con generator should be called in the normal place.

bool atSolution () const

Get whether the con generator should be called when a solution is found.

void setAtSolution (bool value)

Set whether the con generator should be called when a solution is found.

• bool whenInfeasible () const

Get whether the con generator should be called when the subproblem is found to be infeasible.

void setWhenInfeasible (bool value)

Set whether the con generator should be called when the subproblem is found to be infeasible.

• CglCutGenerator \* generator () const

Get the CglCutGenerator bound to this BlisConGenerator.

• int numConsGenerated ()

Get number of generated cons.

void addNumConsGenerated (int n)

Increase the number of generated cons.

int numConsUsed ()

Get number of used cons.

void addNumConsUsed (int n)

Increase the number of generated cons.

• double time () const

Cpu time used.

• void addTime (double t)

Increase Cpu time used.

int calls () const

Number called.

void addCalls (int n=1)

Increase the number of called.

• int noConsCalls () const

Number called and no cons found.

void addNoConsCalls (int n=1)

Increase the number of no cons called.

### **Protected Attributes**

• BlisModel \* model

The client model.

CglCutGenerator \* generator\_

The CglCutGenerator object.

BlisCutStrategy strategy\_

When to call CglCutGenerator::generateCuts routine.

• int cutGenerationFrequency\_

The frequency of calls to the cut generator.

std::string name\_

Name of generator.

bool normal\_

Whether to call the generator in the normal place.

bool atSolution\_

Whether to call the generator when a new solution is found.

bool whenInfeasible

Whether to call generator when a subproblem is found to be infeasible.

int numConsGenerated\_

Number of cons generated.

int numConsUsed\_

Number of cons used.

double time\_

Used CPU/User time.

• int calls\_

The times of calling this generator.

· int noConsCalls\_

The times of calling this generator and no cons found.

## 4.8.1 Detailed Description

Interface between Blis and Cut Generation Library.

BlisConGenerator is intended to provide an intelligent interface between Blis and the cutting plane algorithms in the CGL. A BlisConGenerator is bound to a CglCutGenerator and to an BlisModel. It contains parameters which control when and how the generateCuts method of the CglCutGenerator will be called.

The builtin decision criteria available to use when deciding whether to generate cons are: at root, autmatic, every X nodes, when a solution is found, and when a subproblem is found to be infeasible.

Definition at line 58 of file BlisConGenerator.h.

#### 4.8.2 Constructor & Destructor Documentation

**4.8.2.1** BlisConGenerator::BlisConGenerator() [inline]

Default constructor.

Definition at line 119 of file BlisConGenerator.h.

4.8.2.2 BlisConGenerator::BlisConGenerator ( BlisModel \* model, CglCutGenerator \* generator, const char \* name = NULL, BlisCutStrategy \* strategy \* = BlisCutStrategy \* Auto, int cutGenerationFrequency = 1, bool normal = true, bool atSolution = false, bool infeasible = false)

Useful constructor.

4.8.2.3 BlisConGenerator::BlisConGenerator ( const BlisConGenerator & )

Copy constructor.

**4.8.2.4 virtual BlisConGenerator::**~BlisConGenerator() [inline], [virtual]

Destructor.

Definition at line 152 of file BlisConGenerator.h.

### 4.8.3 Member Function Documentation

4.8.3.1 BlisConGenerator& BlisConGenerator::operator=( const BlisConGenerator & rhs )

Assignment operator.

4.8.3.2 virtual bool BlisConGenerator::generateConstraints ( BcpsConstraintPool & conPool ) [virtual]

Generate cons for the client model.

Evaluate the state of the client model and decide whether to generate cons. The generated cons are inserted into and returned in the collection of cons cs.

The routine returns true if reoptimisation is needed (because the state of the solver interface has been modified).

```
4.8.3.3 BlisModel* BlisConGenerator::getModel( ) [inline]
Set the client model.
In addition to setting the client model, refreshModel also calls the refreshSolver method of the CglCutGenerator
object.Get a pointer to the model
Definition at line 182 of file BlisConGenerator.h.
4.8.3.4 void BlisConGenerator::setName ( const char * str ) [inline]
return name of generator.
Definition at line 191 of file BlisConGenerator.h.
4.8.3.5 std::string BlisConGenerator::name() const [inline]
return name of generator.
Definition at line 194 of file BlisConGenerator.h.
4.8.3.6 void BlisConGenerator::setStrategy ( BlisCutStrategy value ) [inline]
Set the con generation strategy.
Definition at line 197 of file BlisConGenerator.h.
4.8.3.7 BlisCutStrategy BlisConGenerator::strategy ( ) const [inline]
Get the con generation interval.
Definition at line 200 of file BlisConGenerator.h.
4.8.3.8 void BlisConGenerator::setCutGenerationFreq (int freq) [inline]
Set the con generation strategy.
Definition at line 203 of file BlisConGenerator.h.
4.8.3.9 int BlisConGenerator::cutGenerationFreq ( ) const [inline]
Get the con generation interval.
Definition at line 206 of file BlisConGenerator.h.
4.8.3.10 bool BlisConGenerator::normal() const [inline]
Get whether the con generator should be called in the normal place.
```

Definition at line 209 of file BlisConGenerator.h.

```
4.8.3.11 void BlisConGenerator::setNormal (bool value) [inline]

Set whether the congenerator should be called in the normal place.
```

Definition at line 212 of file BlisConGenerator.h.

```
4.8.3.12 bool BlisConGenerator::atSolution ( ) const [inline]
```

Get whether the con generator should be called when a solution is found.

Definition at line 216 of file BlisConGenerator.h.

```
4.8.3.13 void BlisConGenerator::setAtSolution (bool value) [inline]
```

Set whether the con generator should be called when a solution is found.

Definition at line 220 of file BlisConGenerator.h.

```
4.8.3.14 bool BlisConGenerator::whenInfeasible ( ) const [inline]
```

Get whether the con generator should be called when the subproblem is found to be infeasible.

Definition at line 224 of file BlisConGenerator.h.

```
4.8.3.15 void BlisConGenerator::setWhenInfeasible (bool value) [inline]
```

Set whether the con generator should be called when the subproblem is found to be infeasible.

Definition at line 228 of file BlisConGenerator.h.

```
4.8.3.16 CglCutGenerator* BlisConGenerator::generator() const [inline]
```

Get the **CglCutGenerator** bound to this BlisConGenerator.

Definition at line 231 of file BlisConGenerator.h.

```
4.8.3.17 int BlisConGenerator::numConsGenerated() [inline]
```

Get number of generated cons.

Definition at line 234 of file BlisConGenerator.h.

```
4.8.3.18 void BlisConGenerator::addNumConsGenerated(int n) [inline]
```

Increase the number of generated cons.

Definition at line 237 of file BlisConGenerator.h.

```
4.8.3.19 int BlisConGenerator::numConsUsed() [inline]
```

Get number of used cons.

Definition at line 240 of file BlisConGenerator.h.

```
4.8.3.20 void BlisConGenerator::addNumConsUsed(int n) [inline]
Increase the number of generated cons.
Definition at line 243 of file BlisConGenerator.h.
4.8.3.21 double BlisConGenerator::time() const [inline]
Cpu time used.
Definition at line 246 of file BlisConGenerator.h.
4.8.3.22 void BlisConGenerator::addTime ( double t ) [inline]
Increase Cpu time used.
Definition at line 249 of file BlisConGenerator.h.
4.8.3.23 int BlisConGenerator::calls ( ) const [inline]
Number called.
Definition at line 252 of file BlisConGenerator.h.
4.8.3.24 void BlisConGenerator::addCalls (int n = 1) [inline]
Increase the number of called.
Definition at line 255 of file BlisConGenerator.h.
4.8.3.25 int BlisConGenerator::noConsCalls ( ) const [inline]
Number called and no cons found.
Definition at line 258 of file BlisConGenerator.h.
4.8.3.26 void BlisConGenerator::addNoConsCalls (int n = 1) [inline]
Increase the number of no cons called.
Definition at line 261 of file BlisConGenerator.h.
4.8.4 Member Data Documentation
4.8.4.1 BlisModel* BlisConGenerator::model_ [protected]
The client model.
```

Definition at line 62 of file BlisConGenerator.h.

**4.8.4.2 CglCutGenerator**\* **BlisConGenerator**::generator\_ [protected]

The **CglCutGenerator** object.

Definition at line 65 of file BlisConGenerator.h.

4.8.4.3 BlisCutStrategy BlisConGenerator::strategy\_ [protected]

When to call CglCutGenerator::generateCuts routine.

BlisCutStrategyNone: disable BlisCutStrategyRoot: just root BlisCutStrategyAuto: automatically decided by BLIS Blis←CutStrategyPeriodic: Generate every 't' nodes

Definition at line 77 of file BlisConGenerator.h.

**4.8.4.4 int BlisConGenerator::cutGenerationFrequency** [protected]

The frequency of calls to the cut generator.

Definition at line 80 of file BlisConGenerator.h.

**4.8.4.5 std::string BlisConGenerator::name\_** [protected]

Name of generator.

Definition at line 83 of file BlisConGenerator.h.

**4.8.4.6 bool BlisConGenerator::normal\_** [protected]

Whether to call the generator in the normal place.

Definition at line 86 of file BlisConGenerator.h.

**4.8.4.7 bool BlisConGenerator::atSolution** [protected]

Whether to call the generator when a new solution is found.

Definition at line 89 of file BlisConGenerator.h.

**4.8.4.8 bool BlisConGenerator::whenInfeasible** [protected]

Whether to call generator when a subproblem is found to be infeasible.

Definition at line 93 of file BlisConGenerator.h.

**4.8.4.9** int BlisConGenerator::numConsGenerated\_ [protected]

Number of cons generated.

Definition at line 100 of file BlisConGenerator.h.

4.8.4.10 int BlisConGenerator::numConsUsed\_ [protected]

Number of cons used.

Definition at line 103 of file BlisConGenerator.h.

**4.8.4.11** double BlisConGenerator::time\_ [protected]

Used CPU/User time.

Definition at line 106 of file BlisConGenerator.h.

**4.8.4.12** int BlisConGenerator::calls\_ [protected]

The times of calling this generator.

Definition at line 109 of file BlisConGenerator.h.

**4.8.4.13** int BlisConGenerator::noConsCalls\_ [protected]

The times of calling this generator and no cons found.

Definition at line 112 of file BlisConGenerator.h.

The documentation for this class was generated from the following file:

· BlisConGenerator.h

## 4.9 BlisConstraint Class Reference

Inheritance diagram for BlisConstraint:

Collaboration diagram for BlisConstraint:

## **Public Member Functions**

• BlisConstraint ()

Default constructor.

BlisConstraint (int s, const int \*ind, const double \*val)

Useful constructor.

• BlisConstraint (double lbh, double ubh, double lbs, double ubs)

Useful constructor.

• BlisConstraint (double lbh, double ubh, double lbs, double ubs, int size, const int \*ind, const double \*val)

Useful constructor.

virtual ∼BlisConstraint ()

Destructor.

BlisConstraint (const BlisConstraint &rhs)

Copy constructor.

OsiRowCut \* createOsiRowCut ()

Create a OsiRowCut based on this constraint.

virtual void hashing (BcpsModel \*model=NULL)

Compute a hash key.

double violation (const double \*IpSolution)

Check if violates a given lp solution.

virtual AlpsReturnStatus encode (AlpsEncoded \*encoded)

Pack into a encode object.

virtual AlpsKnowledge \* decode (AlpsEncoded &encoded) const

Decode a constraint from an encoded object.

• int getSize () const

Return data.

void setData (int s, const int \*ind, const double \*val)

Set data.

#### **Protected Member Functions**

• AlpsReturnStatus encodeBlis (AlpsEncoded \*encoded)

Pack Blis part into an encoded object.

• AlpsReturnStatus decodeBlis (AlpsEncoded &encoded)

Unpack Blis part from a encode object.

### **Protected Attributes**

int size

Number of nonzero coefficients.

int \* indices\_

Variable indices.

double \* values

Value of nonzero coefficients.

## 4.9.1 Detailed Description

Definition at line 33 of file BlisConstraint.h.

## 4.9.2 Constructor & Destructor Documentation

4.9.2.1 BlisConstraint::BlisConstraint ( )

Default constructor.

4.9.2.2 BlisConstraint::BlisConstraint ( int s, const int \* ind, const double \* val )

Useful constructor.

```
4.9.2.3 BlisConstraint::BlisConstraint (double lbh, double ubh, double lbs, double ubs)
Useful constructor.
       BlisConstraint::BlisConstraint (double lbh, double ubh, double lbs, double ubs, int size, const int * ind, const double *
        val)
Useful constructor.
4.9.2.5 virtual BlisConstraint::∼BlisConstraint() [virtual]
Destructor.
4.9.2.6 BlisConstraint::BlisConstraint ( const BlisConstraint & rhs )
Copy constructor.
       Member Function Documentation
4.9.3
4.9.3.1 AlpsReturnStatus BlisConstraint::encodeBlis ( AlpsEncoded * encoded ) [protected]
Pack Blis part into an encoded object.
4.9.3.2 AlpsReturnStatus BlisConstraint::decodeBlis ( AlpsEncoded & encoded ) [protected]
Unpack Blis part from a encode object.
4.9.3.3 OsiRowCut* BlisConstraint::createOsiRowCut()
Create a OsiRowCut based on this constraint.
4.9.3.4 virtual void BlisConstraint::hashing ( BcpsModel * model = NULL ) [virtual]
Compute a hash key.
Reimplemented from BcpsObject.
4.9.3.5 double BlisConstraint::violation ( const double * IpSolution )
Check if violates a given lp solution.
4.9.3.6 virtual AlpsReturnStatus BlisConstraint::encode ( AlpsEncoded * encoded ) [virtual]
Pack into a encode object.
```

Reimplemented from **BcpsObject**.

4.9.3.7 virtual AlpsKnowledge\* BlisConstraint::decode ( AlpsEncoded & encoded ) const [virtual]

Decode a constraint from an encoded object.

Reimplemented from **BcpsObject**.

The documentation for this class was generated from the following file:

· BlisConstraint.h

## 4.10 BlisHeuristic Class Reference

Heuristic base class.

#include <BlisHeuristic.h>

Inheritance diagram for BlisHeuristic:

Collaboration diagram for BlisHeuristic:

#### **Public Member Functions**

• BlisHeuristic ()

Default Constructor.

BlisHeuristic (BlisModel \*model, const char \*name, BlisHeurStrategy strategy, int heurCallFrequency)

Useful constructor.

• virtual ∼BlisHeuristic ()

Distructor.

• BlisHeuristic (const BlisHeuristic &rhs)

Copy constructor.

virtual void setModel (BlisModel \*model)

update model (This is needed if cliques update matrix etc).

virtual void setStrategy (BlisHeurStrategy strategy)

Get/set strategy.

virtual void setHeurCallFrequency (int freq)

Get/set call frequency.

virtual BlisHeuristic \* clone () const

Clone a heuristic.

virtual bool searchSolution (double &objectiveValue, double \*newSolution)=0

returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value This is called after cuts have been added - so can not add cuts

virtual bool searchSolution (double &objectiveValue, double \*newSolution, OsiCuts &cs)

returns 0 if no solution, 1 if valid solution, -1 if just returning an estimate of best possible solution with better objective value than one passed in Sets solution values if good, sets objective value (only if nonzero code) This is called at same time as cut generators - so can add cuts Default is do nothing

• const char \* name () const

return name of generator.

void addNumSolutions (int num=1)

Record number of solutions found.

• int numSolutions () const

Number of solutions found.

• void addTime (double t=0.0)

Record Cpu time used.

· double time () const

Cpu time used.

void addCalls (int c=1)

Record number of times called.

• int calls () const

Number of times called.

• int noSolCalls () const

Number called and no cons found.

• void addNoSolCalls (int n=1)

Increase the number of no cons called.

#### **Protected Attributes**

BlisModel \* model\_

Pointer to the model.

• char \* name\_

Heuristics name.

BlisHeurStrategy strategy\_

When to call findSolution() routine.

int heurCallFrequency

The frequency with which to call the heuristic.

int numSolutions

Number of solutions found.

• double time\_

Used CPU/User time.

• int calls\_

The times of calling this heuristic.

int noSolsCalls\_

The times of calling this heuristic and no solutions found.

## 4.10.1 Detailed Description

Heuristic base class.

Definition at line 48 of file BlisHeuristic.h.

### 4.10.2 Constructor & Destructor Documentation

4.10.2.1 BlisHeuristic::BlisHeuristic() [inline]

Default Constructor.

Definition at line 90 of file BlisHeuristic.h.

```
4.10.2.2 BlisHeuristic::BlisHeuristic (BlisModel * model, const char * name, BlisHeurStrategy strategy, int heurCallFrequency)
         [inline]
Useful constructor.
Definition at line 102 of file BlisHeuristic.h.
4.10.2.3 virtual BlisHeuristic::~BlisHeuristic() [inline], [virtual]
Distructor.
Definition at line 120 of file BlisHeuristic.h.
4.10.2.4 BlisHeuristic::BlisHeuristic (const BlisHeuristic & rhs) [inline]
Copy constructor.
Definition at line 123 of file BlisHeuristic.h.
4.10.3 Member Function Documentation
4.10.3.1 virtual void BlisHeuristic::setModel ( BlisModel*model ) [inline], [virtual]
update model (This is needed if cliques update matrix etc).
Reimplemented in BlisHeurRound.
Definition at line 135 of file BlisHeuristic.h.
4.10.3.2 virtual void BlisHeuristic::setStrategy (BlisHeurStrategy strategy ) [inline], [virtual]
Get/set strategy.
Definition at line 139 of file BlisHeuristic.h.
4.10.3.3 virtual void BlisHeuristic::setHeurCallFrequency (int freq ) [inline], [virtual]
Get/set call frequency.
Definition at line 145 of file BlisHeuristic.h.
4.10.3.4 virtual BlisHeuristic* BlisHeuristic::clone ( ) const [inline], [virtual]
Clone a heuristic.
Reimplemented in BlisHeurRound.
Definition at line 150 of file BlisHeuristic.h.
4.10.3.5 const char* BlisHeuristic::name ( ) const [inline]
return name of generator.
Definition at line 177 of file BlisHeuristic.h.
```

```
4.10.3.6 void BlisHeuristic::addNumSolutions (int num = 1) [inline]
Record number of solutions found.
Definition at line 180 of file BlisHeuristic.h.
4.10.3.7 int BlisHeuristic::numSolutions ( ) const [inline]
Number of solutions found.
Definition at line 183 of file BlisHeuristic.h.
4.10.3.8 void BlisHeuristic::addTime ( double t = 0.0 ) [inline]
Record Cpu time used.
Definition at line 186 of file BlisHeuristic.h.
4.10.3.9 double BlisHeuristic::time() const [inline]
Cpu time used.
Definition at line 189 of file BlisHeuristic.h.
4.10.3.10 void BlisHeuristic::addCalls (int c = 1 ) [inline]
Record number of times called.
Definition at line 192 of file BlisHeuristic.h.
4.10.3.11 int BlisHeuristic::calls ( ) const [inline]
Number of times called.
Definition at line 195 of file BlisHeuristic.h.
4.10.3.12 int BlisHeuristic::noSolCalls ( ) const [inline]
Number called and no cons found.
Definition at line 198 of file BlisHeuristic.h.
4.10.3.13 void BlisHeuristic::addNoSolCalls (int n = 1 ) [inline]
Increase the number of no cons called.
Definition at line 201 of file BlisHeuristic.h.
```

4.10.4 Member Data Documentation

**4.10.4.1 BlisHeurStrategy BlisHeuristic::strategy** [protected]

When to call findSolution() routine.

BlisHeurStrategyNone: disable BlisHeurStrategyRoot: just root BlisHeurStrategyAuto: automatically decided by BLIS BlisHeurStrategyPeriodic: every 't' nodes BlisHeurStrategyBeforeRoot: before solving first LP

Definition at line 70 of file BlisHeuristic.h.

**4.10.4.2** int BlisHeuristic::numSolutions\_ [protected]

Number of solutions found.

Definition at line 76 of file BlisHeuristic.h.

**4.10.4.3 double BlisHeuristic::time\_** [protected]

Used CPU/User time.

Definition at line 79 of file BlisHeuristic.h.

**4.10.4.4** int BlisHeuristic::calls\_ [protected]

The times of calling this heuristic.

Definition at line 82 of file BlisHeuristic.h.

**4.10.4.5** int BlisHeuristic::noSolsCalls\_ [protected]

The times of calling this heuristic and no solutions found.

Definition at line 85 of file BlisHeuristic.h.

The documentation for this class was generated from the following file:

· BlisHeuristic.h

## 4.11 BlisHeurRound Class Reference

Rounding Heuristic.

#include <BlisHeurRound.h>

Inheritance diagram for BlisHeurRound:

Collaboration diagram for BlisHeurRound:

### **Public Member Functions**

• BlisHeurRound ()

Default Constructor.

BlisHeurRound (BlisModel \*model, const char \*name, BlisHeurStrategy strategy, int freq)

Constructor with model - assumed before cuts.

∼BlisHeurRound ()

Destructor.

• BlisHeurRound (const BlisHeurRound &)

Copy constructor.

• virtual BlisHeuristic \* clone () const

Clone a rounding heuristic.

virtual void setModel (BlisModel \*model)

update model (This is needed if cliques update matrix etc).

virtual bool searchSolution (double &objectiveValue, double \*newSolution)

returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value (only if good) This is called after cuts have been added - so can not add cuts

void setSeed (int value)

Set seed.

### **Protected Attributes**

CoinPackedMatrix matrix

Column majored matrix.

CoinPackedMatrix matrixByRow\_

Row majored matrix.

int seed

Seed for random stuff.

## 4.11.1 Detailed Description

Rounding Heuristic.

Definition at line 44 of file BlisHeurRound.h.

### 4.11.2 Constructor & Destructor Documentation

```
4.11.2.1 BlisHeurRound::BlisHeurRound() [inline]
```

Default Constructor.

Definition at line 61 of file BlisHeurRound.h.

```
4.11.2.2 BlisHeurRound::BlisHeurRound ( BlisModel * model, const char * name, BlisHeurStrategy strategy, int freq )
```

Constructor with model - assumed before cuts.

Definition at line 64 of file BlisHeurRound.h.

```
4.11.2.3 BlisHeurRound::~BlisHeurRound() [inline]
```

Destructor.

Definition at line 73 of file BlisHeurRound.h.

4.11.2.4 BlisHeurRound::BlisHeurRound ( const BlisHeurRound & )

Copy constructor.

### 4.11.3 Member Function Documentation

4.11.3.1 virtual void BlisHeurRound::setModel ( BlisModel \* model ) [virtual]

update model (This is needed if cliques update matrix etc).

Reimplemented from BlisHeuristic.

### 4.11.4 Member Data Documentation

**4.11.4.1 CoinPackedMatrix BlisHeurRound::matrix** [protected]

Column majored matrix.

Definition at line 51 of file BlisHeurRound.h.

**4.11.4.2 CoinPackedMatrix BlisHeurRound::matrixByRow**\_ [protected]

Row majored matrix.

Definition at line 54 of file BlisHeurRound.h.

**4.11.4.3** int BlisHeurRound::seed\_ [protected]

Seed for random stuff.

Definition at line 57 of file BlisHeurRound.h.

The documentation for this class was generated from the following file:

· BlisHeurRound.h

# 4.12 BlisMessage Class Reference

Inheritance diagram for BlisMessage:

Collaboration diagram for BlisMessage:

**Public Member Functions** 

#### Constructors etc

• BlisMessage (Language language=us\_en)

Constructor.

## 4.12.1 Detailed Description

Definition at line 58 of file BlisMessage.h.

The documentation for this class was generated from the following file:

· BlisMessage.h

## 4.13 BlisModel Class Reference

Inheritance diagram for BlisModel:

Collaboration diagram for BlisModel:

### **Public Member Functions**

• BlisModel ()

Default construtor.

virtual ∼BlisModel ()

Destructor.

void gutsOfDestructor ()

Actual destructor.

void setColMatrix (CoinPackedMatrix \*mat)

Pass a matrix in.

void setNumCons (int num)

Pass column upper bounds.

void setNumVars (int num)

Pass column upper bounds.

void setNumElems (int num)

Pass column upper bounds.

void setConLb (double \*cl)

Pass column upper bounds.

void setConUb (double \*cu)

Pass column lower bounds.

void setVarLb (double \*lb)

Pass variable upper bounds.void setVarUb (double \*ub)

old servation (double \*ub)

Pass variable lower bounds.

void setColType (char \*colType)

Pass variable types.

void setObjCoef (double \*obj)

Pass objective coefficients.

• virtual void readInstance (const char \*dataFile)

For parallel code, only the master calls this function.

virtual void importModel (std::vector< BlisVariable \* > vars, std::vector< BlisConstraint \* > cons)

For parallel code, only the master calls this function.

• virtual void readParameters (const int argnum, const char \*const \*arglist)

Read in Alps, Blis parameters.

```
• virtual void writeParameters (std::ostream &outstream) const
      Write out parameters.

    virtual AlpsTreeNode * createRoot ()

      For parallel code, only the master calls this function.

    virtual bool setupSelf ()

      All processes call this function.
• virtual void preprocess ()
      Preprocessing the model.

    virtual void postprocess ()

      Postprocessing the searching results.

    virtual void setSolver (OsiSolverInterface *si)

      Set Ip solver.

    virtual OsiSolverInterface * getSolver ()

      Get Ip solver.

    virtual OsiSolverInterface * solver ()

      Get Ip solver.

    bool resolve ()

      Resolving a lp.

    void setActiveNode (AlpsTreeNode *node)

      Set active node.

    void setSolEstimate (double est)

      Set the solution estimate of the active node.
• int getNumStrong ()
      Get number of strong branchings.

    void addNumStrong (int num=1)

      Add num to number of strong branchings.

    int getNumBranchResolve ()

      Get the maximum number of resolve during branching.

    void setNumBranchResolve (int num)

      Set the maximum number of resolve during branching.

    double * getObjCoef () const

      Get objective coefficients.

    const double * getColLower ()

      Get column lower bound.

    const double * getColUpper ()

      Get column upper bound.
• int getNumCols ()
      Get number of columns.
• int getNumRows ()
      Get number of rows.
double * varLB ()
      Get variable bounds arrary.

    double * conLB ()

      Get original constraint bounds arrary.

    double * startVarLB ()

      The starting variable bounds arrary of a subproblem (internal use).

    double * startConLB ()
```

The starting constraint bounds arrary of a subproblem (internal use).

int \* tempVarLBPos ()

Temparory storage.

double getLpObjValue () const

Get current objective function value.

const double \* getLpSolution () const

Get active Ip solution.

• int getNumSolutions () const

Get number of solutions.

· int getNumHeurSolutions () const

Get number of heuristic solutions.

double \* incumbent ()

Return best ip solution found so far.

• int storeSolution (BlisSolutionType how, BlisSolution \*sol)

Record a new incumbent solution and update objective Value.

• double getCutoff () const

Get cut off value.

void setCutoff (double co)

Set cut off value.

BlisSolution \* feasibleSolutionHeur (const double \*solution)

Test if a solution found by heuristic is feasible.

virtual BlisSolution \* feasibleSolution (int &numIntegerInfs, int &numObjectInfs)

Test the current LP solution for feasiblility.

virtual BlisSolution \* userFeasibleSolution (const double \*solution, bool &feasible)

User's criteria for a feasible solution.

void createIntgerObjects (bool startAgain)

Identify integer variable.

int \* getIntObjIndices () const

Get integers' object indices.

• int getNumIntObjects () const

Get number of integers.

• int \* getIntColIndices () const

Get integers' column indices.

· bool checkInteger (double value) const

Check if a value is integer.

• void addHeuristic (BlisHeuristic \*heur)

Add a heuristic.

BlisHeuristic \* heuristics (int i) const

Get a specific heuristic.

• int numHeuristics () const

Get the number of heuristics.

void addCutGenerator (BlisConGenerator \*generator)

Add a Blis cut generator.

void addCutGenerator (CglCutGenerator \*generator, const char \*name=NULL, BlisCutStrategy strategy=Blis
 — CutStrategyAuto, int cutGenerationFrequency=1, bool normal=true, bool atSolution=false, bool when
 — Infeasible=false)

Add a Cgl cut generator.

BlisConGenerator \* cutGenerators (int i) const

Get a specific cut generator.

· int numCutGenerators () const

Get the number of cut generators.

• int getMaxNumCons () const

Get the max number of cuts can be generated.

void setMaxNumCons (int m)

Set the max number of cuts can be generated.

BcpsConstraintPool \* constraintPool ()

Access constraint pool.

BcpsConstraintPool \* constraintPoolReceive ()

Access receive constraint pool.

BcpsConstraintPool \* constraintPoolSend ()

Access send constraint pool.

BlisCutStrategy getCutStrategy () const

Query constraint generation strategy.

void setCutStrategy (BlisCutStrategy u)

Set constraint generation strategy.

· int getCutGenerationFrequency () const

Query constraint generation frequency.

void setCutStrategy (int f)

Set constraint generation frequency.

• int getDenseConCutoff () const

Get the thresheld to be considered as a dense constraint.

void setDenseConCutoff (int cutoff)

Set the thresheld to be considered as a dense constraint.

double \* getConRandoms () const

Get randoms for check parallel constraints.

void passInPriorities (const int \*priorities, bool ifNotSimpleIntegers, int defaultValue=1000)

Pass in branching priorities.

const int \* priority () const

Priorities.

• int priority (int sequence) const

Returns priority level for an object (or 1000 if no priorities exist)

virtual void modelLog ()

Log of specific models.

• int getNumNodes () const

Get how many Nodes it took to solve the problem.

int getNumIterations () const

Get how many iterations it took to solve the problem.

• int getAveIterations () const

Get the average iterations it took to solve a lp.

void addNumNodes (int newNodes=1)

Increment node count.

void addNumIterations (int newIter)

Increment Iteration count.

CoinMessageHandler \* blisMessageHandler () const

Get the message handler.

• CoinMessages blisMessages ()

Return messages.

virtual void nodeLog (AlpsTreeNode \*node, bool force)

Node log.

virtual bool fathomAllNodes ()

Return true, if all nodes can be fathomed.

virtual void registerKnowledge ()

Register knowledge.

virtual AlpsEncoded \* encode () const

The method that encodes the model into an encoded object.

virtual void decodeToSelf (AlpsEncoded &)

The method that decodes the model from an encoded object.

virtual AlpsEncoded \* packSharedKnowlege ()

Pack knowledge to be shared with others into an encoded object.

virtual void unpackSharedKnowledge (AlpsEncoded &)

Unpack and store shared knowledge from an encoded object.

### **Branching Strategys**

See the BcpsBranchStrategy class for additional information.

BcpsBranchStrategy \* branchStrategy () const

Get the current branching strategy.

void setBranchingMethod (BcpsBranchStrategy \*method)

Set the branching strategy.

void setBranchingMethod (BcpsBranchStrategy &method)

Set the branching stratedy.

BcpsBranchStrategy \* rampUpBranchStrategy () const

#### Object manipulation routines

• int numObjects () const

Get the number of objects.

void setNumObjects (int num)

Set the number of objects.

BcpsObject \*\* objects ()

Get the array of objects.

• BcpsObject \* objects (int which)

Get the specified object.

void setSharedObjectMark (int i)

Mark object to be shared.

void clearSharedObjectMark ()

Clear all the share mark.

• void deleteObjects ()

Delete all object information.

void addObjects (int numObjects, BcpsObject \*\*objects)

Add in object information.

int getNumOldConstraints () const

Get number of old constraints.

void setNumOldConstraints (int num)

Set number of old constraints.

• int getOldConstraintsSize () const

Get max number of old constraints.

void setOldConstraintsSize (int num)

Set max number of old constraints.

BlisConstraint \*\* oldConstraints ()

Access old constraints.

void setOldConstraints (BlisConstraint \*\*old)

set old constraints.

• void delOldConstraints ()

Set max number of old constraints.

• BlisParams \* BlisPar ()

Access parameters.

## **Public Attributes**

bool isRoot

If root node.

int boundingPass

The number of passes during bounding procedure.

double integerTol\_

Integer tolerance.

double optimalRelGap\_

Input relative optimal gap.

double optimalAbsGap\_

Input absolute optimal gap.

double currRelGap

Current relative optimal gap.

double currAbsGap\_

Current absolute optimal gap.

BlisHeurStrategy heurStrategy\_

If use heuristics.

int heurCallFrequency

Frequency of using heuristics.

OsiCuts newCutPool

Store new cuts in each pass.

std::vector< AlpsTreeNode \* > leafToRootPath

Record the path from leaf to root.

## **Protected Member Functions**

• void init ()

Intialize member data.

· void createObjects ()

Create variables and constraints.

AlpsReturnStatus encodeBlis (AlpsEncoded \*encoded) const

Pack Blis portion of the model into an encoded object.

AlpsReturnStatus decodeBlis (AlpsEncoded &encoded)

Unpack Blis portion of the model from an encoded object.

void packSharedPseudocost (AlpsEncoded \*encoded, int numToShare)

Retrieve and pack shared pseudocost.

void unpackSharedPseudocost (AlpsEncoded &encoded)

Unpack and store shared pseduocost.

void packSharedConstraints (AlpsEncoded \*encoded)

Retrieve and pack shared constraints.

void unpackSharedConstraints (AlpsEncoded &encoded)

Unpack and store shared constraints.

void packSharedVariables (AlpsEncoded \*encoded)

Retrieve and pack shared variables.

void unpackSharedVariables (AlpsEncoded &encoded)

Unpack and store shared variables.

#### **Protected Attributes**

OsiSolverInterface \* origLpSolver

Input by user.

OsiSolverInterface \* presolvedLpSolver\_

Presolved.

OsiSolverInterface \* lpSolver

Actually used.

CoinPackedMatrix \* colMatrix\_

Column majored matrix.

· double incObjValue\_

Incumbent objective value.

• double \* incumbent

Incumbent.

double cutoff\_

Cutoff in Ip solver.

• double cutoffInc\_

Cutoff increment.

BcpsBranchStrategy \* branchStrategy\_

Variable selection function.

• int numObjects\_

Number of objects.

BcpsObject \*\* objects\_

The set of objects.

char \* sharedObjectMark

The objects that can be shared.

int \* priority

Priorities of integer object.

AlpsTreeNode \* activeNode

Active node.

int numStrong

Number of strong branching.

· int numBranchResolve\_

Maximum number of resolve during branching.

int numHeuristics

Number of heuristics.

BlisHeuristic \*\* heuristics

The list of heuristics.

BlisCutStrategy cutStrategy\_

If use cut generators.

• int cutGenerationFrequency\_

Frequency of cut generation.

· int numCutGenerators\_

Number of cut generators used.

int maxNumCons\_

Number of cuts can be generators.

• BlisConGenerator \*\* generators\_

The list of cut generators used.

BcpsConstraintPool \* constraintPool\_

Store all the cuts.

• BlisConstraint \*\* oldConstraints\_

Temporary store old cuts at a node when installing a node.

int oldConstraintsSize

The memory size allocated for oldConstraints\_.

• int numOldConstraints\_

Number of old constraints.

double \* conRandoms

Random keys.

int denseConCutoff

Dense constraint cutoff.

• BlisParams \* BlisPar

Blis parameters.

CoinMessageHandler \* blisMessageHandler\_

Message handler.

· CoinMessages blisMessages\_

Blis messages.

int numNodes

Number of processed nodes.

· int numIterations\_

Number of Ip(Simplex) iterations.

int avelterations\_

Average number of lp iterations to solve a subproblem.

BcpsConstraintPool \* constraintPoolSend\_

Constraints that can be sent/broadcasted to other processes.

BcpsConstraintPool \* constraintPoolReceive\_

Constraints that are received from other processses.

double \* varLB

Variable and constraint bounds.

int numCols

Number of columns/rows/elements.

· double objSense\_

Objective function.

int numIntObjects\_

Column types.

std::vector< BcpsVariable \* > inputVar\_

User's input objects.

double \* startVarLB\_

Starting var/con bounds for processing each node.

int \* tempVarLBPos\_

Tempory storage for var/con indices.

## 4.13.1 Detailed Description

Definition at line 69 of file BlisModel.h.

#### 4.13.2 Constructor & Destructor Documentation

```
4.13.2.1 BlisModel::BlisModel() [inline]
```

Default construtor.

Definition at line 339 of file BlisModel.h.

```
4.13.2.2 virtual BlisModel::~BlisModel( ) [virtual]
```

Destructor.

#### 4.13.3 Member Function Documentation

```
4.13.3.1 void BlisModel::createObjects() [protected]
```

Create variables and constraints.

4.13.3.2 void BlisModel::gutsOfDestructor ( )

Actual destructor.

**4.13.3.3** virtual void BlisModel::readInstance ( const char \* dataFile ) [virtual]

For parallel code, only the master calls this function.

1) Read in the instance data 2) Set colMatrix\_, varLB\_, varUB\_, conLB\_, conUB numCols\_, numRows\_ 3) Set obj 
Coef\_ and objSense\_ 4) Set colType\_ ('C', 'I', or 'B') 5) Create variables and constraints 6) Set numCoreVariables\_ and numCoreConstraints

Reimplemented from AlpsModel.

```
4.13.3.4 virtual void BlisModel::importModel ( std::vector < BlisVariable *> vars, std::vector < BlisConstraint *> cons ) [virtual]
```

For parallel code, only the master calls this function.

Import model from vars and cons. 1) Set colMatrix\_, varLB\_, varUB\_, conLB\_, conUB numCols\_, numRows\_ 2) Set objCoef\_ (Assume minimization) 3) Set colType\_ ('C', 'I', or 'B') 4) Set variables\_ and constraints\_ 5) Set numCore variables\_ and numCoreConstraints\_ NOTE: Blis takes over the memory ownship of vars and cons, which means users must NOT free vars or cons.

```
4.13.3.5 virtual void BlisModel::readParameters ( const int argnum, const char *const * arglist ) [virtual]
```

Read in Alps, Blis parameters.

Reimplemented from AlpsModel.

```
4.13.3.6 virtual void BlisModel::writeParameters ( std::ostream & outstream ) const [virtual]
```

Write out parameters.

```
4.13.3.7 virtual AlpsTreeNode* BlisModel::createRoot() [virtual]
```

For parallel code, only the master calls this function.

Create the root node based on model.

Reimplemented from AlpsModel.

```
4.13.3.8 virtual bool BlisModel::setupSelf() [virtual]
```

All processes call this function.

Do necessary work to make model usable. Return success or not. 1) Set numIntObjects\_, intColIndices\_, intObject Indices\_ 2) Load problem to LP solver. 3) Create integer objects (must after load to lp since using lp info) 4) Set branch strategy 5) Add heuristics 6) Add Cgl cut generators

Reimplemented from **AlpsModel**.

```
4.13.3.9 virtual void BlisModel::preprocess ( ) [virtual]
```

Preprocessing the model.

Reimplemented from AlpsModel.

```
4.13.3.10 virtual void BlisModel::postprocess() [virtual]
Postprocessing the searching results.
Reimplemented from AlpsModel.
4.13.3.11 virtual void BlisModel::setSolver( OsiSolverInterface * si) [inline], [virtual]
Set lp solver.
Definition at line 440 of file BlisModel.h.
4.13.3.12 virtual OsiSolverInterface* BlisModel::getSolver( ) [inline], [virtual]
Get lp solver.
Definition at line 443 of file BlisModel.h.
4.13.3.13 virtual OsiSolverInterface * BlisModel::solver( ) [inline], [virtual]
Get lp solver.
Definition at line 446 of file BlisModel.h.
4.13.3.14 bool BlisModel::resolve ( )
Resolving a lp.
4.13.3.15 void BlisModel::setActiveNode( AlpsTreeNode * node) [inline]
Set active node.
Definition at line 452 of file BlisModel.h.
4.13.3.16 void BlisModel::setSolEstimate ( double est ) [inline]
Set the solution estimate of the active node.
Definition at line 455 of file BlisModel.h.
4.13.3.17 int BlisModel::getNumStrong() [inline]
Get number of strong branchings.
Definition at line 458 of file BlisModel.h.
4.13.3.18 void BlisModel::addNumStrong(int num = 1) [inline]
Add num to number of strong branchings.
Definition at line 461 of file BlisModel.h.
```

```
4.13.3.19 int BlisModel::getNumBranchResolve( ) [inline]
Get the maximum number of resolve during branching.
Definition at line 464 of file BlisModel.h.
4.13.3.20 void BlisModel::setNumBranchResolve (int num ) [inline]
Set the maximum number of resolve during branching.
Definition at line 467 of file BlisModel.h.
4.13.3.21 double* BlisModel::getObjCoef( ) const [inline]
Get objective coefficients.
Definition at line 474 of file BlisModel.h.
4.13.3.22 const double* BlisModel::getColLower( ) [inline]
Get column lower bound.
Definition at line 477 of file BlisModel.h.
4.13.3.23 const double* BlisModel::getColUpper( ) [inline]
Get column upper bound.
Definition at line 480 of file BlisModel.h.
4.13.3.24 int BlisModel::getNumCols() [inline]
Get number of columns.
Definition at line 483 of file BlisModel.h.
4.13.3.25 int BlisModel::getNumRows() [inline]
Get number of rows.
Definition at line 486 of file BlisModel.h.
4.13.3.26 double * BlisModel::varLB( ) [inline]
Get variable bounds arrary.
Definition at line 489 of file BlisModel.h.
4.13.3.27 double* BlisModel::conLB( ) [inline]
Get original constraint bounds arrary.
```

Definition at line 493 of file BlisModel.h.

```
4.13.3.28 double* BlisModel::startVarLB( ) [inline]
The starting variable bounds arrary of a subproblem (internal use).
Definition at line 497 of file BlisModel.h.
4.13.3.29 double* BlisModel::startConLB() [inline]
The starting constraint bounds arrary of a subproblem (internal use).
Definition at line 501 of file BlisModel.h.
4.13.3.30 int* BlisModel::tempVarLBPos() [inline]
Temparory storage.
Definition at line 505 of file BlisModel.h.
4.13.3.31 double BlisModel::getLpObjValue ( ) const [inline]
Get current objective function value.
Definition at line 515 of file BlisModel.h.
4.13.3.32 const double* BlisModel::getLpSolution() const [inline]
Get active lp solution.
Definition at line 518 of file BlisModel.h.
4.13.3.33 int BlisModel::getNumSolutions ( ) const [inline]
Get number of solutions.
Definition at line 525 of file BlisModel.h.
4.13.3.34 int BlisModel::getNumHeurSolutions ( ) const [inline]
Get number of heuristic solutions.
Definition at line 528 of file BlisModel.h.
4.13.3.35 double* BlisModel::incumbent() [inline]
Return best ip solution found so far.
Definition at line 531 of file BlisModel.h.
4.13.3.36 int BlisModel::storeSolution ( BlisSolutionType how, BlisSolution * sol )
```

Record a new incumbent solution and update objective Value.

4.13.3.37 double BlisModel::getCutoff() const [inline]

Get cut off value.

Definition at line 537 of file BlisModel.h.

4.13.3.38 void BlisModel::setCutoff ( double co ) [inline]

Set cut off value.

Definition at line 540 of file BlisModel.h.

4.13.3.39 BlisSolution \*\* BlisModel::feasibleSolutionHeur ( const double \*\* solution )

Test if a solution found by heuristic is feasible.

4.13.3.40 virtual BlisSolution \* BlisModel::feasibleSolution (int & numIntegerInfs, int & numObjectInfs ) [virtual]

Test the current LP solution for feasiblility.

Scan all objects for indications of infeasibility. This is broken down into simple integer infeasibility (numIntegerInfs) and all other reports of infeasibility(numObjectInfs).

4.13.3.41 virtual BlisSolution\* BlisModel::userFeasibleSolution( const double \* solution, bool & feasible ) [inline], [virtual]

User's criteria for a feasible solution.

If user think the given solution is feasible then need 1) set userFeasible to true, and 2) return a non-null solution. If user think the solution is infeasible then need 1) set userFeasible to false, and 2) return a null.

Definition at line 571 of file BlisModel.h.

4.13.3.42 BcpsBranchStrategy\* BlisModel::branchStrategy( )const [inline]

Get the current branching strategy.

Definition at line 587 of file BlisModel.h.

4.13.3.43 void BlisModel::setBranchingMethod ( BcpsBranchStrategy \* method ) [inline]

Set the branching strategy.

Definition at line 591 of file BlisModel.h.

4.13.3.44 void BlisModel::setBranchingMethod ( BcpsBranchStrategy & method ) [inline]

Set the branching stratedy.

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Definition at line 597 of file BlisModel.h.

```
4.13.3.45 int BlisModel::numObjects ( ) const [inline]
Get the number of objects.
Definition at line 609 of file BlisModel.h.
4.13.3.46 void BlisModel::setNumObjects (int num ) [inline]
Set the number of objects.
Definition at line 612 of file BlisModel.h.
4.13.3.47 BcpsObject** BlisModel::objects() [inline]
Get the array of objects.
Definition at line 615 of file BlisModel.h.
4.13.3.48 BcpsObject* BlisModel::objects (int which ) [inline]
Get the specified object.
Definition at line 618 of file BlisModel.h.
4.13.3.49 void BlisModel::setSharedObjectMark(int i ) [inline]
Mark object to be shared.
Definition at line 621 of file BlisModel.h.
4.13.3.50 void BlisModel::clearSharedObjectMark( ) [inline]
Clear all the share mark.
Definition at line 624 of file BlisModel.h.
4.13.3.51 void BlisModel::deleteObjects ( )
Delete all object information.
4.13.3.52 void BlisModel::addObjects (int numObjects, BcpsObject ** objects)
Add in object information.
Objects are cloned; the owner can delete the originals.
4.13.3.53 void BlisModel::createIntgerObjects ( bool startAgain )
Identify integer variable.
```

```
4.13.3.54 int* BlisModel::getIntObjIndices ( ) const [inline]
Get integers' object indices.
Definition at line 642 of file BlisModel.h.
4.13.3.55 int BlisModel::getNumIntObjects ( ) const [inline]
Get number of integers.
Definition at line 645 of file BlisModel.h.
4.13.3.56 int* BlisModel::getIntColIndices ( ) const [inline]
Get integers' column indices.
Definition at line 648 of file BlisModel.h.
4.13.3.57 bool BlisModel::checkInteger ( double value ) const [inline]
Check if a value is integer.
Definition at line 651 of file BlisModel.h.
4.13.3.58 void BlisModel::addHeuristic ( BlisHeuristic * heur )
Add a heuristic.
4.13.3.59 BlisHeuristic* BlisModel::heuristics (int i) const [inline]
Get a specific heuristic.
Definition at line 672 of file BlisModel.h.
4.13.3.60 int BlisModel::numHeuristics ( ) const [inline]
Get the number of heuristics.
Definition at line 675 of file BlisModel.h.
4.13.3.61 void BlisModel::addCutGenerator ( BlisConGenerator * generator )
Add a Blis cut generator.
4.13.3.62 void BlisModel::addCutGenerator ( CglCutGenerator * generator, const char * name = NULL, BlisCutStrategy
          strategy = BlisCutStrategyAuto, int cutGenerationFrequency = 1, bool normal = true, bool atSolution =
          false, bool whenInfeasible = false )
```

Add a Cgl cut generator.

```
4.13.3.63 BlisConGenerator* BlisModel::cutGenerators (int i) const [inline]
Get a specific cut generator.
Definition at line 694 of file BlisModel.h.
4.13.3.64 int BlisModel::numCutGenerators ( ) const [inline]
Get the number of cut generators.
Definition at line 697 of file BlisModel.h.
4.13.3.65 int BlisModel::getMaxNumCons ( ) const [inline]
Get the max number of cuts can be generated.
Definition at line 700 of file BlisModel.h.
4.13.3.66 void BlisModel::setMaxNumCons (int m) [inline]
Set the max number of cuts can be generated.
Definition at line 703 of file BlisModel.h.
4.13.3.67 BcpsConstraintPool* BlisModel::constraintPool() [inline]
Access constraint pool.
Definition at line 706 of file BlisModel.h.
4.13.3.68 BcpsConstraintPool* BlisModel::constraintPoolReceive( ) [inline]
Access receive constraint pool.
Definition at line 709 of file BlisModel.h.
4.13.3.69 BcpsConstraintPool* BlisModel::constraintPoolSend() [inline]
Access send constraint pool.
Definition at line 713 of file BlisModel.h.
4.13.3.70 int BlisModel::getNumOldConstraints ( ) const [inline]
Get number of old constraints.
Definition at line 717 of file BlisModel.h.
4.13.3.71 void BlisModel::setNumOldConstraints (int num) [inline]
Set number of old constraints.
```

Definition at line 720 of file BlisModel.h.

```
4.13.3.72 int BlisModel::getOldConstraintsSize() const [inline]
Get max number of old constraints.
Definition at line 723 of file BlisModel.h.
4.13.3.73 void BlisModel::setOldConstraintsSize (int num ) [inline]
Set max number of old constraints.
Definition at line 726 of file BlisModel.h.
4.13.3.74 BlisConstraint** BlisModel::oldConstraints() [inline]
Access old constraints.
Definition at line 729 of file BlisModel.h.
4.13.3.75 void BlisModel::setOldConstraints ( BlisConstraint ** old ) [inline]
set old constraints.
Definition at line 732 of file BlisModel.h.
4.13.3.76 void BlisModel::delOldConstraints() [inline]
Set max number of old constraints.
Definition at line 735 of file BlisModel.h.
4.13.3.77 BlisCutStrategy BlisModel::getCutStrategy ( ) const [inline]
Query constraint generation strategy.
Definition at line 742 of file BlisModel.h.
4.13.3.78 void BlisModel::setCutStrategy ( BlisCutStrategy u ) [inline]
Set constraint generation strategy.
Definition at line 747 of file BlisModel.h.
4.13.3.79 int BlisModel::getCutGenerationFrequency() const [inline]
Query constraint generation frequency.
Definition at line 750 of file BlisModel.h.
4.13.3.80 void BlisModel::setCutStrategy (int f ) [inline]
Set constraint generation frequency.
Definition at line 753 of file BlisModel.h.
```

```
4.13.3.81 int BlisModel::getDenseConCutoff( ) const [inline]
```

Get the thresheld to be considered as a dense constraint.

Definition at line 756 of file BlisModel.h.

```
4.13.3.82 void BlisModel::setDenseConCutoff (int cutoff) [inline]
```

Set the thresheld to be considered as a dense constraint.

Definition at line 759 of file BlisModel.h.

```
4.13.3.83 double* BlisModel::getConRandoms ( ) const [inline]
```

Get randoms for check parallel constraints.

Definition at line 762 of file BlisModel.h.

```
4.13.3.84 void BlisModel::passInPriorities ( const int * priorities, bool ifNotSimpleIntegers, int defaultValue = 1 0 0 0 )
```

Pass in branching priorities.

If ifClique then priorities are on cliques otherwise priorities are on integer variables. Other type (if exists set to default) 1 is highest priority. (well actually -INT\_MAX is but that's ugly) If hotstart > 0 then branches are created to force the variable to the value given by best solution. This enables a sort of hot start. The node choice should be greatest depth and hotstart should normally be switched off after a solution.

If ifNotSimpleIntegers true then appended to normal integers

```
4.13.3.85 const int* BlisModel::priority ( ) const [inline]
```

Priorities.

Definition at line 787 of file BlisModel.h.

```
4.13.3.86 virtual void BlisModel::modelLog() [virtual]
```

Log of specific models.

Reimplemented from AlpsModel.

```
4.13.3.87 int BlisModel::getNumNodes ( ) const [inline]
```

Get how many Nodes it took to solve the problem.

Definition at line 808 of file BlisModel.h.

```
4.13.3.88 int BlisModel::getNumIterations ( ) const [inline]
```

Get how many iterations it took to solve the problem.

Definition at line 811 of file BlisModel.h.

```
4.13.3.89 int BlisModel::getAvelterations ( ) const [inline]
Get the average iterations it took to solve a lp.
Definition at line 814 of file BlisModel.h.
4.13.3.90 void BlisModel::addNumNodes (int newNodes = 1) [inline]
Increment node count.
Definition at line 817 of file BlisModel.h.
4.13.3.91 void BlisModel::addNumlterations (int newlter) [inline]
Increment Iteration count.
Definition at line 820 of file BlisModel.h.
4.13.3.92 CoinMessageHandler* BlisModel::blisMessageHandler( ) const [inline]
Get the message handler.
Definition at line 826 of file BlisModel.h.
4.13.3.93 CoinMessages BlisModel::blisMessages ( ) [inline]
Return messages.
Definition at line 830 of file BlisModel.h.
4.13.3.94 BlisParams* BlisModel::BlisPar() [inline]
Access parameters.
Definition at line 834 of file BlisModel.h.
4.13.3.95 virtual void BlisModel::nodeLog ( AlpsTreeNode * node, bool force ) [virtual]
Node log.
Reimplemented from AlpsModel.
4.13.3.96 virtual bool BlisModel::fathomAllNodes() [virtual]
Return true, if all nodes can be fathomed.
Reimplemented from AlpsModel.
4.13.3.97 AlpsReturnStatus BlisModel::encodeBlis ( AlpsEncoded * encoded ) const [protected]
Pack Blis portion of the model into an encoded object.
```

```
4.13.3.98 AlpsReturnStatus BlisModel::decodeBlis ( AlpsEncoded & encoded ) [protected]
Unpack Blis portion of the model from an encoded object.
4.13.3.99 void BlisModel::packSharedPseudocost ( AlpsEncoded * encoded, int numToShare ) [protected]
Retrieve and pack shared pseudocost.
4.13.3.100 void BlisModel::packSharedConstraints ( AlpsEncoded * encoded ) [protected]
Retrieve and pack shared constraints.
4.13.3.101 void BlisModel::unpackSharedConstraints ( AlpsEncoded & encoded ) [protected]
Unpack and store shared constraints.
4.13.3.102 void BlisModel::packSharedVariables ( AlpsEncoded * encoded ) [protected]
Retrieve and pack shared variables.
4.13.3.103 void BlisModel::unpackSharedVariables ( AlpsEncoded & encoded ) [protected]
Unpack and store shared variables.
4.13.3.104 virtual void BlisModel::registerKnowledge( ) [virtual]
Register knowledge.
Reimplemented from AlpsModel.
4.13.3.105 virtual AlpsEncoded* BlisModel::encode( )const [virtual]
The method that encodes the model into an encoded object.
Reimplemented from AlpsKnowledge.
4.13.3.106 virtual void BlisModel::decodeToSelf ( AlpsEncoded & ) [virtual]
The method that decodes the model from an encoded object.
Reimplemented from AlpsModel.
4.13.3.107 virtual AlpsEncoded* BlisModel::packSharedKnowlege( ) [virtual]
Pack knowledge to be shared with others into an encoded object.
Return NULL means that no knowledge can be shared.
```

Reimplemented from AlpsModel.

4.13.3.108 virtual void BlisModel::unpackSharedKnowledge( AlpsEncoded & ) [virtual]

Unpack and store shared knowledge from an encoded object.

Reimplemented from AlpsModel.

4.13.4 Member Data Documentation

**4.13.4.1 OsiSolverInterface**\* BlisModel::origLpSolver\_ [protected]

Input by user.

Definition at line 78 of file BlisModel.h.

**4.13.4.2 OsiSolverInterface**\* BlisModel::presolvedLpSolver\_ [protected]

Presolved.

Definition at line 80 of file BlisModel.h.

**4.13.4.3 OsiSolverInterface**\* **BlisModel::lpSolver\_** [protected]

Actually used.

If using presolve, then it is presolved; otherwise it is the original.

Definition at line 83 of file BlisModel.h.

**4.13.4.4 CoinPackedMatrix**\* BlisModel::colMatrix\_ [protected]

Column majored matrix.

(For MPS file, etc.)

Definition at line 90 of file BlisModel.h.

**4.13.4.5** double\* BlisModel::varLB\_ [protected]

Variable and constraint bounds.

Definition at line 94 of file BlisModel.h.

**4.13.4.6** double BlisModel::objSense\_ [protected]

Objective function.

Definition at line 109 of file BlisModel.h.

4.13.4.7 int BlisModel::numIntObjects\_ [protected]

Column types.

Definition at line 115 of file BlisModel.h.

```
4.13.4.8 std::vector<BcpsVariable *> BlisModel::inputVar_ [protected]
User's input objects.
Definition at line 121 of file BlisModel.h.
4.13.4.9 double BlisModel::incObjValue [protected]
Incumbent objective value.
Definition at line 143 of file BlisModel.h.
4.13.4.10 double BlisModel::cutoff_ [protected]
Cutoff in lp solver.
Definition at line 149 of file BlisModel.h.
4.13.4.11 double BlisModel::cutofflnc_ [protected]
Cutoff increment.
Definition at line 152 of file BlisModel.h.
4.13.4.12 BcpsBranchStrategy* BlisModel::branchStrategy_ [protected]
Variable selection function.
Definition at line 170 of file BlisModel.h.
4.13.4.13 int BlisModel::numObjects_ [protected]
Number of objects.
Definition at line 179 of file BlisModel.h.
4.13.4.14 BcpsObject** BlisModel::objects_ [protected]
The set of objects.
Definition at line 182 of file BlisModel.h.
4.13.4.15 char* BlisModel::sharedObjectMark_ [protected]
The objects that can be shared.
Definition at line 185 of file BlisModel.h.
4.13.4.16 int* BlisModel::priority_ [protected]
Priorities of integer object.
Definition at line 188 of file BlisModel.h.
```

**4.13.4.17 AlpsTreeNode**\* **BlisModel::activeNode**\_ [protected]

Active node.

Definition at line 191 of file BlisModel.h.

**4.13.4.18** int BlisModel::numStrong\_ [protected]

Number of strong branching.

Definition at line 194 of file BlisModel.h.

**4.13.4.19** int BlisModel::numBranchResolve\_ [protected]

Maximum number of resolve during branching.

Definition at line 200 of file BlisModel.h.

**4.13.4.20** int BlisModel::numHeuristics\_ [protected]

Number of heuristics.

Definition at line 207 of file BlisModel.h.

**4.13.4.21** BlisHeuristic\*\* BlisModel::heuristics\_ [protected]

The list of heuristics.

Definition at line 210 of file BlisModel.h.

**4.13.4.22** BlisCutStrategy BlisModel::cutStrategy\_ [protected]

If use cut generators.

Definition at line 217 of file BlisModel.h.

**4.13.4.23** int BlisModel::numCutGenerators\_ [protected]

Number of cut generators used.

Definition at line 223 of file BlisModel.h.

4.13.4.24 int BlisModel::maxNumCons\_ [protected]

Number of cuts can be generators.

Definition at line 226 of file BlisModel.h.

**4.13.4.25** BlisConGenerator\*\* BlisModel::generators\_ [protected]

The list of cut generators used.

Definition at line 229 of file BlisModel.h.

```
4.13.4.26 BcpsConstraintPool* BlisModel::constraintPool_ [protected]
Store all the cuts.
Definition at line 232 of file BlisModel.h.
4.13.4.27 BlisConstraint** BlisModel::oldConstraints_ [protected]
Temporary store old cuts at a node when installing a node.
Definition at line 235 of file BlisModel.h.
4.13.4.28 int BlisModel::oldConstraintsSize_ [protected]
The memory size allocated for oldConstraints_.
Definition at line 238 of file BlisModel.h.
4.13.4.29 int BlisModel::numOldConstraints_ [protected]
Number of old constraints.
Definition at line 241 of file BlisModel.h.
4.13.4.30 double* BlisModel::conRandoms_ [protected]
Random keys.
Definition at line 244 of file BlisModel.h.
4.13.4.31 BlisParams* BlisModel::BlisPar_ [protected]
Blis parameters.
Definition at line 254 of file BlisModel.h.
4.13.4.32 CoinMessageHandler* BlisModel::blisMessageHandler_ [protected]
Message handler.
Definition at line 257 of file BlisModel.h.
4.13.4.33 CoinMessages BlisModel::blisMessages_ [protected]
Blis messages.
Definition at line 260 of file BlisModel.h.
4.13.4.34 int BlisModel::numNodes_ [protected]
Number of processed nodes.
```

Definition at line 263 of file BlisModel.h.

**4.13.4.35** int BlisModel::numlterations\_ [protected]

Number of lp(Simplex) iterations.

Definition at line 266 of file BlisModel.h.

**4.13.4.36** int BlisModel::avelterations\_ [protected]

Average number of lp iterations to solve a subproblem.

Definition at line 269 of file BlisModel.h.

**4.13.4.37** int\* BlisModel::tempVarLBPos\_ [protected]

Tempory storage for var/con indices.

Definition at line 277 of file BlisModel.h.

**4.13.4.38** BcpsConstraintPool\* BlisModel::constraintPoolSend\_ [protected]

Constraints that can be sent/broadcasted to other processes.

Definition at line 288 of file BlisModel.h.

**4.13.4.39 BcpsConstraintPool\* BlisModel::constraintPoolReceive\_** [protected]

Constraints that are received from other processes.

Definition at line 291 of file BlisModel.h.

4.13.4.40 bool BlisModel::isRoot\_

If root node.

Definition at line 296 of file BlisModel.h.

4.13.4.41 int BlisModel::boundingPass\_

The number of passes during bounding procedure.

Definition at line 299 of file BlisModel.h.

4.13.4.42 double BlisModel::integerTol\_

Integer tolerance.

Definition at line 302 of file BlisModel.h.

4.13.4.43 double BlisModel::optimalRelGap\_

Input relative optimal gap.

Definition at line 305 of file BlisModel.h.

4.13.4.44 double BlisModel::optimalAbsGap\_

Input absolute optimal gap.

Definition at line 308 of file BlisModel.h.

4.13.4.45 double BlisModel::currRelGap

Current relative optimal gap.

Definition at line 311 of file BlisModel.h.

4.13.4.46 double BlisModel::currAbsGap\_

Current absolute optimal gap.

Definition at line 314 of file BlisModel.h.

4.13.4.47 BlisHeurStrategy BlisModel::heurStrategy\_

If use heuristics.

Definition at line 317 of file BlisModel.h.

4.13.4.48 int BlisModel::heurCallFrequency\_

Frequency of using heuristics.

Definition at line 320 of file BlisModel.h.

4.13.4.49 OsiCuts BlisModel::newCutPool\_

Store new cuts in each pass.

Definition at line 323 of file BlisModel.h.

 $4.13.4.50 \quad \text{std::vector} < \textbf{AlpsTreeNode} *> \textbf{BlisModel::leafToRootPath}$ 

Record the path from leaf to root.

Definition at line 326 of file BlisModel.h.

The documentation for this class was generated from the following file:

· BlisModel.h

# 4.14 BlisNodeDesc Class Reference

Inheritance diagram for BlisNodeDesc:

Collaboration diagram for BlisNodeDesc:

## **Public Member Functions**

• BlisNodeDesc ()

Default constructor.

BlisNodeDesc (BlisModel \*m)

Useful constructor.

virtual ∼BlisNodeDesc ()

Destructor.

void setBasis (CoinWarmStartBasis \*&ws)

Set basis.

CoinWarmStartBasis \* getBasis () const

Get warm start basis.

· void setBranchedDir (int d)

Set branching direction.

• int getBranchedDir () const

Get branching direction.

void setBranchedInd (int d)

Set branching object index.

• int getBranchedInd () const

Get branching object index.

void setBranchedVal (double d)

Set branching value.

double getBranchedVal () const

Get branching direction.

• virtual AlpsReturnStatus encode (AlpsEncoded \*encoded) const

Pack node description into an encoded.

• virtual AlpsReturnStatus decode (AlpsEncoded &encoded)

Unpack a node description from an encoded.

## **Protected Member Functions**

• AlpsReturnStatus encodeBlis (AlpsEncoded \*encoded) const

Pack blis portion of node description into an encoded.

AlpsReturnStatus decodeBlis (AlpsEncoded &encoded)

Unpack blis portion of node description from an encoded.

## 4.14.1 Detailed Description

Definition at line 40 of file BlisNodeDesc.h.

#### 4.14.2 Constructor & Destructor Documentation

4.14.2.1 BlisNodeDesc::BlisNodeDesc() [inline]

Default constructor.

Definition at line 59 of file BlisNodeDesc.h.

```
4.14.2.2 BlisNodeDesc::BlisNodeDesc ( BlisModel * m ) [inline]
Useful constructor.
Definition at line 68 of file BlisNodeDesc.h.
4.14.2.3 virtual BlisNodeDesc::~BlisNodeDesc( ) [inline], [virtual]
Destructor.
Definition at line 78 of file BlisNodeDesc.h.
4.14.3 Member Function Documentation
4.14.3.1 void BlisNodeDesc::setBasis ( CoinWarmStartBasis *& ws ) [inline]
Set basis.
Definition at line 81 of file BlisNodeDesc.h.
4.14.3.2 CoinWarmStartBasis* BlisNodeDesc::getBasis( ) const [inline]
Get warm start basis.
Definition at line 88 of file BlisNodeDesc.h.
4.14.3.3 void BlisNodeDesc::setBranchedDir(int d) [inline]
Set branching direction.
Definition at line 91 of file BlisNodeDesc.h.
4.14.3.4 int BlisNodeDesc::getBranchedDir() const [inline]
Get branching direction.
Definition at line 94 of file BlisNodeDesc.h.
4.14.3.5 void BlisNodeDesc::setBranchedInd(int d) [inline]
Set branching object index.
Definition at line 97 of file BlisNodeDesc.h.
4.14.3.6 int BlisNodeDesc::getBranchedInd() const [inline]
Get branching object index.
```

Definition at line 100 of file BlisNodeDesc.h.

**4.14.3.7 void** BlisNodeDesc::setBranchedVal( double *d* ) [inline]

Set branching value.

Definition at line 103 of file BlisNodeDesc.h.

4.14.3.8 double BlisNodeDesc::getBranchedVal( ) const [inline]

Get branching direction.

Definition at line 106 of file BlisNodeDesc.h.

4.14.3.9 AlpsReturnStatus BlisNodeDesc::encodeBlis ( AlpsEncoded \* encoded ) const [inline], [protected]

Pack blis portion of node description into an encoded.

Definition at line 111 of file BlisNodeDesc.h.

4.14.3.10 AlpsReturnStatus BlisNodeDesc::decodeBlis ( AlpsEncoded & encoded ) [inline], [protected]

Unpack blis portion of node description from an encoded.

Definition at line 133 of file BlisNodeDesc.h.

4.14.3.11 virtual AlpsReturnStatus BlisNodeDesc::encode ( AlpsEncoded \* encoded ) const [inline], [virtual]

Pack node description into an encoded.

Reimplemented from AlpsNodeDesc.

Definition at line 157 of file BlisNodeDesc.h.

4.14.3.12 virtual AlpsReturnStatus BlisNodeDesc::decode ( AlpsEncoded & encoded ) [inline], [virtual]

Unpack a node description from an encoded.

Fill member data.

Reimplemented from AlpsNodeDesc.

Definition at line 167 of file BlisNodeDesc.h.

The documentation for this class was generated from the following file:

· BlisNodeDesc.h

# 4.15 BlisObjectInt Class Reference

Inheritance diagram for BlisObjectInt:

Collaboration diagram for BlisObjectInt:

#### **Public Member Functions**

• BlisObjectInt ()

Default Constructor.

BlisObjectInt (int objectIndex, int iColumn, double lb, double ub, double breakEven=0.5)

Useful constructor - passed integer index and model index.

virtual ∼BlisObjectInt ()

Destructor.

BlisObjectInt (const BlisObjectInt &)

Copy constructor.

virtual BcpsObject \* clone () const

Clone an object.

• BlisObjectInt & operator= (const BlisObjectInt &rhs)

Assignment operator.

virtual double infeasibility (BcpsModel \*m, int &preferredWay) const

Infeasibility

virtual void feasibleRegion (BcpsModel \*m)

Set bounds to contain the current solution.

virtual BcpsBranchObject \* createBranchObject (BcpsModel \*m, int direction) const

Creates a branching object.

virtual BcpsBranchObject \* preferredNewFeasible (BcpsModel \*m) const

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in the good direction.

virtual BcpsBranchObject \* notPreferredNewFeasible (BcpsModel \*m) const

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a bad direction.

virtual void resetBounds (BcpsModel \*m)

Reset original upper and lower bound values from the solver.

· virtual int columnIndex () const

Column number if single column object, otherwise.

• double breakEven () const

Breakeven e.g 0.7 ->> = 0.7 go up first.

void setBreakEven (double value)

Set breakeven e.g 0.7 ->> = 0.7 go up first.

• BlisPseudocost & pseudocost ()

Access pseudocost.

# Get or set Original bounds.

- double originalLowerBound () const
- void setOriginalLowerBound (double value)
- · double originalUpperBound () const
- void setOriginalUpperBound (double value)

## **Protected Attributes**

int columnIndex

Column index in the lp model.

· double originalLower\_

Original lower bound.

• double originalUpper\_

Original upper bound.

double breakEven\_

Breakeven i.e.

· BlisPseudocost pseudocost\_

Pseudo cost.

# 4.15.1 Detailed Description

Definition at line 36 of file BlisObjectInt.h.

# 4.15.2 Constructor & Destructor Documentation

```
4.15.2.1 BlisObjectInt::BlisObjectInt()
```

Default Constructor.

4.15.2.2 BlisObjectInt::BlisObjectInt (int objectIndex, int iColumn, double lb, double ub, double breakEven = 0.5)

Useful constructor - passed integer index and model index.

```
4.15.2.3 virtual BlisObjectInt:: \sim BlisObjectInt( ) [inline], [virtual]
```

Destructor.

Definition at line 68 of file BlisObjectInt.h.

4.15.2.4 BlisObjectInt::BlisObjectInt ( const BlisObjectInt & )

Copy constructor.

#### 4.15.3 Member Function Documentation

```
4.15.3.1 virtual BcpsObject* BlisObjectInt::clone( )const [inline], [virtual]
```

Clone an object.

Reimplemented from BcpsObject.

Definition at line 74 of file BlisObjectInt.h.

4.15.3.2 BlisObjectInt& BlisObjectInt::operator= ( const BlisObjectInt & rhs )

Assignment operator.

4.15.3.3 virtual double BlisObjectInt::infeasibility ( BcpsModel \* m, int & preferredWay ) const [virtual]

Infeasibility.

Range is [0.0, 0.5].

**Parameters** 

PreferredWay the direction close to an integer.

Reimplemented from BcpsObject.

**4.15.3.4** virtual void BlisObjectInt::feasibleRegion ( BcpsModel \* m ) [virtual]

Set bounds to contain the current solution.

More precisely, for the variable associated with this object, take the value given in the current solution, force it within the current bounds if required, then set the bounds to fix the variable at the integer nearest the solution value.

Reimplemented from **BcpsObject**.

4.15.3.5 virtual BcpsBranchObject\* BlisObjectInt::createBranchObject ( BcpsModel \* m, int direction ) const [virtual]

Creates a branching object.

Reimplemented from BcpsObject.

4.15.3.6 virtual BcpsBranchObject\* BlisObjectInt::preferredNewFeasible ( BcpsModel \* m ) const [virtual]

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in the good direction.

The preferred branching object will force the variable to be +/-1 from its current value, depending on the reduced cost and objective sense. If movement in the direction which improves the objective is impossible due to bounds on the variable, the branching object will move in the other direction. If no movement is possible, the method returns NULL.

Only the bounds on this variable are considered when determining if the new point is feasible.

Reimplemented from **BcpsObject**.

4.15.3.7 virtual BcpsBranchObject\* BlisObjectInt::notPreferredNewFeasible(BcpsModel\* m)const [virtual]

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a bad direction.

As for preferredNewFeasible(), but the preferred branching object will force movement in a direction that degrades the objective.

Reimplemented from **BcpsObject**.

```
4.15.3.8 virtual void BlisObjectInt::resetBounds ( BcpsModel * m ) [virtual]
Reset original upper and lower bound values from the solver.
Handy for updating bounds held in this object after bounds held in the solver have been tightened.
Reimplemented from BcpsObject.
4.15.3.9 virtual int BlisObjectInt::columnIndex ( ) const [inline], [virtual]
Column number if single column object, otherwise.
Definition at line 129 of file BlisObjectInt.h.
4.15.3.10 double BlisObjectInt::breakEven() const [inline]
Breakeven e.g 0.7 ->> = 0.7 go up first.
Definition at line 140 of file BlisObjectInt.h.
4.15.3.11 void BlisObjectInt::setBreakEven ( double value ) [inline]
Set breakeven e.g 0.7 ->> = 0.7 go up first.
Definition at line 143 of file BlisObjectInt.h.
4.15.3.12 BlisPseudocost& BlisObjectInt::pseudocost() [inline]
Access pseudocost.
Definition at line 146 of file BlisObjectInt.h.
4.15.4 Member Data Documentation
4.15.4.1 int BlisObjectInt::columnIndex_ [protected]
Column index in the lp model.
Definition at line 41 of file BlisObjectInt.h.
4.15.4.2 double BlisObjectInt::originalLower_ [protected]
Original lower bound.
Definition at line 44 of file BlisObjectInt.h.
```

Generated on Thu Oct 8 2015 22:51:24 for Blis by Doxygen

Definition at line 47 of file BlisObjectInt.h.

Original upper bound.

**4.15.4.3** double BlisObjectInt::originalUpper\_ [protected]

```
4.15.4.4 double BlisObjectInt::breakEven_ [protected]
Breakeven i.e.
>= this preferred is up.
Definition at line 50 of file BlisObjectInt.h.
4.15.4.5 BlisPseudocost BlisObjectInt::pseudocost_ [protected]
```

Pseudo cost.

Definition at line 53 of file BlisObjectInt.h.

The documentation for this class was generated from the following file:

· BlisObjectInt.h

# 4.16 BlisParams Class Reference

Inheritance diagram for BlisParams:

Collaboration diagram for BlisParams:

# **Public Types**

```
    enum chrParams {
        cutRampUp, presolve, shareConstraints, shareVariables,
        sharePseudocostRampUp, sharePseudocostSearch }
        Character parameters.
    enum intParams {
        branchStrategy, cutStrategy, cutGenerationFrequency, quickCutPass,
        cutCliqueStrategy, difference, heurStrategy, heurCallFrequency,
```

lookAhead, pseudoRelibility, sharePcostDepth, sharePcostFrequency,

Integer paramters.

strongCandSize }

enum dblParams {
 cutFactor, cutoff, cutoffInc, denseConFactor,
 integerTol, objSense, optimalRelGap, optimalAbsGap,
 pseudoWeight, scaleConFactor, tailOff }

Double parameters.

• enum strParams

String parameters.

• enum strArrayParams

There are no string array parameters.

## **Public Member Functions**

virtual void createKeywordList ()

Method for creating the list of keyword looked for in the parameter file.

virtual void setDefaultEntries ()

Method for setting the default values for the parameters.

void setEntry (const chrParams key, const char \*val)

char\* is true(1) or false(0), not used

void setEntry (const chrParams key, const char val)

char is true(1) or false(0), not used

· void setEntry (const chrParams key, const bool val)

This method is the one that ever been used.

#### Constructors.

• BlisParams ()

The default constructor creates a parameter set with from the template argument structure.

#### Query methods

For user application: Following code are do NOT need to change.

The reason can not put following functions in base class AlpsParameterSet is that chrParams and endOf← ChrParams etc., are NOT the same as those declared in base class.

The members of the parameter set can be queried for using the overloaded entry() method. Using the example in the class documentation the user can get a parameter with the "<code>param.entry(USER\_par::parameter\_
name)</code>" expression.

- bool entry (const chrParams key) const
- int entry (const intParams key) const
- double entry (const dblParams key) const
- const std::string & entry (const strParams key) const
- const std::vector< std::string > & entry (const strArrayParams key) const

## Packing/unpacking methods

void pack (AlpsEncoded &buf)

Pack the parameter set into the buffer (AlpsEncoded is used as buffer Here).

void unpack (AlpsEncoded &buf)

Unpack the parameter set from the buffer.

# 4.16.1 Detailed Description

Definition at line 35 of file BlisParams.h.

# 4.16.2 Member Enumeration Documentation

#### 4.16.2.1 enum BlisParams::chrParams

Character parameters.

All of these variable are used as booleans (ture = 1, false = 0).

#### Enumerator

cutRampUp Generate cuts during rampup. Default: true presolve Presolve or not.

shareConstraints Share constraints Default: false.

shareVariables Share constraints Default: false.
 sharePseudocostRampUp Share pseudocost during ramp up. Default: true
 sharePseudocostSearch Share pseudocost during search Default: false.

Definition at line 39 of file BlisParams.h.

#### 4.16.2.2 enum BlisParams::intParams

Integer paramters.

#### **Enumerator**

**branchStrategy** Branching strategy. 0: max infeasibilty, 1: pseudocost, 2: relibility, 3: strong branching. 4: bilevel branching

cutStrategy Cut generators control. -2: root, -1: auto, 0: disable, any positive frequency

cutGenerationFrequency All constraint generators.

quickCutPass The pass to generate cuts.

cutCliqueStrategy The pass to generate cuts for quick branching.

difference -1 auto, 0, no, any integer frequency

heurStrategy Heuristics control. BlisHeurStrategyRoot: root, BlisHeurStrategyAuto: auto, BlisHuerStrategy← None: disable, BlisHeurStrategyPeriodic: every 't' nodes

heurCallFrequency All heuristics.

lookAhead The look ahead of pseudocost.

pseudoRelibility The relibility of pseudocost.

sharePcostDepth Maximum tree depth of sharing pseudocost.

sharePcostFrequency Frequency of sharing pseudocost.

strongCandSize The number of candidate used in strong branching. Default: 10.

Definition at line 62 of file BlisParams.h.

#### 4.16.2.3 enum BlisParams::dblParams

Double parameters.

## **Enumerator**

cutFactor Limit the max number cuts applied at a node. maxNumCons = (CutFactor - 1) \* numCoreConstraints.

cutoff Cutoff any nodes whose objective value is higher than it.

cutoffinc The value added to relaxation value when deciding fathom. Default:1.0e-6

denseConFactor Dense constraint factor.

integerTol Tolerance to treat as an integer. Default: 1.0e-5

objSense Objective sense: min = 1.0, max = -1.0.

optimalRelGap If the relative gap between best feasible and best relaxed fall into this gap, search stops. Default:1.0e-6

optimalAbsGap If the absolute gap between best feasible and best relaxed fall into this gap, search stops. Default: 1.0e-4

**pseudoWeight** Weight used to calculate pseudocost.

scaleConFactor Scaling indicator of a constraint.

tailOff Tail off.

Definition at line 133 of file BlisParams.h.

## 4.16.2.4 enum BlisParams::strParams

String parameters.

Definition at line 174 of file BlisParams.h.

#### 4.16.2.5 enum BlisParams::strArrayParams

There are no string array parameters.

Definition at line 181 of file BlisParams.h.

#### 4.16.3 Constructor & Destructor Documentation

```
4.16.3.1 BlisParams::BlisParams() [inline]
```

The default constructor creates a parameter set with from the template argument structure.

The keyword list is created and the defaults are set.

Definition at line 193 of file BlisParams.h.

#### 4.16.4 Member Function Documentation

```
4.16.4.1 virtual void BlisParams::createKeywordList() [virtual]
```

Method for creating the list of keyword looked for in the parameter file.

Implements AlpsParameterSet.

```
4.16.4.2 virtual void BlisParams::setDefaultEntries() [virtual]
```

Method for setting the default values for the parameters.

Implements AlpsParameterSet.

```
4.16.4.3 void BlisParams::pack ( AlpsEncoded & buf ) [inline], [virtual]
```

Pack the parameter set into the buffer (AlpsEncoded is used as buffer Here).

Reimplemented from AlpsParameterSet.

Definition at line 284 of file BlisParams.h.

```
4.16.4.4 void BlisParams::unpack( AlpsEncoded & buf) [inline], [virtual]
```

Unpack the parameter set from the buffer.

Reimplemented from AlpsParameterSet.

Definition at line 297 of file BlisParams.h.

The documentation for this class was generated from the following file:

· BlisParams.h

# 4.17 BlisPresolve Class Reference

A interface to Osi/Coin Presolve.

#include <BlisPresolve.h>

Inheritance diagram for BlisPresolve:

Collaboration diagram for BlisPresolve:

#### **Public Member Functions**

• BlisPresolve ()

Default constructor (empty object)

virtual ∼BlisPresolve ()

Virtual destructor.

• virtual **OsiSolverInterface** \* preprocess (**OsiSolverInterface** & origModel, double feasibilityTolerance=0.0, bool keepIntegers=true, int numberPasses=5, const char \*prohibited=NULL)

Presolve.

virtual void postprocess (bool updateStatus=true)

Postsolve.

# 4.17.1 Detailed Description

A interface to Osi/Coin Presolve.

Definition at line 37 of file BlisPresolve.h.

The documentation for this class was generated from the following file:

· BlisPresolve.h

# 4.18 BlisPseudocost Class Reference

Inheritance diagram for BlisPseudocost:

Collaboration diagram for BlisPseudocost:

## **Public Member Functions**

• BlisPseudocost ()

Default constructor.

BlisPseudocost (double uc, int un, double dc, int dn, double s)

Useful constructor.

BlisPseudocost (const BlisPseudocost &cost)

Copy constructor.

BlisPseudocost & operator= (const BlisPseudocost &cost)

Overload operator =.

void setWeight (double w)

Set weigth.

- void update (const int dir, const double parentObjValue, const double objValue, const double solValue)
   Update pseudocost.
- void update (const int dir, const double objDiff, const double solValue)

Update pseudocost.

void update (double upCost, int upCount, double downCost, int downCount)

Update pseudocost.

• int getUpCount ()

Get up branching count.

double getUpCost ()

Get up branching cost.

int getDownCount ()

Get down branching count.

• double getDownCost ()

Get down branching cost.

• double getScore ()

Get importance.

void setScore (double s)

Set importance.

AlpsReturnStatus encodeTo (AlpsEncoded \*encoded) const

Pack pseudocost to the given object.

AlpsReturnStatus decodeFrom (AlpsEncoded &encoded)

Unpack pseudocost from the given encode object.

virtual AlpsEncoded \* encode () const

Encode this node for message passing.

virtual AlpsKnowledge \* decode (AlpsEncoded &) const

Decode a node from an encoded object.

# 4.18.1 Detailed Description

Definition at line 32 of file BlisPseudo.h.

### 4.18.2 Constructor & Destructor Documentation

4.18.2.1 BlisPseudocost::BlisPseudocost( ) [inline]

Default constructor.

Definition at line 58 of file BlisPseudo.h.

4.18.2.2 BlisPseudocost::BlisPseudocost (double uc, int un, double dc, int dn, double s) [inline]

Useful constructor.

Definition at line 68 of file BlisPseudo.h.

```
4.18.3
        Member Function Documentation
4.18.3.1 void BlisPseudocost::setWeight ( double w ) [inline]
Set weigth.
Definition at line 104 of file BlisPseudo.h.
4.18.3.2 void BlisPseudocost::update ( const int dir, const double parentObjValue, const double objValue, const double solValue)
Update pseudocost.
4.18.3.3 void BlisPseudocost::update ( const int dir, const double objDiff, const double solValue )
Update pseudocost.
4.18.3.4 void BlisPseudocost::update ( double upCost, int upCount, double downCost, int downCount )
Update pseudocost.
4.18.3.5 int BlisPseudocost::getUpCount() [inline]
Get up branching count.
Definition at line 130 of file BlisPseudo.h.
4.18.3.6 double BlisPseudocost::getUpCost() [inline]
Get up branching cost.
Definition at line 133 of file BlisPseudo.h.
4.18.3.7 int BlisPseudocost::getDownCount() [inline]
Get down branching count.
Definition at line 136 of file BlisPseudo.h.
4.18.3.8 double BlisPseudocost::getDownCost() [inline]
Get down branching cost.
Definition at line 139 of file BlisPseudo.h.
4.18.3.9 double BlisPseudocost::getScore() [inline]
Get importance.
```

Definition at line 142 of file BlisPseudo.h.

4.18.3.10 void BlisPseudocost::setScore ( double s ) [inline]

Set importance.

Definition at line 145 of file BlisPseudo.h.

4.18.3.11 AlpsReturnStatus BlisPseudocost::encodeTo ( AlpsEncoded \* encoded ) const

Pack pseudocost to the given object.

4.18.3.12 AlpsReturnStatus BlisPseudocost::decodeFrom ( AlpsEncoded & encoded )

Unpack pseudocost from the given encode object.

4.18.3.13 virtual AlpsEncoded\* BlisPseudocost::encode( ) const [virtual]

Encode this node for message passing.

Reimplemented from AlpsKnowledge.

4.18.3.14 virtual AlpsKnowledge\* BlisPseudocost::decode ( AlpsEncoded & ) const [virtual]

Decode a node from an encoded object.

Reimplemented from **AlpsKnowledge**.

The documentation for this class was generated from the following file:

· BlisPseudo.h

# 4.19 BlisSolution Class Reference

This class contains the solutions generated by the LP solver (either primal or dual.

```
#include <BlisSolution.h>
```

Inheritance diagram for BlisSolution:

Collaboration diagram for BlisSolution:

## **Public Member Functions**

• BlisSolution ()

Default constructor.

• BlisSolution (int s, const double \*values, double objValue)

Useful constructor.

virtual ∼BlisSolution ()

Destructor.

virtual void print (std::ostream &os) const

Print out the solution.

virtual AlpsEncoded \* encode () const

The method that encodes the solution into a encoded object.

• virtual AlpsKnowledge \* decode (AlpsEncoded &encoded) const

The method that decodes the solution from a encoded object.

# 4.19.1 Detailed Description

This class contains the solutions generated by the LP solver (either primal or dual.

The class exists primarily to pass solutions to the object generator(s).

Definition at line 36 of file BlisSolution.h.

## 4.19.2 Constructor & Destructor Documentation

```
4.19.2.1 BlisSolution::BlisSolution() [inline]
```

Default constructor.

Definition at line 43 of file BlisSolution.h.

```
4.19.2.2 BlisSolution::BlisSolution (int s, const double * values, double objValue ) [inline]
```

Useful constructor.

Definition at line 49 of file BlisSolution.h.

```
4.19.2.3 virtual BlisSolution::~BlisSolution() [inline], [virtual]
```

Destructor.

Definition at line 55 of file BlisSolution.h.

## 4.19.3 Member Function Documentation

```
4.19.3.1 virtual void BlisSolution::print ( std::ostream & os ) const [inline], [virtual]
```

Print out the solution.

Print the solution.

Reimplemented from **BcpsSolution**.

Definition at line 59 of file BlisSolution.h.

```
4.19.3.2 virtual AlpsEncoded* BlisSolution::encode( ) const [inline], [virtual]
```

The method that encodes the solution into a encoded object.

Reimplemented from AlpsKnowledge.

Definition at line 80 of file BlisSolution.h.

4.19.3.3 virtual AlpsKnowledge\* BlisSolution::decode ( AlpsEncoded & encoded ) const [inline], [virtual]

The method that decodes the solution from a encoded object.

Reimplemented from AlpsKnowledge.

Definition at line 88 of file BlisSolution.h.

The documentation for this class was generated from the following file:

· BlisSolution.h

# 4.20 BlisStrong Struct Reference

Collaboration diagram for BlisStrong:

# 4.20.1 Detailed Description

Definition at line 41 of file BlisBranchStrategyStrong.h.

The documentation for this struct was generated from the following file:

BlisBranchStrategyStrong.h

# 4.21 BlisTreeNode Class Reference

This is the class in which we are finally able to concretely define the bounding procedure.

```
#include <BlisSubTree.h>
```

Inheritance diagram for BlisTreeNode:

Collaboration diagram for BlisTreeNode:

## **Public Member Functions**

• BlisTreeNode ()

Default constructor.

• BlisTreeNode (BlisModel \*m)

Useful constructor.

• BlisTreeNode (AlpsNodeDesc \*&desc)

Useful constructor.

virtual ~BlisTreeNode ()

Destructor.

• void init ()

Initilize member data when constructing a node.

AlpsTreeNode \* createNewTreeNode (AlpsNodeDesc \*&desc) const

Create a new node based on given desc.

• virtual int installSubProblem (BcpsModel \*mode)

intall subproblem

virtual int process (bool isRoot=false, bool rampUp=false)

Performing the bounding operation.

virtual int bound (BcpsModel \*model)

Bounding procedure.

virtual std::vector< CoinTriple< AlpsNodeDesc \*, AlpsNodeStatus, double >> branch ()

Takes the explicit description of the current active node and creates the children's descriptions, which contain information about how the branching is to be done.

int selectBranchObject (BlisModel \*model, bool &foundSol, int numPassesLeft)

Select a branching object based on give branching strategy.

virtual int chooseBranchingObject (BcpsModel \*)

To be defined.

• int generateConstraints (BlisModel \*model, BcpsConstraintPool &conPool)

Generate constraints.

• int callHeuristics (BlisModel \*model, bool onlyBeforeRoot=false)

Call heuristic to search solutions.

- void getViolatedConstraints (BlisModel \*model, const double \*currLpSolution, BcpsConstraintPool &conPool)
   Get violated constraints.
- BlisReturnStatus applyConstraints (BlisModel \*model, const double \*solution, BcpsConstraintPool &conPool)
   Select and apply constraints.
- BlisReturnStatus reducedCostFix (BlisModel \*model)

Fix and tighten varaibles based optimality conditions.

virtual AlpsEncoded \* encode () const

Encode this node for message passing.

virtual AlpsKnowledge \* decode (AlpsEncoded &) const

Decode a node from an encoded object.

virtual void convertToExplicit ()

Convert explicit description to difference, and vise-vesa.

## 4.21.1 Detailed Description

This is the class in which we are finally able to concretely define the bounding procedure.

Here we can assume that we have an LP solver and that the objects are cuts and variables, etc.

Definition at line 33 of file BlisSubTree.h.

#### 4.21.2 Constructor & Destructor Documentation

```
4.21.2.1 BlisTreeNode::BlisTreeNode() [inline]
```

Default constructor.

Definition at line 79 of file BlisTreeNode.h.

```
4.21.2.2 BlisTreeNode::BlisTreeNode(BlisModel*m) [inline]
```

Useful constructor.

Definition at line 85 of file BlisTreeNode.h.

4.21.2.3 BlisTreeNode::BlisTreeNode ( AlpsNodeDesc \*& desc ) [inline]

Useful constructor.

Definition at line 91 of file BlisTreeNode.h.

**4.21.2.4** virtual BlisTreeNode::~BlisTreeNode( ) [inline], [virtual]

Destructor.

Definition at line 98 of file BlisTreeNode.h.

## 4.21.3 Member Function Documentation

```
4.21.3.1 void BlisTreeNode::init() [inline]
```

Initilize member data when constructing a node.

Definition at line 103 of file BlisTreeNode.h.

4.21.3.2 AlpsTreeNode\* BlisTreeNode::createNewTreeNode( AlpsNodeDesc \*& desc ) const [virtual]

Create a new node based on given desc.

Implements AlpsTreeNode.

**4.21.3.3** virtual int BlisTreeNode::process (bool isRoot = false, bool rampUp = false) [virtual]

Performing the bounding operation.

Reimplemented from **BcpsTreeNode**.

```
4.21.3.4 virtual std::vector< CoinTriple<AlpsNodeDesc*, AlpsNodeStatus, double> > BlisTreeNode::branch ( ) [virtual]
```

Takes the explicit description of the current active node and creates the children's descriptions, which contain information about how the branching is to be done.

The stati of the children are AlpsNodeStatusCandidate.

Implements **BcpsTreeNode**.

4.21.3.5 int BlisTreeNode::selectBranchObject ( BlisModel \* model, bool & foundSol, int numPassesLeft )

Select a branching object based on give branching strategy.

4.21.3.6 virtual int BlisTreeNode::chooseBranchingObject ( BcpsModel \* ) [inline], [virtual]

To be defined.

Implements BcpsTreeNode.

Definition at line 139 of file BlisTreeNode.h.

94 Class Documentation

4.21.3.7 int BlisTreeNode::generateConstraints ( BlisModel \* model, BcpsConstraintPool & conPool )

Generate constraints.

4.21.3.8 int BlisTreeNode::callHeuristics ( BlisModel \* model, bool onlyBeforeRoot = false )

Call heuristic to search solutions.

0: no solution; 1: found solutions; 2: fathom this node. onlyBeforeRoot is for heuristics like feasibility pump.

4.21.3.9 void BlisTreeNode::getViolatedConstraints ( BlisModel \* model, const double \* currLpSolution, BcpsConstraintPool & conPool )

Get violated constraints.

4.21.3.10 BlisReturnStatus BlisTreeNode::applyConstraints ( BlisModel \* model, const double \* solution, BcpsConstraintPool & conPool )

Select and apply constraints.

4.21.3.11 BlisReturnStatus BlisTreeNode::reducedCostFix ( BlisModel \* model )

Fix and tighten varaibles based optimality conditions.

4.21.3.12 virtual AlpsEncoded\* BlisTreeNode::encode( ) const [virtual]

Encode this node for message passing.

Reimplemented from AlpsKnowledge.

4.21.3.13 virtual AlpsKnowledge\* BlisTreeNode::decode( AlpsEncoded & ) const [virtual]

Decode a node from an encoded object.

Reimplemented from AlpsKnowledge.

The documentation for this class was generated from the following files:

- · BlisSubTree.h
- · BlisTreeNode.h

# 4.22 BlisVariable Class Reference

Inheritance diagram for BlisVariable:

Collaboration diagram for BlisVariable:

## **Public Member Functions**

• virtual AlpsReturnStatus encode (AlpsEncoded \*encoded)

Pack to a encode object.

virtual AlpsKnowledge \* decode (AlpsEncoded &encoded) const

Decode a variable from an encoded object.

double getObjCoef ()

Return data.

void setData (int s, const int \*ind, const double \*val)

Set data.

#### **Protected Member Functions**

AlpsReturnStatus encodeBlis (AlpsEncoded \*encoded)

Pack Blis part into an encoded object.

• AlpsReturnStatus decodeBlis (AlpsEncoded &encoded)

Unpack Blis part from a encode object.

# 4.22.1 Detailed Description

Definition at line 31 of file BlisVariable.h.

## 4.22.2 Member Function Documentation

**4.22.2.1** AlpsReturnStatus BlisVariable::encodeBlis ( AlpsEncoded \* encoded ) [inline], [protected]

Pack Blis part into an encoded object.

Definition at line 106 of file BlisVariable.h.

**4.22.2.2** AlpsReturnStatus BlisVariable::decodeBlis ( AlpsEncoded & encoded ) [inline], [protected]

Unpack Blis part from a encode object.

Definition at line 119 of file BlisVariable.h.

**4.22.2.3** virtual AlpsReturnStatus BlisVariable::encode ( AlpsEncoded \* encoded ) [inline], [virtual]

Pack to a encode object.

Reimplemented from BcpsObject.

Definition at line 135 of file BlisVariable.h.

96 Class Documentation

4.22.2.4 virtual AlpsKnowledge\* BlisVariable::decode ( AlpsEncoded & encoded ) const [inline], [virtual]

Decode a variable from an encoded object.

Reimplemented from **BcpsObject**.

Definition at line 145 of file BlisVariable.h.

The documentation for this class was generated from the following file:

· BlisVariable.h

File Documentation

# Index

$\sim$ BlisBranchObjectInt	addNumConsUsed
BlisBranchObjectInt, 20	BlisConGenerator, 35
~BlisBranchStrategyBilevel	addNumIterations
BlisBranchStrategyBilevel, 22	BlisModel, 67
~BlisBranchStrategyMaxInf	addNumNodes
BlisBranchStrategyMaxInf, 24	BlisModel, 67
~BlisBranchStrategyPseudo	addNumSolutions
BlisBranchStrategyPseudo, 26	BlisHeuristic, 43
~BlisBranchStrategyRel	addNumStrong
BlisBranchStrategyRel, 28	BlisModel, 58
~BlisBranchStrategyStrong	addObjects
BlisBranchStrategyStrong, 29	BlisModel, 62
~BlisConGenerator	addTime
BlisConGenerator, 33	BlisConGenerator, 36
~BlisConstraint	BlisHeuristic, 44
BlisConstraint, 40	applyConstraints
~BlisHeurRound	BlisTreeNode, 94
BlisHeurRound, 46	atSolution
~BlisHeuristic	BlisConGenerator, 35
BlisHeuristic, 43	atSolution
~BlisModel	BlisConGenerator, 37
BlisModel, 56	avelterations_
~BlisNodeDesc	BlisModel, 73
BlisNodeDesc, 76	,
~BlisObjectInt	betterBranchObject
BlisObjectInt, 79	BlisBranchStrategyBilevel, 23
~BlisSolution	BlisBranchStrategyMaxInf, 25
BlisSolution, 90	BlisBranchStrategyPseudo, 26
$\sim$ BlisTreeNode	BlisBranchStrategyRel, 28
BlisTreeNode, 93	BlisBranchStrategyStrong, 30
	BlisBranchObjectBilevel, 17
activeNode_	BlisBranchObjectInt, 17
BlisModel, 70	$\sim$ BlisBranchObjectInt, 20
addCalls	BlisBranchObjectInt, 18, 20
BlisConGenerator, 36	branch, 20
BlisHeuristic, 44	clone, 20
addCutGenerator	decode, 21
BlisModel, 63	decodeBlis, 21
addHeuristic	encode, 21
BlisModel, 63	encodeBlis, 21
addNoConsCalls	getDown, 21
BlisConGenerator, 36	getUp, 21
addNoSolCalls	operator=, 20
BlisHeuristic, 44	print, 20
addNumConsGenerated	BlisBranchStrategyBilevel, 21
BlisConGenerator, 35	$\sim$ BlisBranchStrategyBilevel, 22

betterBranchObject, 23	normal_, 37
BlisBranchStrategyBilevel, 22	numConsGenerated, 35
clone, 23	numConsGenerated_, 37
createCandBranchObjects, 23	numConsUsed, 35
BlisBranchStrategyMaxInf, 23	numConsUsed_, 37
$\sim$ BlisBranchStrategyMaxInf, 24	operator=, 33
betterBranchObject, 25	setAtSolution, 35
BlisBranchStrategyMaxInf, 24	setCutGenerationFreq, 34
clone, 24	setName, 34
createCandBranchObjects, 24	setNormal, 34
BlisBranchStrategyPseudo, 25	setStrategy, 34
$\sim$ BlisBranchStrategyPseudo, 26	setWhenInfeasible, 35
betterBranchObject, 26	strategy, 34
BlisBranchStrategyPseudo, 26	strategy_, 37
clone, 26	time, 36
createCandBranchObjects, 27	time_, 38
setRelibility, 26	whenInfeasible, 35
BlisBranchStrategyRel, 27	whenInfeasible_, 37
~BlisBranchStrategyRel, 28	BlisConstraint, 38
betterBranchObject, 28	∼BlisConstraint, 40
BlisBranchStrategyRel, 28	BlisConstraint, 39, 40
clone, 28	createOsiRowCut, 40
createCandBranchObjects, 28	decode, 40
setRelibility, 28	decodeBlis, 40
BlisBranchStrategyStrong, 29	encode, 40
~BlisBranchStrategyStrong, 29	encodeBlis, 40
betterBranchObject, 30	hashing, 40
BlisBranchStrategyStrong, 29, 30	violation, 40
clone, 30	BlisHeurRound, 45
createCandBranchObjects, 30	~BlisHeurRound, 46
BlisConGenerator, 30	BlisHeurRound, 46
~BlisConGenerator, 33	matrix_, 47
addCalls, 36	matrixByRow_, 47
addNoConsCalls, 36	seed , 47
addNumConsGenerated, 35	setModel, 47
addNumConsUsed, 35	BlisHeuristic, 41
addTime, 36	~BlisHeuristic, 43
	addCalls, 44
atSolution, 35 atSolution, 37	addCalls, 44 addNoSolCalls, 44
BlisConGenerator, 33	addNumSolutions, 43
	addTime, 44
calls, 36	•
calls_, 38	BlisHeuristic, 42, 43
cutGenerationFreq, 34	calls, 44
cutGenerationFrequency_, 37	calls_, 45
generateConstraints, 33	clone, 43
generator, 35	name, 43
generator_, 36	noSolCalls, 44
getModel, 33	noSolsCalls_, 45
model_, 36	numSolutions, 44
name, 34	numSolutions_, 45
name_, 37	setHeurCallFrequency, 43
noConsCalls, 36	setModel, 43
noConsCalls_, 38	setStrategy, 43
normal, 34	strategy_, 44

time, 44	deleteObjects, 62
time_, 45	encode, 68
BlisMessage, 47	encodeBlis, 67 fathomAllNodes, 67
blisMessageHandler BlisModel, 67	•
•	feasibleSolution, 61
blisMessageHandler_ BlisModel, 72	feasibleSolutionHeur, 61
	generators_, 71 getAveIterations, 66
blisMessages BlisModel, 67	getColLower, 59
	getColUpper, 59
blisMessages_ BlisModel, 72	getConRandoms, 66
BlisModel, 48	getCutGenerationFrequency, 65
~BlisModel, 56	getCutStrategy, 65
activeNode_, 70	getCutoff, 60
addCutGenerator, 63	getDenseConCutoff, 65
addHeuristic, 63	getIntColIndices, 63
addNumIterations, 67	getIntObjIndices, 62
addNumNodes, 67	getLpObjValue, 60
addNumStrong, 58	getLpSolution, 60
addObjects, 62	getMaxNumCons, 64
avelterations, 73	getNumBranchResolve, 58
blisMessageHandler, 67	getNumCols, 59
blisMessageHandler_, 72	getNumHeurSolutions, 60
blisMessages, 67	getNumIntObjects, 63
blisMessages_, 72	getNumIterations, 66
BlisModel, 56	getNumNodes, 66
BlisPar, 67	getNumOldConstraints, 64
BlisPar_, 72	getNumRows, 59
boundingPass_, 73	getNumSolutions, 60
branchStrategy, 61	getNumStrong, 58
branchStrategy_, 70	getObjCoef, 59
checkInteger, 63	getOldConstraintsSize, 64
clearSharedObjectMark, 62	getSolver, 58
colMatrix_, 69	gutsOfDestructor, 56
conLB, 59	heurCallFrequency_, 74
conRandoms_, 72	heurStrategy_, 74
constraintPool, 64	heuristics, 63
constraintPool_, 71	heuristics_, 71
constraintPoolReceive, 64	importModel, 57
constraintPoolReceive_, 73	incObjValue_, 70
constraintPoolSend, 64	incumbent, 60
constraintPoolSend_, 73	inputVar_, 69
createIntgerObjects, 62	integerTol_, 73
createObjects, 56	isRoot_, 73
createRoot, 57	leafToRootPath, 74
currAbsGap_, 74	lpSolver_, 69
currRelGap_, 74	maxNumCons_, 71
cutGenerators, 63	modelLog, 66
cutStrategy_, 71	newCutPool_, 74
cutoff_, 70	nodeLog, 67
cutofflnc_, 70	numBranchResolve_, 71
decodeBlis, 67	numCutConcretors, 64
decodeToSelf, 68	numCutGenerators_, 71
delOldConstraints, 65	numHeuristics, 63

numHeuristics_, 71	unpackSharedKnowledge, 68
numIntObjects_, 69	unpackSharedVariables, 68
numIterations_, 72	userFeasibleSolution, 61
numNodes_, 72	varLB, 59
numObjects, 61	varLB_, 69
numObjects_, 70	writeParameters, 57
numOldConstraints , 72	BlisNodeDesc, 74
numStrong_, 71	∼BlisNodeDesc, 76
objSense_, 69	BlisNodeDesc, 75
objects, 62	decode, 77
objects_, 70	decodeBlis, 77
oldConstraints, 65	encode, 77
oldConstraints_, 72	encodeBlis, 77
oldConstraintsSize_, 72	getBasis, 76
optimalAbsGap_, 73	getBranchedDir, 76
optimalRelGap_, 73	getBranchedInd, 76
origLpSolver , 69	getBranchedVal, 77
packSharedConstraints, 68	setBasis, 76
packSharedKnowlege, 68	setBranchedDir, 76
packSharedPseudocost, 68	setBranchedInd, 76
packSharedVariables, 68	setBranchedVal, 76
passInPriorities, 66	BlisObjectInt, 77
postprocess, 57	~BlisObjectInt, 77
preprocess, 57	BlisObjectInt, 79
·	-
presolvedLpSolver_, 69 priority, 66	breakEven, 81 breakEven_, 81
•	clone, 79
priority_, 70 readInstance, 56	columnIndex, 81
readParameters, 57	columnIndex_, 81
registerKnowledge, 68	createBranchObject, 80
resolve, 58	feasibleRegion, 80
setActiveNode, 58	infeasibility, 80
setBranchingMethod, 61	notPreferredNewFeasible, 80
setCutStrategy, 65	operator=, 79
setCutoff, 61	original laner 81
setDenseConCutoff, 66	originalUpper_, 81
setMaxNumCons, 64	preferredNewFeasible, 80
setNumBranchResolve, 59	pseudocost, 81
setNumObjects, 62	pseudocost_, 82
setNumOldConstraints, 64	resetBounds, 80
setOldConstraints, 65	setBreakEven, 81
setOldConstraintsSize, 65	BlisPar
setSharedObjectMark, 62	BlisModel, 67
setSolEstimate, 58	BlisPar_
setSolver, 58	BlisModel, 72
setupSelf, 57	BlisParams, 82
sharedObjectMark_, 70	BlisParams, 85
solver, 58	branchStrategy, 84
startConLB, 60	chrParams, 83
startVarLB, 59	createKeywordList, 85
storeSolution, 60	cutCliqueStrategy, 84
tempVarLBPos, 60	cutFactor, 84
tempVarLBPos_, 73	cutGenerationFrequency, 84
unpackSharedConstraints, 68	cutRampUp, 83

cutStrategy, 84	BlisTreeNode, 91
cutoff, 84	$\sim$ BlisTreeNode, 93
cutoffInc, 84	applyConstraints, 94
dblParams, 84	BlisTreeNode, 92
denseConFactor, 84	branch, 93
difference, 84	callHeuristics, 94
heurCallFrequency, 84	chooseBranchingObject, 93
heurStrategy, 84	createNewTreeNode, 93
intParams, 84	decode, 94
integerTol, 84	encode, 94
lookAhead, 84	generateConstraints, 93
objSense, 84	getViolatedConstraints, 94
optimalAbsGap, 84	init, 93
optimalRelGap, 84	process, 93
pack, 85	reducedCostFix, 94
presolve, 83	selectBranchObject, 93
pseudoRelibility, 84	BlisVariable, 94
pseudoWeight, 84	decode, 95
quickCutPass, 84	decodeBlis, 95
scaleConFactor, 84	encode, 95
setDefaultEntries, 85	encodeBlis, 95
shareConstraints, 83	boundingPass_
sharePcostDepth, 84	BlisModel, 73
sharePcostFrequency, 84	branch
sharePseudocostRampUp, 84	BlisBranchObjectInt, 20
sharePseudocostSearch, 84	BlisTreeNode, 93
shareVariables, 83	branchStrategy
strArrayParams, 85	BlisModel, 61
strParams, 84	BlisParams, 84
strongCandSize, 84	branchStrategy_
tailOff, 84	BlisModel, 70
unpack, 85	breakEven
BlisPresolve, 86	BlisObjectInt, 81
BlisPseudocost, 86	breakEven
	<del>-</del>
BlisPseudocost, 87	BlisObjectInt, 81
decode, 89	o all Houristian
decodeFrom, 89	callHeuristics
encode, 89	BlisTreeNode, 94
encodeTo, 89	calls
getDownCost, 88	BlisConGenerator, 36
getDownCount, 88	BlisHeuristic, 44
getScore, 88	calls_
getUpCost, 88	BlisConGenerator, 38
getUpCount, 88	BlisHeuristic, 45
setScore, 88	checkInteger
setWeight, 88	BlisModel, 63
update, 88	chooseBranchingObject
BlisSolution, 89	BlisTreeNode, 93
∼BlisSolution, 90	chrParams
BlisSolution, 90	BlisParams, 83
decode, 90	clearSharedObjectMark
encode, 90	BlisModel, 62
print, 90	clone
BlisStrong, 91	BlisBranchObjectInt, 20

BlisBranchStrategyBilevel, 23	BlisParams, 84
BlisBranchStrategyMaxInf, 24	cutFactor
BlisBranchStrategyPseudo, 26	BlisParams, 84
BlisBranchStrategyRel, 28	cutGenerationFreq
BlisBranchStrategyStrong, 30	BlisConGenerator, 34
BlisHeuristic, 43	cutGenerationFrequency
BlisObjectInt, 79	BlisParams, 84
colMatrix_	cutGenerationFrequency_
BlisModel, 69	BlisConGenerator, 37
columnIndex	cutGenerators
BlisObjectInt, 81	BlisModel, 63
columnIndex_	cutRampUp
BlisObjectInt, 81	BlisParams, 83
conLB	cutStrategy
BlisModel, 59	BlisParams, 84
conRandoms_	cutStrategy_
BlisModel, 72	BlisModel, 71
constraintPool	cutoff
BlisModel, 64	BlisParams, 84
constraintPool_	cutoff_
BlisModel, 71	BlisModel, 70
constraintPoolReceive	cutoffInc
BlisModel, 64	BlisParams, 84
constraintPoolReceive_	cutoffInc_
BlisModel, 73	BlisModel, 70
constraintPoolSend	
BlisModel, 64	dblParams
constraintPoolSend	BlisParams, 84
BlisModel, 73	decode
BlisModel, 73 createBranchObject	
createBranchObject	decode  BlisBranchObjectInt, 21  BlisConstraint, 40
createBranchObject BlisObjectInt, 80	BlisBranchObjectInt, 21
createBranchObject	BlisBranchObjectInt, 21 BlisConstraint, 40
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList BlisParams, 85 createNewTreeNode	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67 BlisNodeDesc, 77
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList BlisParams, 85 createNewTreeNode BlisTreeNode, 93	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67 BlisNodeDesc, 77 BlisVariable, 95 decodeFrom
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList BlisParams, 85 createNewTreeNode BlisTreeNode, 93 createObjects	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67 BlisNodeDesc, 77 BlisVariable, 95
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList BlisParams, 85 createNewTreeNode BlisTreeNode, 93	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67 BlisNodeDesc, 77 BlisVariable, 95 decodeFrom BlisPseudocost, 89 decodeToSelf
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList BlisParams, 85 createNewTreeNode BlisTreeNode, 93 createObjects BlisModel, 56 createOsiRowCut	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67 BlisNodeDesc, 77 BlisVariable, 95 decodeFrom BlisPseudocost, 89
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList BlisParams, 85 createNewTreeNode BlisTreeNode, 93 createObjects BlisModel, 56	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67 BlisNodeDesc, 77 BlisVariable, 95 decodeFrom BlisPseudocost, 89 decodeToSelf BlisModel, 68 delOldConstraints
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList BlisParams, 85 createNewTreeNode BlisTreeNode, 93 createObjects BlisModel, 56 createOsiRowCut BlisConstraint, 40 createRoot	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67 BlisNodeDesc, 77 BlisVariable, 95 decodeFrom BlisPseudocost, 89 decodeToSelf BlisModel, 68 delOldConstraints BlisModel, 65
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList BlisParams, 85 createNewTreeNode BlisTreeNode, 93 createObjects BlisModel, 56 createOsiRowCut BlisConstraint, 40 createRoot BlisModel, 57	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67 BlisNodeDesc, 77 BlisVariable, 95 decodeFrom BlisPseudocost, 89 decodeToSelf BlisModel, 68 delOldConstraints BlisModel, 65 deleteObjects
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList BlisParams, 85 createNewTreeNode BlisTreeNode, 93 createObjects BlisModel, 56 createOsiRowCut BlisConstraint, 40 createRoot BlisModel, 57 currAbsGap_	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67 BlisNodeDesc, 77 BlisVariable, 95 decodeFrom BlisPseudocost, 89 decodeToSelf BlisModel, 68 delOldConstraints BlisModel, 65
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList BlisParams, 85 createNewTreeNode BlisTreeNode, 93 createObjects BlisModel, 56 createOsiRowCut BlisConstraint, 40 createRoot BlisModel, 57 currAbsGap_ BlisModel, 74	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67 BlisNodeDesc, 77 BlisVariable, 95 decodeFrom BlisPseudocost, 89 decodeToSelf BlisModel, 68 delOldConstraints BlisModel, 65 deleteObjects BlisModel, 62 denseConFactor
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList BlisParams, 85 createNewTreeNode BlisTreeNode, 93 createObjects BlisModel, 56 createOsiRowCut BlisConstraint, 40 createRoot BlisModel, 57 currAbsGap_ BlisModel, 74 currRelGap_	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67 BlisNodeDesc, 77 BlisVariable, 95 decodeFrom BlisPseudocost, 89 decodeToSelf BlisModel, 68 delOldConstraints BlisModel, 65 deleteObjects BlisModel, 62 denseConFactor BlisParams, 84
createBranchObject BlisObjectInt, 80 createCandBranchObjects BlisBranchStrategyBilevel, 23 BlisBranchStrategyMaxInf, 24 BlisBranchStrategyPseudo, 27 BlisBranchStrategyRel, 28 BlisBranchStrategyStrong, 30 createIntgerObjects BlisModel, 62 createKeywordList BlisParams, 85 createNewTreeNode BlisTreeNode, 93 createObjects BlisModel, 56 createOsiRowCut BlisConstraint, 40 createRoot BlisModel, 57 currAbsGap_ BlisModel, 74	BlisBranchObjectInt, 21 BlisConstraint, 40 BlisNodeDesc, 77 BlisPseudocost, 89 BlisSolution, 90 BlisTreeNode, 94 BlisVariable, 95 decodeBlis BlisBranchObjectInt, 21 BlisConstraint, 40 BlisModel, 67 BlisNodeDesc, 77 BlisVariable, 95 decodeFrom BlisPseudocost, 89 decodeToSelf BlisModel, 68 delOldConstraints BlisModel, 65 deleteObjects BlisModel, 62 denseConFactor

encode	BlisModel, 65
BlisBranchObjectInt, 21	getCutoff
BlisConstraint, 40	BlisModel, 60
BlisModel, 68	getDenseConCutoff
BlisNodeDesc, 77	BlisModel, 65
BlisPseudocost, 89	getDown
BlisSolution, 90	BlisBranchObjectInt, 21
BlisTreeNode, 94	getDownCost
BlisVariable, 95	BlisPseudocost, 88
encodeBlis	getDownCount
BlisBranchObjectInt, 21	BlisPseudocost, 88
BlisConstraint, 40	getIntColIndices
BlisModel, 67	BlisModel, 63
BlisNodeDesc, 77	getIntObjIndices
BlisVariable, 95	BlisModel, 62
encodeTo	getLpObjValue
BlisPseudocost, 89	BlisModel, 60
	getLpSolution
fathomAllNodes	BlisModel, 60
BlisModel, 67	getMaxNumCons
feasibleRegion	BlisModel, 64
BlisObjectInt, 80	getModel
feasibleSolution	BlisConGenerator, 33
BlisModel, 61	getNumBranchResolve
feasibleSolutionHeur	BlisModel, 58
BlisModel, 61	getNumCols
	BlisModel, 59
generateConstraints	getNumHeurSolutions
BlisConGenerator, 33	BlisModel, 60
BlisTreeNode, 93	getNumIntObjects
generator	BlisModel, 63
BlisConGenerator, 35	getNumIterations
generator_	BlisModel, 66
BlisConGenerator, 36	
generators_	getNumNodes
BlisModel, 71	BlisModel, 66
getAveIterations	getNumOldConstraints
BlisModel, 66	BlisModel, 64
getBasis	getNumRows
BlisNodeDesc, 76	BlisModel, 59
getBranchedDir	getNumSolutions
BlisNodeDesc, 76	BlisModel, 60
getBranchedInd	getNumStrong
BlisNodeDesc, 76	BlisModel, 58
getBranchedVal	getObjCoef
BlisNodeDesc, 77	BlisModel, 59
getColLower	getOldConstraintsSize
BlisModel, 59	BlisModel, 64
getColUpper	getScore
BlisModel, 59	BlisPseudocost, 88
getConRandoms	getSolver
BlisModel, 66	BlisModel, 58
getCutGenerationFrequency	getUp
BlisModel, 65	BlisBranchObjectInt, 21
getCutStrategy	getUpCost

BlisPseudocost, 88	maxNumCons_
getUpCount	BlisModel, 71
BlisPseudocost, 88	model_
getViolatedConstraints	BlisConGenerator, 36
BlisTreeNode, 94	modelLog
gutsOfDestructor	BlisModel, 66
BlisModel, 56	
	name
hashing	BlisConGenerator, 34
BlisConstraint, 40	BlisHeuristic, 43
heurCallFrequency	name_
BlisParams, 84	BlisConGenerator, 37
heurCallFrequency_	newCutPool_
BlisModel, 74	BlisModel, 74
heurStrategy	noConsCalls
BlisParams, 84	BlisConGenerator, 36
heurStrategy_	noConsCalls_
BlisModel, 74	BlisConGenerator, 38
heuristics	noSolCalls
BlisModel, 63	BlisHeuristic, 44
heuristics_	noSolsCalls_
BlisModel, 71	BlisHeuristic, 45
Survey and Mandal	nodeLog
importModel	BlisModel, 67
BlisModel, 57	normal
incObjValue_	BlisConGenerator, 34
BlisModel, 70	normal_
incumbent CO	BlisConGenerator, 37
BlisModel, 60	notPreferredNewFeasible
infeasibility	BlisObjectInt, 80
BlisObjectInt, 80	numBranchResolve_
init	BlisModel, 71
BlisTreeNode, 93	numConsGenerated
inputVar_	BlisConGenerator, 35
BlisModel, 69 intParams	numConsGenerated_
	BlisConGenerator, 37
BlisParams, 84	numConsUsed
integerTol	BlisConGenerator, 35
BlisParams, 84	numConsUsed_
integerTol_	BlisConGenerator, 37
BlisModel, 73 isRoot	numCutGenerators
BlisModel, 73	BlisModel, 64
DilSiviodei, 73	numCutGenerators
leafToRootPath	BlisModel, 71
BlisModel, 74	numHeuristics
lookAhead	BlisModel, 63
BlisParams, 84	numHeuristics
lpSolver_	BlisModel, 71
BlisModel, 69	numIntObjects_
	BlisModel, 69
matrix	numIterations_
BlisHeurRound, 47	BlisModel, 72
matrixByRow	numNodes
BlisHeurRound, 47	BlisModel, 72
,	- ,

numObjects	BlisModel, 68
BlisModel, 61	passInPriorities
numObjects_	BlisModel, 66
BlisModel, 70	postprocess
numOldConstraints_	BlisModel, 57
BlisModel, 72	preferredNewFeasible
numSolutions	BlisObjectInt, 80
BlisHeuristic, 44	preprocess
numSolutions_	BlisModel, 57
BlisHeuristic, 45	presolve
numStrong_	BlisParams, 83
BlisModel, 71	presolvedLpSolver_
1:0	BlisModel, 69
objSense	print
BlisParams, 84	BlisBranchObjectInt, 20
objSense_	BlisSolution, 90
BlisModel, 69	priority
objects	BlisModel, 66
BlisModel, 62	priority_
objects_	BlisModel, 70
BlisModel, 70	process
oldConstraints	BlisTreeNode, 93
BlisModel, 65	pseudoRelibility
oldConstraints_	BlisParams, 84
BlisModel, 72	pseudoWeight
oldConstraintsSize_	BlisParams, 84
BlisModel, 72	pseudocost
operator=	BlisObjectInt, 81
BlisBranchObjectInt, 20	pseudocost_
BlisConGenerator, 33	BlisObjectInt, 82
BlisObjectInt, 79	
optimalAbsGap	quickCutPass
BlisParams, 84	BlisParams, 84
optimalAbsGap_	
BlisModel, 73	readInstance
optimalRelGap	BlisModel, 56
BlisParams, 84	readParameters
optimalRelGap_	BlisModel, 57
BlisModel, 73	reducedCostFix
origLpSolver_	BlisTreeNode, 94
BlisModel, 69	registerKnowledge
originalLower_	BlisModel, 68
BlisObjectInt, 81	resetBounds
originalUpper_	BlisObjectInt, 80
BlisObjectInt, 81	resolve
	BlisModel, 58
pack	
BlisParams, 85	scaleConFactor
packSharedConstraints	BlisParams, 84
BlisModel, 68	seed_
packSharedKnowlege	BlisHeurRound, 47
BlisModel, 68	selectBranchObject
packSharedPseudocost	BlisTreeNode, 93
BlisModel, 68	setActiveNode
packSharedVariables	BlisModel, 58
	•

setAtSolution	setSolver
BlisConGenerator, 35	BlisModel, 58
setBasis	setStrategy
BlisNodeDesc, 76	BlisConGenerator, 34
setBranchedDir	BlisHeuristic, 43
BlisNodeDesc, 76	setWeight
setBranchedInd	BlisPseudocost, 88
BlisNodeDesc, 76	setWhenInfeasible
setBranchedVal	BlisConGenerator, 35
BlisNodeDesc, 76	setupSelf
setBranchingMethod	BlisModel, 57
BlisModel, 61	shareConstraints
setBreakEven	BlisParams, 83
BlisObjectInt, 81	sharePcostDepth
setCutGenerationFreq	BlisParams, 84
BlisConGenerator, 34	sharePcostFrequency
setCutStrategy	BlisParams, 84
BlisModel, 65	sharePseudocostRampUp
setCutoff	BlisParams, 84
BlisModel, 61	sharePseudocostSearch
setDefaultEntries	BlisParams, 84
BlisParams, 85	shareVariables
setDenseConCutoff	BlisParams, 83
BlisModel, 66	sharedObjectMark_
setHeurCallFrequency	BlisModel, 70
BlisHeuristic, 43	solver
setMaxNumCons	BlisModel, 58
BlisModel, 64	startConLB
setModel	BlisModel, 60
BlisHeurRound, 47	startVarLB
BlisHeuristic, 43	BlisModel, 59
setName	storeSolution
BlisConGenerator, 34	BlisModel, 60
setNormal	strArrayParams
BlisConGenerator, 34	BlisParams, 85
setNumBranchResolve	strParams
BlisModel, 59	BlisParams, 84
setNumObjects	strategy
BlisModel, 62	BlisConGenerator, 34
setNumOldConstraints	strategy_
BlisModel, 64	BlisConGenerator, 37
setOldConstraints	BlisHeuristic, 44
BlisModel, 65	strongCandSize
setOldConstraintsSize	_
	RlicParame 84
	BlisParams, 84
BlisModel, 65	,
BlisModel, 65 setRelibility	tailOff
BlisModel, 65 setRelibility BlisBranchStrategyPseudo, 26	tailOff BlisParams, 84
BlisModel, 65 setRelibility BlisBranchStrategyPseudo, 26 BlisBranchStrategyRel, 28	tailOff BlisParams, 84 tempVarLBPos
BlisModel, 65 setRelibility BlisBranchStrategyPseudo, 26 BlisBranchStrategyRel, 28 setScore	tailOff BlisParams, 84 tempVarLBPos BlisModel, 60
BlisModel, 65 setRelibility BlisBranchStrategyPseudo, 26 BlisBranchStrategyRel, 28 setScore BlisPseudocost, 88	tailOff BlisParams, 84 tempVarLBPos BlisModel, 60 tempVarLBPos_
BlisModel, 65 setRelibility BlisBranchStrategyPseudo, 26 BlisBranchStrategyRel, 28 setScore BlisPseudocost, 88 setSharedObjectMark	tailOff BlisParams, 84 tempVarLBPos BlisModel, 60 tempVarLBPos_ BlisModel, 73
BlisModel, 65 setRelibility BlisBranchStrategyPseudo, 26 BlisBranchStrategyRel, 28 setScore BlisPseudocost, 88 setSharedObjectMark BlisModel, 62	tailOff BlisParams, 84 tempVarLBPos BlisModel, 60 tempVarLBPos_ BlisModel, 73 time
BlisModel, 65 setRelibility BlisBranchStrategyPseudo, 26 BlisBranchStrategyRel, 28 setScore BlisPseudocost, 88 setSharedObjectMark	tailOff BlisParams, 84 tempVarLBPos BlisModel, 60 tempVarLBPos_ BlisModel, 73

time\_ BlisConGenerator, 38 BlisHeuristic, 45 unpack BlisParams, 85 unpackSharedConstraints BlisModel, 68 unpackSharedKnowledge BlisModel, 68 unpackSharedVariables BlisModel, 68 update BlisPseudocost, 88 userFeasibleSolution BlisModel, 61 varLB BlisModel, 59 varLB BlisModel, 69 violation BlisConstraint, 40 whenInfeasible BlisConGenerator, 35 whenInfeasible\_ BlisConGenerator, 37 writeParameters BlisModel, 57