Cbc

trunk

Generated by Doxygen 1.8.5

Mon Oct 21 2013 19:03:07

ii CONTENTS

Contents

1	Todo List							
2	Nam	nespace Index	2					
	2.1	Namespace List	2					
3	Hiera	rarchical Index	2					
	3.1	Class Hierarchy	2					
4	Clas	ss Index	10					
	4.1	Class List	10					
5	File	Index	17					
	5.1	File List	17					
6	Nam	nespace Documentation	20					
	6.1	CbcCbcParamUtils Namespace Reference	20					
		6.1.1 Function Documentation	20					
	6.2	CbcGenParamUtils Namespace Reference	21					
		6.2.1 Function Documentation	21					
	6.3	CbcOsiParamUtils Namespace Reference	22					
		6.3.1 Function Documentation	22					
7	Clas	Class Documentation 22						
7.1 ampl_info Struct Reference		ampl_info Struct Reference	22					
		7.1.1 Detailed Description	23					
		7.1.2 Member Data Documentation	23					
	7.2	CbcGenCtlBlk::babState_struct Struct Reference	26					
		7.2.1 Detailed Description	27					
		7.2.2 Member Data Documentation	27					
	7.3	CbcBaseModel Class Reference	27					
		7.3.1 Detailed Description	27					
		7.3.2 Constructor & Destructor Documentation	27					
	7.4	CbcBranchAllDifferent Class Reference	28					
		7.4.1 Detailed Description	29					
		7.4.2 Constructor & Destructor Documentation	29					
		7.4.3 Member Function Documentation	29					
		7.4.4 Member Data Documentation	29					
	7.5	CbcBranchCut Class Reference	30					

	7.5.1	Detailed Description	31
	7.5.2	Constructor & Destructor Documentation	31
	7.5.3	Member Function Documentation	31
7.6	CbcBra	anchDecision Class Reference	32
	7.6.1	Detailed Description	33
	7.6.2	Constructor & Destructor Documentation	34
	7.6.3	Member Function Documentation	34
	7.6.4	Member Data Documentation	35
7.7	CbcBra	anchDefaultDecision Class Reference	36
	7.7.1	Detailed Description	37
	7.7.2	Constructor & Destructor Documentation	37
	7.7.3	Member Function Documentation	37
7.8	CbcBra	anchDynamicDecision Class Reference	38
	7.8.1	Detailed Description	39
	7.8.2	Constructor & Destructor Documentation	39
	7.8.3	Member Function Documentation	39
7.9	CbcBra	anchingObject Class Reference	40
	7.9.1	Detailed Description	43
	7.9.2	Constructor & Destructor Documentation	43
	7.9.3	Member Function Documentation	43
	7.9.4	Member Data Documentation	46
7.10	CbcBra	anchToFixLots Class Reference	47
	7.10.1	Detailed Description	48
	7.10.2	Constructor & Destructor Documentation	48
	7.10.3	Member Function Documentation	48
	7.10.4	Member Data Documentation	49
7.11	CbcCb	cParam Class Reference	50
	7.11.1	Detailed Description	51
	7.11.2	Member Enumeration Documentation	51
	7.11.3	Constructor & Destructor Documentation	52
	7.11.4	Member Function Documentation	53
7.12	CbcClid	que Class Reference	54
	7.12.1	Detailed Description	55
	7.12.2	Constructor & Destructor Documentation	56
	7.12.3	Member Function Documentation	56
	7.12.4	Member Data Documentation	57
7.13	CbcClid	queBranchingObject Class Reference	58

iv CONTENTS

	7.13.1	Detailed Description	59
	7.13.2	Constructor & Destructor Documentation	59
	7.13.3	Member Function Documentation	59
7.14	CbcCo	mpare Class Reference	60
	7.14.1	Detailed Description	61
	7.14.2	Constructor & Destructor Documentation	61
	7.14.3	Member Function Documentation	61
	7.14.4	Member Data Documentation	61
7.15	CbcCo	mpareBase Class Reference	61
	7.15.1	Detailed Description	62
	7.15.2	Constructor & Destructor Documentation	62
	7.15.3	Member Function Documentation	63
	7.15.4	Member Data Documentation	64
7.16	CbcCo	mpareDefault Class Reference	64
	7.16.1	Detailed Description	66
	7.16.2	Constructor & Destructor Documentation	66
	7.16.3	Member Function Documentation	66
	7.16.4	Member Data Documentation	68
7.17	CbcCo	mpareDepth Class Reference	69
	7.17.1	Detailed Description	69
	7.17.2	Constructor & Destructor Documentation	70
	7.17.3	Member Function Documentation	70
7.18	CbcCo	mpareEstimate Class Reference	70
	7.18.1	Detailed Description	71
	7.18.2	Constructor & Destructor Documentation	71
	7.18.3	Member Function Documentation	71
7.19	CbcCo	mpareObjective Class Reference	71
	7.19.1	Detailed Description	72
	7.19.2	Constructor & Destructor Documentation	72
	7.19.3	Member Function Documentation	72
7.20	CbcCo	nsequence Class Reference	73
	7.20.1	Detailed Description	73
	7.20.2	Constructor & Destructor Documentation	73
	7.20.3	Member Function Documentation	73
7.21	CbcCo	untRowCut Class Reference	74
	7.21.1	Detailed Description	75
	7.21.2	Constructor & Destructor Documentation	75

	7.21.3 Member Function Documentation	 75
7.22	CbcCutBranchingObject Class Reference	 76
	7.22.1 Detailed Description	 77
	7.22.2 Constructor & Destructor Documentation	 77
	7.22.3 Member Function Documentation	 78
	7.22.4 Member Data Documentation	 79
7.23	CbcCutGenerator Class Reference	 79
	7.23.1 Detailed Description	 82
	7.23.2 Constructor & Destructor Documentation	 82
	7.23.3 Member Function Documentation	 83
7.24	CbcCutModifier Class Reference	 90
	7.24.1 Detailed Description	 90
	7.24.2 Constructor & Destructor Documentation	 90
	7.24.3 Member Function Documentation	 91
7.25	CbcCutSubsetModifier Class Reference	 91
	7.25.1 Detailed Description	 92
	7.25.2 Constructor & Destructor Documentation	 92
	7.25.3 Member Function Documentation	 92
	7.25.4 Member Data Documentation	 93
7.26	CbcDummyBranchingObject Class Reference	 93
	7.26.1 Detailed Description	 94
	7.26.2 Constructor & Destructor Documentation	 94
	7.26.3 Member Function Documentation	 94
7.27	CbcDynamicPseudoCostBranchingObject Class Reference	 95
	7.27.1 Detailed Description	 97
	7.27.2 Constructor & Destructor Documentation	 97
	7.27.3 Member Function Documentation	 97
	7.27.4 Member Data Documentation	 99
7.28	CbcEventHandler Class Reference	 99
	7.28.1 Detailed Description	 100
	7.28.2 Member Typedef Documentation	 100
	7.28.3 Member Enumeration Documentation	 101
	7.28.4 Constructor & Destructor Documentation	 101
	7.28.5 Member Function Documentation	 102
	7.28.6 Member Data Documentation	 102
7.29	CbcFathom Class Reference	 103
	7.29.1 Detailed Description	 104

vi CONTENTS

	7.29.2	Constructor & Destructor Documentation
	7.29.3	Member Function Documentation
	7.29.4	Member Data Documentation
7.30	CbcFat	homDynamicProgramming Class Reference
	7.30.1	Detailed Description
	7.30.2	Constructor & Destructor Documentation
	7.30.3	Member Function Documentation
	7.30.4	Member Data Documentation
7.31	CbcFea	asibilityBase Class Reference
	7.31.1	Detailed Description
	7.31.2	Constructor & Destructor Documentation
	7.31.3	Member Function Documentation
7.32	CbcFix	ingBranchingObject Class Reference
	7.32.1	Detailed Description
	7.32.2	Constructor & Destructor Documentation
	7.32.3	Member Function Documentation
7.33	CbcFix	Variable Class Reference
	7.33.1	Detailed Description
	7.33.2	Constructor & Destructor Documentation
	7.33.3	Member Function Documentation
	7.33.4	Member Data Documentation
7.34	CbcFol	lowOn Class Reference
	7.34.1	Detailed Description
	7.34.2	Constructor & Destructor Documentation
	7.34.3	Member Function Documentation
	7.34.4	Member Data Documentation
7.35	CbcFul	NodeInfo Class Reference
	7.35.1	Detailed Description
	7.35.2	Constructor & Destructor Documentation
	7.35.3	Member Function Documentation
	7.35.4	Member Data Documentation
7.36	CbcGe	nCtlBlk Class Reference
	7.36.1	Detailed Description
	7.36.2	Member Enumeration Documentation
	7.36.3	Constructor & Destructor Documentation
	7.36.4	Member Function Documentation
	7.36.5	Friends And Related Function Documentation

CONTENTS vii

142
· · · · · -
143
143
147
148
148
152
155
156
156
156
159
159
159
160
161
163
163
163
165
166
167
167
167

VIII CONTENTS

	7.44.3	Member Function Documentation
7.45	CbcHe	uristicDiveGuided Class Reference
	7.45.1	Detailed Description
	7.45.2	Constructor & Destructor Documentation
	7.45.3	Member Function Documentation
7.46	CbcHei	uristicDiveLineSearch Class Reference
	7.46.1	Detailed Description
	7.46.2	Constructor & Destructor Documentation
	7.46.3	Member Function Documentation
7.47	CbcHei	uristicDivePseudoCost Class Reference
	7.47.1	Detailed Description
	7.47.2	Constructor & Destructor Documentation
	7.47.3	Member Function Documentation
7.48	CbcHei	uristicDiveVectorLength Class Reference
	7.48.1	Detailed Description
	7.48.2	Constructor & Destructor Documentation
	7.48.3	Member Function Documentation
7.49	CbcHei	uristicDW Class Reference
	7.49.1	Detailed Description
	7.49.2	Member Typedef Documentation
	7.49.3	Constructor & Destructor Documentation
	7.49.4	Member Function Documentation
	7.49.5	Member Data Documentation
7.50	CbcHei	uristicDynamic3 Class Reference
	7.50.1	Detailed Description
	7.50.2	Constructor & Destructor Documentation
	7.50.3	Member Function Documentation
7.51	CbcHe	uristicFPump Class Reference
	7.51.1	Detailed Description
	7.51.2	Constructor & Destructor Documentation
	7.51.3	Member Function Documentation
	7.51.4	Member Data Documentation
7.52	CbcHei	uristicGreedyCover Class Reference
	7.52.1	Detailed Description
	7.52.2	Constructor & Destructor Documentation
	7.52.3	Member Function Documentation
	7.52.4	Member Data Documentation

CONTENTS ix

7.53	CbcHe	uristicGreedyEquality Class Reference
	7.53.1	Detailed Description
	7.53.2	Constructor & Destructor Documentation
	7.53.3	Member Function Documentation
	7.53.4	Member Data Documentation
7.54	CbcHe	uristicGreedySOS Class Reference
	7.54.1	Detailed Description
	7.54.2	Constructor & Destructor Documentation
	7.54.3	Member Function Documentation
	7.54.4	Member Data Documentation
7.55	CbcHe	uristicJustOne Class Reference
	7.55.1	Detailed Description
	7.55.2	Constructor & Destructor Documentation
	7.55.3	Member Function Documentation
	7.55.4	Member Data Documentation
7.56	CbcHe	uristicLocal Class Reference
	7.56.1	Detailed Description
	7.56.2	Constructor & Destructor Documentation
	7.56.3	Member Function Documentation
	7.56.4	Member Data Documentation
7.57	CbcHe	uristicNaive Class Reference
	7.57.1	Detailed Description
	7.57.2	Constructor & Destructor Documentation
	7.57.3	Member Function Documentation
	7.57.4	Member Data Documentation
7.58	CbcHe	uristicNode Class Reference
	7.58.1	Detailed Description
	7.58.2	Constructor & Destructor Documentation
	7.58.3	Member Function Documentation
7.59	CbcHe	uristicNodeList Class Reference
	7.59.1	Detailed Description
	7.59.2	Constructor & Destructor Documentation
	7.59.3	Member Function Documentation
7.60	CbcHe	uristicPartial Class Reference
	7.60.1	Detailed Description
	7.60.2	Constructor & Destructor Documentation
	7.60.3	Member Function Documentation

X CONTENTS

	7.60.4	Member Data Documentation	221
7.61	CbcHe	uristicPivotAndFix Class Reference	221
	7.61.1	Detailed Description	222
	7.61.2	Constructor & Destructor Documentation	222
	7.61.3	Member Function Documentation	222
7.62	CbcHe	uristicProximity Class Reference	223
	7.62.1	Detailed Description	224
	7.62.2	Constructor & Destructor Documentation	224
	7.62.3	Member Function Documentation	224
	7.62.4	Member Data Documentation	225
7.63	CbcHe	uristicRandRound Class Reference	225
	7.63.1	Detailed Description	226
	7.63.2	Constructor & Destructor Documentation	226
	7.63.3	Member Function Documentation	226
7.64	CbcHe	uristicRENS Class Reference	227
	7.64.1	Detailed Description	228
	7.64.2	Constructor & Destructor Documentation	228
	7.64.3	Member Function Documentation	228
	7.64.4	Member Data Documentation	229
7.65	CbcHe	uristicRINS Class Reference	229
	7.65.1	Detailed Description	230
	7.65.2	Constructor & Destructor Documentation	231
	7.65.3	Member Function Documentation	231
	7.65.4	Member Data Documentation	232
7.66	CbcHe	uristicVND Class Reference	233
	7.66.1	Detailed Description	234
	7.66.2	Constructor & Destructor Documentation	234
	7.66.3	Member Function Documentation	234
	7.66.4	Member Data Documentation	235
7.67	Cbcldio	otBranch Class Reference	236
	7.67.1	Detailed Description	237
	7.67.2	Constructor & Destructor Documentation	237
	7.67.3	Member Function Documentation	237
	7.67.4	Member Data Documentation	238
7.68	CbcInte	egerBranchingObject Class Reference	239
	7.68.1	Detailed Description	240
	7.68.2	Constructor & Destructor Documentation	240

CONTENTS xi

	7.68.3	Member Function Documentation
	7.68.4	Member Data Documentation
7.69	CbcInte	egerPseudoCostBranchingObject Class Reference
	7.69.1	Detailed Description
	7.69.2	Constructor & Destructor Documentation
	7.69.3	Member Function Documentation
	7.69.4	Member Data Documentation
7.70	CbcLor	ngCliqueBranchingObject Class Reference
	7.70.1	Detailed Description
	7.70.2	Constructor & Destructor Documentation
	7.70.3	Member Function Documentation
7.71	CbcLot	size Class Reference
	7.71.1	Detailed Description
	7.71.2	Constructor & Destructor Documentation
	7.71.3	Member Function Documentation
7.72	CbcLot	sizeBranchingObject Class Reference
	7.72.1	Detailed Description
	7.72.2	Constructor & Destructor Documentation
	7.72.3	Member Function Documentation
	7.72.4	Member Data Documentation
7.73	CbcMe	ssage Class Reference
	7.73.1	Detailed Description
	7.73.2	Constructor & Destructor Documentation
7.74	CbcMo	del Class Reference
	7.74.1	Detailed Description
	7.74.2	Member Enumeration Documentation
	7.74.3	Constructor & Destructor Documentation
	7.74.4	Member Function Documentation
7.75	CbcNo	de Class Reference
	7.75.1	Detailed Description
	7.75.2	Constructor & Destructor Documentation
	7.75.3	Member Function Documentation
7.76	CbcNo	deInfo Class Reference
	7.76.1	Detailed Description
	7.76.2	Constructor & Destructor Documentation
	7.76.3	Member Function Documentation
	7.76.4	Member Data Documentation

xii CONTENTS

7.77	CbcNV	Vay Class Reference
	7.77.1	Detailed Description
	7.77.2	Constructor & Destructor Documentation
	7.77.3	Member Function Documentation
	7.77.4	Member Data Documentation
7.78	CbcNV	VayBranchingObject Class Reference
	7.78.1	Detailed Description
	7.78.2	Constructor & Destructor Documentation
	7.78.3	Member Function Documentation
7.79	CbcOb	ject Class Reference
	7.79.1	Detailed Description
	7.79.2	Constructor & Destructor Documentation
	7.79.3	Member Function Documentation
	7.79.4	Member Data Documentation
7.80	CbcOb	jectUpdateData Class Reference
	7.80.1	Detailed Description
	7.80.2	Constructor & Destructor Documentation
	7.80.3	Member Function Documentation
	7.80.4	Member Data Documentation
7.81	CbcOs	iParam Class Reference
	7.81.1	Detailed Description
	7.81.2	Member Enumeration Documentation
	7.81.3	Constructor & Destructor Documentation
	7.81.4	Member Function Documentation
7.82	CbcOs	iSolver Class Reference
	7.82.1	Detailed Description
	7.82.2	Constructor & Destructor Documentation
	7.82.3	Member Function Documentation
	7.82.4	Member Data Documentation
7.83	CbcPa	ram Class Reference
	7.83.1	Detailed Description
	7.83.2	Constructor & Destructor Documentation
	7.83.3	Member Function Documentation
7.84	CbcGe	nCtlBlk::cbcParamsInfo_struct Struct Reference
	7.84.1	Detailed Description
	7.84.2	Member Data Documentation
7.85	CbcPa	rtialNodeInfo Class Reference

CONTENTS xiii

	7.85.1	Detailed Description	355
	7.85.2	Constructor & Destructor Documentation	355
	7.85.3	Member Function Documentation	355
	7.85.4	Member Data Documentation	356
7.86	CbcRo	unding Class Reference	356
	7.86.1	Detailed Description	357
	7.86.2	Constructor & Destructor Documentation	357
	7.86.3	Member Function Documentation	358
	7.86.4	Member Data Documentation	359
7.87	CbcRo	wCuts Class Reference	359
	7.87.1	Detailed Description	359
	7.87.2	Constructor & Destructor Documentation	360
	7.87.3	Member Function Documentation	360
7.88	CbcSe	rendipity Class Reference	360
	7.88.1	Detailed Description	361
	7.88.2	Constructor & Destructor Documentation	361
	7.88.3	Member Function Documentation	361
7.89	CbcSin	npleInteger Class Reference	362
	7.89.1	Detailed Description	364
	7.89.2	Constructor & Destructor Documentation	364
	7.89.3	Member Function Documentation	364
	7.89.4	Member Data Documentation	366
7.90	CbcSin	npleIntegerDynamicPseudoCost Class Reference	366
	7.90.1	Detailed Description	371
	7.90.2	Constructor & Destructor Documentation	371
	7.90.3	Member Function Documentation	371
	7.90.4	Member Data Documentation	378
7.91	CbcSin	npleIntegerPseudoCost Class Reference	381
	7.91.1	Detailed Description	382
	7.91.2	Constructor & Destructor Documentation	382
	7.91.3	Member Function Documentation	382
	7.91.4	Member Data Documentation	384
7.92	CbcSol	lver Class Reference	384
	7.92.1	Detailed Description	386
	7.92.2	Constructor & Destructor Documentation	386
	7.92.3	Member Function Documentation	387
7.93	CbcSol	lverUsefulData Struct Reference	389

xiv CONTENTS

	7.93.1	Detailed Description
	7.93.2	Member Data Documentation
7.94	CbcSO	S Class Reference
	7.94.1	Detailed Description
	7.94.2	Constructor & Destructor Documentation
	7.94.3	Member Function Documentation
7.95	CbcSO	SBranchingObject Class Reference
	7.95.1	Detailed Description
	7.95.2	Constructor & Destructor Documentation
	7.95.3	Member Function Documentation
7.96	CbcSta	atistics Class Reference
	7.96.1	Detailed Description
	7.96.2	Constructor & Destructor Documentation
	7.96.3	Member Function Documentation
	7.96.4	Member Data Documentation
7.97	CbcStc	ppNow Class Reference
	7.97.1	Detailed Description
	7.97.2	Constructor & Destructor Documentation
	7.97.3	Member Function Documentation
7.98	CbcStr	ategy Class Reference
	7.98.1	Detailed Description
	7.98.2	Constructor & Destructor Documentation
	7.98.3	Member Function Documentation
	7.98.4	Member Data Documentation
7.99	CbcStr	ategyDefault Class Reference
	7.99.1	Detailed Description
	7.99.2	Constructor & Destructor Documentation
	7.99.3	Member Function Documentation
	7.99.4	Member Data Documentation
7.10	0CbcStr	ategyDefaultSubTree Class Reference
	7.100.1	Detailed Description
	7.100.2	2 Constructor & Destructor Documentation
	7.100.3	Member Function Documentation
	7.100.4	Member Data Documentation
7.10	1 CbcStr	ategyNull Class Reference
	7.101.1	Detailed Description
	7.101.2	Constructor & Destructor Documentation

CONTENTS xv

7.101.3 Member Function Documentation
7.102CbcStrongInfo Struct Reference
7.102.1 Detailed Description
7.102.2 Member Data Documentation
7.103CbcThread Class Reference
7.103.1 Detailed Description
7.103.2 Constructor & Destructor Documentation
7.104CbcTree Class Reference
7.104.1 Detailed Description
7.104.2 Constructor & Destructor Documentation
7.104.3 Member Function Documentation
7.104.4 Member Data Documentation
7.105CbcTreeLocal Class Reference
7.105.1 Detailed Description
7.105.2 Constructor & Destructor Documentation
7.105.3 Member Function Documentation
7.106CbcTreeVariable Class Reference
7.106.1 Detailed Description
7.106.2 Constructor & Destructor Documentation
7.106.3 Member Function Documentation
7.107CbcUser Class Reference
7.107.1 Detailed Description
7.107.2 Constructor & Destructor Documentation
7.107.3 Member Function Documentation
7.107.4 Member Data Documentation
7.108CglTemporary Class Reference
7.108.1 Detailed Description
7.108.2 Constructor & Destructor Documentation
7.108.3 Member Function Documentation
7.109CbcGenCtlBlk::chooseStrongCtl_struct Struct Reference
7.109.1 Detailed Description
7.109.2 Member Data Documentation
7.110ClpAmplObjective Class Reference
7.110.1 Detailed Description
7.110.2 Constructor & Destructor Documentation
7.110.3 Member Function Documentation
7.111 ClpConstraintAmpl Class Reference

xvi CONTENTS

CONTENTS xvii

xviii CONTENTS

		7.129.3 Member Function Documentation
		7.129.4 Member Data Documentation
	7.130	0OsiSolverLink Class Reference
		7.130.1 Detailed Description
		7.130.2 Constructor & Destructor Documentation
		7.130.3 Member Function Documentation
		7.130.4 Member Data Documentation
	7.131	1OsiUsesBiLinear Class Reference
		7.131.1 Detailed Description
		7.131.2 Constructor & Destructor Documentation
		7.131.3 Member Function Documentation
		7.131.4 Member Data Documentation
	7.132	2PseudoReducedCost Struct Reference
		7.132.1 Detailed Description
		7.132.2 Member Data Documentation
_	En l	
8		Documentation 504
	8.1	/home/ted/COIN/trunk/Cbc/src/Cbc_ampl.h File Reference
	0.0	8.1.1 Function Documentation
	8.2	/home/ted/COIN/trunk/Cbc/src/Cbc_C_Interface.h File Reference
		8.2.1 Function Documentation
	0.0	8.2.2 Variable Documentation
	8.3	/home/ted/COIN/trunk/Cbc/src/CbcBranchActual.hpp File Reference
	8.4	/home/ted/COIN/trunk/Cbc/src/CbcBranchAllDifferent.hpp File Reference
	8.5	/home/ted/COIN/trunk/Cbc/src/CbcBranchBase.hpp File Reference
		8.5.1 Enumeration Type Documentation
	0.0	8.5.2 Function Documentation
	8.6	/home/ted/COIN/trunk/Cbc/src/CbcBranchCut.hpp File Reference
	8.7	/home/ted/COIN/trunk/Cbc/src/CbcBranchDecision.hpp File Reference
	8.8	/home/ted/COIN/trunk/Cbc/src/CbcBranchDefaultDecision.hpp File Reference
	8.9	/home/ted/COIN/trunk/Cbc/src/CbcBranchDynamic.hpp File Reference
	8.10	/home/ted/COIN/trunk/Cbc/src/CbcBranchingObject.hpp File Reference
		8.10.1 Enumeration Type Documentation
		/home/ted/COIN/trunk/Cbc/src/CbcBranchLotsize.hpp File Reference
		/home/ted/COIN/trunk/Cbc/src/CbcBranchToFixLots.hpp File Reference
		/home/ted/COIN/trunk/Cbc/src/CbcClique.hpp File Reference
	8.14	/home/ted/COIN/trunk/Cbc/src/CbcCompare.hpp File Reference

CONTENTS xix

8.15	/home/ted/COIN/trunk/Cbc/src/CbcCompareActual.hpp File Reference
8.16	/home/ted/COIN/trunk/Cbc/src/CbcCompareBase.hpp File Reference
8.17	/home/ted/COIN/trunk/Cbc/src/CbcCompareDefault.hpp File Reference
8.18	/home/ted/COIN/trunk/Cbc/src/CbcCompareDepth.hpp File Reference
8.19	/home/ted/COIN/trunk/Cbc/src/CbcCompareEstimate.hpp File Reference
8.20	/home/ted/COIN/trunk/Cbc/src/CbcCompareObjective.hpp File Reference
8.21	/home/ted/COIN/trunk/Cbc/src/CbcConfig.h File Reference
8.22	/home/ted/COIN/trunk/Cbc/src/CbcConsequence.hpp File Reference
8.23	/home/ted/COIN/trunk/Cbc/src/CbcCountRowCut.hpp File Reference
8.24	/home/ted/COIN/trunk/Cbc/src/CbcCutGenerator.hpp File Reference
	8.24.1 Macro Definition Documentation
8.25	/home/ted/COIN/trunk/Cbc/src/CbcCutModifier.hpp File Reference
8.26	/home/ted/COIN/trunk/Cbc/src/CbcCutSubsetModifier.hpp File Reference
8.27	/home/ted/COIN/trunk/Cbc/src/CbcDummyBranchingObject.hpp File Reference
8.28	/home/ted/COIN/trunk/Cbc/src/CbcEventHandler.hpp File Reference
	8.28.1 Detailed Description
8.29	/home/ted/COIN/trunk/Cbc/src/CbcFathom.hpp File Reference
8.30	/home/ted/COIN/trunk/Cbc/src/CbcFathomDynamicProgramming.hpp File Reference
8.31	/home/ted/COIN/trunk/Cbc/src/CbcFeasibilityBase.hpp File Reference
8.32	/home/ted/COIN/trunk/Cbc/src/CbcFixVariable.hpp File Reference
8.33	/home/ted/COIN/trunk/Cbc/src/CbcFollowOn.hpp File Reference
8.34	/home/ted/COIN/trunk/Cbc/src/CbcFullNodeInfo.hpp File Reference
8.35	/home/ted/COIN/trunk/Cbc/src/CbcGenCbcParam.hpp File Reference
8.36	/home/ted/COIN/trunk/Cbc/src/CbcGenCtlBlk.hpp File Reference
	8.36.1 Macro Definition Documentation
8.37	/home/ted/COIN/trunk/Cbc/src/CbcGeneral.hpp File Reference
8.38	/home/ted/COIN/trunk/Cbc/src/CbcGeneralDepth.hpp File Reference
8.39	/home/ted/COIN/trunk/Cbc/src/CbcGenMessages.hpp File Reference
	8.39.1 Detailed Description
	8.39.2 Enumeration Type Documentation
8.40	/home/ted/COIN/trunk/Cbc/src/CbcGenOsiParam.hpp File Reference
8.41	/home/ted/COIN/trunk/Cbc/src/CbcGenParam.hpp File Reference
8.42	/home/ted/COIN/trunk/Cbc/src/CbcHeuristic.hpp File Reference
	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDINS.hpp File Reference
8.44	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDive.hpp File Reference
8.45	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveCoefficient.hpp File Reference
8.46	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveFractional.hpp File Reference

XX CONTENTS

8.47	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveGuided.hpp File Reference
8.48	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveLineSearch.hpp File Reference
8.49	$/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDivePseudoCost.hpp\ File\ Reference \$
8.50	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveVectorLength.hpp File Reference
8.51	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDW.hpp File Reference
8.52	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicFPump.hpp File Reference
8.53	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicGreedy.hpp File Reference
8.54	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicLocal.hpp File Reference
8.55	$/home/ted/COIN/trunk/Cbc/src/CbcHeuristicPivotAndFix.hpp\ File\ Reference \\ \ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .$
8.56	$/home/ted/COIN/trunk/Cbc/src/CbcHeuristicRandRound.hpp\ File\ Reference \\ \ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .$
8.57	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicRENS.hpp File Reference
8.58	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicRINS.hpp File Reference
8.59	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicVND.hpp File Reference
8.60	/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp File Reference
	8.60.1 Function Documentation
8.61	/home/ted/COIN/trunk/Cbc/src/CbcMessage.hpp File Reference
	8.61.1 Enumeration Type Documentation
8.62	/home/ted/COIN/trunk/Cbc/src/CbcMipStartIO.hpp File Reference
	8.62.1 Function Documentation
8.63	/home/ted/COIN/trunk/Cbc/src/CbcModel.hpp File Reference
	8.63.1 Function Documentation
8.64	/home/ted/COIN/trunk/Cbc/src/CbcNode.hpp File Reference
8.65	/home/ted/COIN/trunk/Cbc/src/CbcNodeInfo.hpp File Reference
8.66	/home/ted/COIN/trunk/Cbc/src/CbcNWay.hpp File Reference
8.67	/home/ted/COIN/trunk/Cbc/src/CbcObject.hpp File Reference
8.68	/home/ted/COIN/trunk/Cbc/src/CbcObjectUpdateData.hpp File Reference
8.69	/home/ted/COIN/trunk/Cbc/src/CbcParam.hpp File Reference
	8.69.1 Enumeration Type Documentation
8.70	/home/ted/COIN/trunk/Cbc/src/CbcPartialNodeInfo.hpp File Reference
8.71	/home/ted/COIN/trunk/Cbc/src/CbcSimpleInteger.hpp File Reference
8.72	$/home/ted/COIN/trunk/Cbc/src/CbcSimpleIntegerDynamicPseudoCost.hpp\ File\ Reference\ .\ .\ .\ .\ .\ .539$
	8.72.1 Macro Definition Documentation
8.73	$/home/ted/COIN/trunk/Cbc/src/CbcSimpleIntegerPseudoCost.hpp\ File\ Reference$
8.74	/home/ted/COIN/trunk/Cbc/src/CbcSolver.hpp File Reference
	8.74.1 Detailed Description
8.75	/home/ted/COIN/trunk/Cbc/src/CbcSolverAnalyze.hpp File Reference
	8.75.1 Detailed Description

1 Todo List

	8.75.2 Function Documentation
8.76	/home/ted/COIN/trunk/Cbc/src/CbcSolverExpandKnapsack.hpp File Reference
	8.76.1 Detailed Description
	8.76.2 Function Documentation
8.77	/home/ted/COIN/trunk/Cbc/src/CbcSolverHeuristics.hpp File Reference
	8.77.1 Detailed Description
	8.77.2 Function Documentation
8.78	/home/ted/COIN/trunk/Cbc/src/CbcSOS.hpp File Reference
8.79	/home/ted/COIN/trunk/Cbc/src/CbcStatistics.hpp File Reference
8.80	/home/ted/COIN/trunk/Cbc/src/CbcStrategy.hpp File Reference
8.81	/home/ted/COIN/trunk/Cbc/src/CbcSubProblem.hpp File Reference
8.82	/home/ted/COIN/trunk/Cbc/src/CbcThread.hpp File Reference
8.83	/home/ted/COIN/trunk/Cbc/src/CbcTree.hpp File Reference
8.84	/home/ted/COIN/trunk/Cbc/src/CbcTreeLocal.hpp File Reference
8.85	/home/ted/COIN/trunk/Cbc/src/ClpAmplObjective.hpp File Reference
8.86	/home/ted/COIN/trunk/Cbc/src/ClpConstraintAmpl.hpp File Reference
8.87	/home/ted/COIN/trunk/Cbc/src/config_cbc_default.h File Reference
	8.87.1 Macro Definition Documentation
8.88	/home/ted/COIN/trunk/Cbc/src/config_default.h File Reference
	8.88.1 Macro Definition Documentation
8.89	$/home/ted/COIN/trunk/Cbc/src/OsiCbc/OsiCbcSolverInterface.hpp\ File\ Reference \\ \ldots \ldots 546$
	8.89.1 Function Documentation
	8.89.2 Variable Documentation

Index 548

1 Todo List

Class CbcCutGenerator

Add a pointer to function member which will allow a client to install their own decision algorithm to decide whether or not to call the CGL generateCuts method. Create a default decision method that looks at the builtin criteria.

It strikes me as not good that generateCuts contains code specific to individual CGL algorithms. Another set of pointer to function members, so that the client can specify the cut generation method as well as pre- and post-generation methods? Taken a bit further, should this class contain a bunch of pointer to function members, one for each of the places where the cut generator might be referenced? Initialization, root node, search tree node, discovery of solution, and termination all come to mind. Initialization and termination would also be useful for instrumenting cbc.

Class CbcFullNodeInfo

While there's no explicit statement, the code often makes the implicit assumption that an CbcFullNodeInfo structure will appear only at the root node of the search tree. Things will break if this assumption is violated.

Member CbcModel::addCuts1 (CbcNode *node, CoinWarmStartBasis *&lastws)

addCuts1() is called in contexts where it's known in advance that all that's desired is to determine a list of cuts and do the bookkeeping (adjust the reference counts). The work of installing bounds and building a basis goes to waste.

Member CbcModel::integerPresolve (bool weak=false)

It remains to work out the cleanest way of getting a solution to the original problem at the end. So this is very preliminary.

Member CbcNodeInfo::numberBranchesLeft_

There seems to be redundancy between this field and CbcBranchingObject::numberBranchesLeft_. It'd be good to sort out if both are necessary.

Class CbcStrongInfo

The notion that all branches are binary (two arms) is wired into the implementation of CbcObject, CbcBranching-Object, and CbcBranchDecision. Changing this will require a moderate amount of recoding.

2 Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

CbcCbcParamUtils	20
CbcGenParamUtils	21
CbcOsiParamUtils	22

3 Hierarchical Index

CbcBranchDefaultDecision

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

```
std::allocator< T >
                                                                                                          22
ampl_info
std::array< T >
std::auto_ptr< T >
                                                                                                          26
CbcGenCtlBlk::babState struct
std::basic_string< Char >
   std::string
   std::wstring
std::basic_string< char >
std::basic_string< wchar_t >
std::bitset< Bits >
CbcBaseModel
                                                                                                          27
CbcBranchDecision
                                                                                                          32
```

36

CbcBranchDynamicDecision	38
CbcCompare	60
CbcCompareBase	61
CbcCompareDefault	64
CbcCompareDepth	69
CbcCompareEstimate	70
CbcCompareObjective	71
CbcConsequence	73
CbcFixVariable	113
CbcCutGenerator	79
CbcCutModifier	90
CbcCutSubsetModifier	91
CbcEventHandler	99
CbcFathom	103
CbcFathomDynamicProgramming	105
CbcFeasibilityBase	110
CbcGenCtlBlk	121
CbcHeuristic	143
CbcHeuristicCrossover	155
CbcHeuristicDINS	157
CbcHeuristicDive	161
CbcHeuristicDiveCoefficient	166
CbcHeuristicDiveFractional	168
CbcHeuristicDiveGuided	170
CbcHeuristicDiveLineSearch	171
CbcHeuristicDivePseudoCost	173
CbcHeuristicDiveVectorLength	175
CbcHeuristicDW	176
CbcHeuristicDynamic3	190
CbcHeuristicFPump	192

	CbcHeuristicGreedyCover	201
	CbcHeuristicGreedyEquality	203
	CbcHeuristicGreedySOS	207
	CbcHeuristicJustOne	210
	CbcHeuristicLocal	212
	CbcHeuristicNaive	215
	CbcHeuristicPartial	219
	CbcHeuristicPivotAndFix	221
	CbcHeuristicProximity	223
	CbcHeuristicRandRound	225
	CbcHeuristicRENS	227
	CbcHeuristicRINS	229
	CbcHeuristicVND	233
	CbcRounding	356
	CbcSerendipity	360
Cb	cHeuristicNode	217
Cb	cHeuristicNodeList	218
Cb	cModel	255
Cb	cNodeInfo	318
	CbcFullNodeInfo	118
	CbcPartialNodeInfo	354
Cb	cObjectUpdateData	339
Cb	cParam	348
Cb	cGenCtlBlk::cbcParamsInfo_struct	353
Cb	cRowCuts	359
Cb	cSolver	384
Cb	cSolverUsefulData	389
Cb	cStatistics	397
Cb	cStopNow	400
Cb	cStrategy	402

3.1 Class Hierarchy 5

CbcStrategyDefault	405
CbcStrategyDefaultSubTree	408
CbcStrategyNull	410
CbcStrongInfo	412
CbcThread	414
CbcTree	414
CbcTreeLocal	422
CbcTreeVariable	425
CbcUser CglStored	428
CglTemporary	431
CbcGenCtlBlk::chooseStrongCtl_struct ClpConstraint	433
ClpConstraintAmpl ClpObjective	436
ClpAmplObjective	434
CoinHashLink CoinMessages	439
CbcMessage CoinParam	254
CbcCbcParam	50
CbcGenParam	139
CbcOsiParam CoinTreeNode	341
CbcNode std::complex std::list< T >::const_iterator std::map< K, T >::const_iterator std::forward_list< T >::const_iterator std::unordered_map< K, T >::const_iterator std::basic_string< Char >::const_iterator std::multimap< K, T >::const_iterator std::unordered_multimap< K, T >::const_iterator std::set< K >::const_iterator std::set< K >::const_iterator	310
std::unordered_set< K >::const_iterator std::multiset< K >::const_iterator std::wstring::const_iterator std::unordered_multiset< K >::const_iterator	

```
std::vector< T >::const_iterator
std::deque < T >::const iterator
std::list< T >::const reverse iterator
std::forward list< T >::const reverse iterator
std::map < K, T >::const reverse iterator
std::unordered_map< K, T >::const_reverse_iterator
std::multimap< K, T >::const reverse iterator
std::basic string< Char >::const reverse iterator
std::unordered multimap< K, T >::const reverse iterator
std::set< K >::const_reverse_iterator
std::string::const_reverse_iterator
std::unordered_set< K >::const_reverse_iterator
std::multiset < K >::const reverse iterator
std::wstring::const_reverse_iterator
std::unordered multiset < K >::const reverse iterator
std::vector< T >::const_reverse_iterator
std::deque< T >::const_reverse_iterator
CbcGenCtlBlk::debugSolInfo_struct
                                                                                                             439
std::deque < T >
                                                                                                             440
CbcGenCtlBlk::djFixCtl_struct
std::error category
std::error code
std::error condition
std::exception
   std::bad alloc
   std::bad cast
   std::bad exception
   std::bad typeid
   std::ios base::failure
   std::logic_error
       std::domain error
       std::invalid argument
       std::length error
       std::out_of_range
   std::runtime error
       std::overflow_error
       std::range_error
       std::underflow error
std::forward_list< T >
                                                                                                             441
CbcGenCtlBlk::genParamsInfo_struct
std::ios base
   basic_ios < char >
   basic_ios< wchar_t >
   std::basic_ios
       basic istream < char >
       basic istream< wchar t>
       basic_ostream< char >
       basic ostream< wchar t>
       std::basic_istream
          basic ifstream < char >
          basic ifstream< wchar t >
          basic iostream < char >
```

3.1 Class Hierarchy 7

```
basic_iostream< wchar_t >
          basic istringstream < char >
          basic_istringstream< wchar_t >
          std::basic ifstream
              std::ifstream
              std::wifstream
          std::basic iostream
              basic_fstream < char >
              basic fstream< wchar t>
              basic_stringstream< char >
              basic_stringstream< wchar_t >
              std::basic_fstream
                 std::fstream
                 std::wfstream
              std::basic stringstream
                 std::stringstream
                 std::wstringstream
          std::basic_istringstream
              std::istringstream
              std::wistringstream
          std::istream
          std::wistream
       std::basic_ostream
          basic iostream < char >
          basic iostream< wchar t>
          basic ofstream < char >
          basic_ofstream< wchar_t >
          basic_ostringstream< char >
          basic_ostringstream< wchar_t >
          std::basic_iostream
          std::basic ofstream
              std::ofstream
              std::wofstream
          std::basic ostringstream
              std::ostringstream
              std::wostringstream
          std::ostream
          std::wostream
       std::ios
       std::wios
std::unordered_set< K >::iterator
std::set< K >::iterator
std::list< T >::iterator
std::map < K, T >::iterator
std::forward_list< T >::iterator
std::unordered_map< K, T >::iterator
std::multimap< K, T >::iterator
std::unordered_multimap< K, T >::iterator
std::string::iterator
std::wstring::iterator
std::multiset< K >::iterator
std::unordered_multiset< K >::iterator
std::basic string< Char >::iterator
std::vector< T >::iterator
```

std::deque < T >::iterator std::list < T >	
std::map < K, T >	
$ \begin{array}{l} \text{std::multimap} < \text{K, T} > \\ \text{std::multiset} < \text{K} > \\ \end{array} $	
OsiBranchingObject	
CbcBranchingObject	40
CbcCliqueBranchingObject	58
CbcCutBranchingObject	76
CbcDummyBranchingObject	93
CbcFixingBranchingObject	111
CbcIntegerBranchingObject	239
CbcDynamicPseudoCostBranchingObject	95
CbcIntegerPseudoCostBranchingObject	242
CbcLongCliqueBranchingObject	245
CbcLotsizeBranchingObject	25 1
CbcNWayBranchingObject	329
CbcSOSBranchingObject OsiChooseStrong	394
OsiChooseStrongSubset OsiClpSolverInterface	473
CbcOsiSolver	346
OsiSolverLink	491
OsiSolverLinearizedQuadratic	488
OsiLinkedBound OsiObject	479
CbcObject	332
CbcBranchCut	30
CbcBranchAllDifferent	28
CbcBranchToFixLots	47
CbcClique	54
CbcFollowOn	115
CbcGeneral	137

3.1 Class Hierarchy 9

CbcldiotBranch	236
CbcLotsize	247
CbcNWay	326
CbcSimpleInteger	362
CbcSimpleIntegerDynamicPseudoCost	366
CbcSimpleIntegerPseudoCost	381
CbcSOS OsiObject2	390
OsiBiLinear	441
OsiBiLinearEquality	453
OsiOneLink	484
CbcGenCtIBIk::osiParamsInfo_struct OsiRowCut	486
CbcCountRowCut OsiSimpleInteger	74
OsiSimpleFixedInteger	486
OsiUsesBiLinear OsiSolverInterface	500
OsiCbcSolverInterface OsiSOS	455
OsiLink	476
OsiOldLink OsiSOSBranchingObject	480
OsiOldLinkBranchingObject OsiTwoWayBranchingObject	483
OsiBiLinearBranchingObject	452
OsiLinkBranchingObject std::priority_queue < T >	478
PseudoReducedCost std::queue< T > std::string::reverse_iterator std::forward_list< T >::reverse_iterator std::list< T >::reverse_iterator std::map< K, T >::reverse_iterator std::unordered_map< K, T >::reverse_iterator std::deque< T >::reverse_iterator std::basic_string< Char >::reverse_iterator	503

```
std::vector< T >::reverse_iterator
std::set< K >::reverse iterator
std::unordered\_multiset < K > :: reverse\_iterator
std::wstring::reverse iterator
std::multimap< K, T >::reverse_iterator
std::multiset < K >::reverse\_iterator
std::unordered multimap< K, T >::reverse iterator
std::unordered_set< K >::reverse_iterator
std::set< K >
std::smart_ptr< T >
std::stack< T >
std::system_error
std::thread
std::unique_ptr< T >
std::unordered map< K, T >
std::unordered_multimap< K, T >
std::unordered_multiset< K >
std::unordered_set< K >
std::valarray< T >
std::vector< T >
std::vector< bool >
std::vector < CbcHeuristicNode * >
std::vector< CbcNode * >
std::vector< double >
std::vector< int >
std::vector< std::pair< std::string, double >>
std::vector< std::string >
std::weak_ptr< T >
Κ
Т
```

4 Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

mpl_info	22
bcGenCtlBlk::babState_struct	
State of branch-and-cut	26
bcBaseModel	
Base model	27
bcBranchAllDifferent	
Define a branch class that branches so that it is only satsified if all members have different values	
So cut is $x \le y-1$ or $x \ge y+1$	28
bcBranchCut	
Define a cut branching class	30
bcBranchDecision	32

4.1 Class List

CbcBranchDefaultDecision Branching decision default class	36
CbcBranchDynamicDecision Branching decision dynamic class	38
CbcBranchingObject Abstract branching object base class Now just difference with OsiBranchingObject	40
CbcBranchToFixLots Define a branch class that branches so that one way variables are fixed while the other way cuts off that solution	47
CbcCbcParam Class for control parameters that act on a CbcModel object	50
CbcClique Branching object for cliques	54
CbcCliqueBranchingObject Branching object for unordered cliques	58
CbcCompare	60
CbcCompareBase	61
CbcCompareDefault	64
CbcCompareDepth	69
CbcCompareEstimate	70
CbcCompareObjective	71
CbcConsequence Abstract base class for consequent bounds	73
CbcCountRowCut OsiRowCut augmented with bookkeeping	74
CbcCutBranchingObject Cut branching object	76
CbcCutGenerator Interface between Cbc and Cut Generation Library	79
CbcCutModifier Abstract cut modifier base class	90
CbcCutSubsetModifier Simple cut modifier base class	91
CbcDummyBranchingObject Dummy branching object	93
CbcDynamicPseudoCostBranchingObject Simple branching object for an integer variable with pseudo costs	95

CbcEventHandler Base class for Cbc event handling	99
CbcFathom Fathom base class	103
CbcFathomDynamicProgramming FathomDynamicProgramming class	105
CbcFeasibilityBase	110
CbcFixingBranchingObject General Branching Object class	111
CbcFixVariable Class for consequent bounds	113
CbcFollowOn Define a follow on class	115
CbcFullNodeInfo Information required to recreate the subproblem at this node	118
CbcGenCtlBlk	121
CbcGeneral Define a catch all class	137
CbcGenParam Class for cbc-generic control parameters	139
CbcHeuristic Heuristic base class	143
CbcHeuristicCrossover Crossover Search class	155
CbcHeuristicDINS	157
CbcHeuristicDive Dive class	161
CbcHeuristicDiveCoefficient DiveCoefficient class	166
CbcHeuristicDiveFractional DiveFractional class	168
CbcHeuristicDiveGuided DiveGuided class	170
CbcHeuristicDiveLineSearch DiveLineSearch class	171
CbcHeuristicDivePseudoCost DivePseudoCost class	173

4.1 Class List 13

CbcHeuristicDiveVectorLength DiveVectorLength class	175
CbcHeuristicDW This is unlike the other heuristics in that it is very very compute intensive	176
CbcHeuristicDynamic3 Heuristic - just picks up any good solution	190
CbcHeuristicFPump Feasibility Pump class	192
CbcHeuristicGreedyCover Greedy heuristic classes	201
CbcHeuristicGreedyEquality	203
CbcHeuristicGreedySOS Greedy heuristic for SOS and L rows (and positive elements)	207
CbcHeuristicJustOne Just One class - this chooses one at random	210
CbcHeuristicLocal LocalSearch class	212
CbcHeuristicNaive Naive class a) Fix all ints as close to zero as possible b) Fix all ints with nonzero costs and < large to zero c) Put bounds round continuous and UIs and maximize	215
CbcHeuristicNode A class describing the branching decisions that were made to get to the node where a heuristic was invoked from	217
CbcHeuristicNodeList	218
CbcHeuristicPartial Partial solution class If user knows a partial solution this tries to get an integer solution it uses hotstart information	219
CbcHeuristicPivotAndFix LocalSearch class	221
CbcHeuristicProximity	223
CbcHeuristicRandRound LocalSearch class	225
CbcHeuristicRENS LocalSearch class	227
CbcHeuristicRINS LocalSearch class	229
CbcHeuristicVND LocalSearch class	233

CbcldiotBranch Define an idiotic idea class	236
CbcIntegerBranchingObject Simple branching object for an integer variable	239
CbcIntegerPseudoCostBranchingObject Simple branching object for an integer variable with pseudo costs	242
CbcLongCliqueBranchingObject Unordered Clique Branching Object class	245
CbcLotsize Lotsize class	247
CbcLotsizeBranchingObject Lotsize branching object	251
CbcMessage	254
CbcModel Simple Branch and bound class	255
CbcNode Information required while the node is live	310
CbcNodeInfo Information required to recreate the subproblem at this node	318
CbcNWay Define an n-way class for variables	326
CbcNWayBranchingObject N way branching Object class	329
CbcObject	332
CbcObjectUpdateData	339
CbcOsiParam Class for control parameters that act on a OsiSolverInterface object	341
CbcOsiSolver This is for codes where solver needs to know about CbcModel Seems to provide only one value- added feature, a CbcModel object	346
CbcParam Very simple class for setting parameters	348
CbcGenCtlBlk::cbcParamsInfo_struct Start and end of CbcModel parameters in parameter vector	353
CbcPartialNodeInfo Holds information for recreating a subproblem by incremental change from the parent	354
CbcRounding Rounding class	356

4.1 Class List

CbcRowCuts	359
CbcSerendipity Heuristic - just picks up any good solution found by solver - see OsiBabSolver	360
CbcSimpleInteger Define a single integer class	362
CbcSimpleIntegerDynamicPseudoCost Define a single integer class but with dynamic pseudo costs	366
CbcSimpleIntegerPseudoCost Define a single integer class but with pseudo costs	381
CbcSolver This allows the use of the standalone solver in a flexible manner	384
CbcSolverUsefulData Structure to hold useful arrays	389
CbcSOS Branching object for Special Ordered Sets of type 1 and 2	390
CbcSOSBranchingObject Branching object for Special ordered sets	394
CbcStatistics For gathering statistics	397
CbcStopNow Support the use of a call back class to decide whether to stop	400
CbcStrategy Strategy base class	402
CbcStrategyDefault Default class	405
CbcStrategyDefaultSubTree Default class for sub trees	408
CbcStrategyNull Null class	410
CbcStrongInfo Abstract base class for 'objects'	412
CbcThread A class to encapsulate thread stuff	414
CbcTree Using MS heap implementation	414
CbcTreeLocal	422
CbcTreeVariable	425

CbcUser A class to allow the use of unknown user functionality	428
CglTemporary Stored Temporary Cut Generator Class - destroyed after first use	431
CbcGenCtlBlk::chooseStrongCtl_struct Control variables for a strong branching method	433
ClpAmplObjective Ampl Objective Class	434
ClpConstraintAmpl Ampl Constraint Class	436
CoinHashLink Really for Conflict cuts to - a) stop duplicates b) allow half baked cuts The whichRow_ field in OsiRowCut2 is used for a type 0 - normal 1 - processed cut 2 - unprocessed cut i.e	439
CbcGenCtlBlk::debugSolInfo_struct Array of primal variable values for debugging	439
CbcGenCtlBlk::djFixCtl_struct Control use of reduced cost fixing prior to B&C	440
CbcGenCtlBlk::genParamsInfo_struct Start and end of cbc-generic parameters in parameter vector	441
OsiBiLinear Define BiLinear objects	441
OsiBiLinearBranchingObject Branching object for BiLinear objects	452
OsiBiLinearEquality Define Continuous BiLinear objects for an == bound	453
OsiCbcSolverInterface Cbc Solver Interface	455
OsiChooseStrongSubset This class chooses a variable to branch on	473
OsiLink Define Special Linked Ordered Sets	476
OsiLinkBranchingObject Branching object for Linked ordered sets	478
OsiLinkedBound List of bounds which depend on other bounds	479
OsiOldLink	480
OsiOldLinkBranchingObject Branching object for Linked ordered sets	483

5 File Index 17

	OsiOneLink Define data for one link	484
	CbcGenCtlBlk::osiParamsInfo_struct Start and end of OsiSolverInterface parameters in parameter vector	486
	OsiSimpleFixedInteger Define a single integer class - but one where you keep branching until fixed even if satisfied	486
	OsiSolverLinearizedQuadratic This is to allow the user to replace initialSolve and resolve	488
	OsiSolverLink This is to allow the user to replace initialSolve and resolve This version changes coefficients	491
	OsiUsesBiLinear Define a single variable class which is involved with OsiBiLinear objects	500
	PseudoReducedCost	503
5	File Index	
5.	1 File List	
Нє	ere is a list of all files with brief descriptions:	
	/home/ted/COIN/trunk/Cbc/src/Cbc_ampl.h	504
	/home/ted/COIN/trunk/Cbc/src/Cbc_C_Interface.h	504
	/home/ted/COIN/trunk/Cbc/src/CbcBranchActual.hpp	509
	/home/ted/COIN/trunk/Cbc/src/CbcBranchAllDifferent.hpp	509
	/home/ted/COIN/trunk/Cbc/src/CbcBranchBase.hpp	510
	/home/ted/COIN/trunk/Cbc/src/CbcBranchCut.hpp	511
	/home/ted/COIN/trunk/Cbc/src/CbcBranchDecision.hpp	511
	/home/ted/COIN/trunk/Cbc/src/CbcBranchDefaultDecision.hpp	511
	/home/ted/COIN/trunk/Cbc/src/CbcBranchDynamic.hpp	511
	/home/ted/COIN/trunk/Cbc/src/CbcBranchingObject.hpp	512
	/home/ted/COIN/trunk/Cbc/src/CbcBranchLotsize.hpp	512
	/home/ted/COIN/trunk/Cbc/src/CbcBranchToFixLots.hpp	513
	/home/ted/COIN/trunk/Cbc/src/CbcClique.hpp	513
	/home/ted/COIN/trunk/Cbc/src/CbcCompare.hpp	513
	/home/ted/COIN/trunk/Cbc/src/CbcCompareActual.hpp	513

/home/ted/COIN/trunk/Cbc/src/CbcCompareBase.hpp	514
/home/ted/COIN/trunk/Cbc/src/CbcCompareDefault.hpp	514
/home/ted/COIN/trunk/Cbc/src/CbcCompareDepth.hpp	514
/home/ted/COIN/trunk/Cbc/src/CbcCompareEstimate.hpp	514
/home/ted/COIN/trunk/Cbc/src/CbcCompareObjective.hpp	514
/home/ted/COIN/trunk/Cbc/src/CbcConfig.h	515
/home/ted/COIN/trunk/Cbc/src/CbcConsequence.hpp	515
/home/ted/COIN/trunk/Cbc/src/CbcCountRowCut.hpp	515
/home/ted/COIN/trunk/Cbc/src/CbcCutGenerator.hpp	515
/home/ted/COIN/trunk/Cbc/src/CbcCutModifier.hpp	516
/home/ted/COIN/trunk/Cbc/src/CbcCutSubsetModifier.hpp	516
/home/ted/COIN/trunk/Cbc/src/CbcDummyBranchingObject.hpp	516
/home/ted/COIN/trunk/Cbc/src/CbcEventHandler.hpp Event handling for cbc	517
/home/ted/COIN/trunk/Cbc/src/CbcFathom.hpp	517
/home/ted/COIN/trunk/Cbc/src/CbcFathomDynamicProgramming.hpp	518
/home/ted/COIN/trunk/Cbc/src/CbcFeasibilityBase.hpp	518
/home/ted/COIN/trunk/Cbc/src/CbcFixVariable.hpp	518
/home/ted/COIN/trunk/Cbc/src/CbcFollowOn.hpp	518
/home/ted/COIN/trunk/Cbc/src/CbcFullNodeInfo.hpp	519
/home/ted/COIN/trunk/Cbc/src/CbcGenCbcParam.hpp	519
/home/ted/COIN/trunk/Cbc/src/CbcGenCtiBlk.hpp	519
/home/ted/COIN/trunk/Cbc/src/CbcGeneral.hpp	52 1
/home/ted/COIN/trunk/Cbc/src/CbcGeneralDepth.hpp	521
/home/ted/COIN/trunk/Cbc/src/CbcGenMessages.hpp This file contains the enum that defines symbolic names for for cbc-generic messages	521
/home/ted/COIN/trunk/Cbc/src/CbcGenOsiParam.hpp	522
/home/ted/COIN/trunk/Cbc/src/CbcGenParam.hpp	522
/home/ted/COIN/trunk/Cbc/src/CbcHeuristic.hpp	523
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDINS.hpp	523
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDive.hpp	524

5.1 File List 19

/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveCoefficient.hpp	52 4
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveFractional.hpp	52 4
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveGuided.hpp	52 4
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveLineSearch.hpp	525
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDivePseudoCost.hpp	525
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveVectorLength.hpp	525
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDW.hpp	525
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicFPump.hpp	525
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicGreedy.hpp	526
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicLocal.hpp	526
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicPivotAndFix.hpp	526
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicRandRound.hpp	526
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicRENS.hpp	527
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicRINS.hpp	527
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicVND.hpp	527
/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp	527
/home/ted/COIN/trunk/Cbc/src/CbcMessage.hpp	529
/home/ted/COIN/trunk/Cbc/src/CbcMipStartIO.hpp	53 1
/home/ted/COIN/trunk/Cbc/src/CbcModel.hpp	53 1
/home/ted/COIN/trunk/Cbc/src/CbcNode.hpp	533
/home/ted/COIN/trunk/Cbc/src/CbcNodeInfo.hpp	533
/home/ted/COIN/trunk/Cbc/src/CbcNWay.hpp	533
/home/ted/COIN/trunk/Cbc/src/CbcObject.hpp	533
/home/ted/COIN/trunk/Cbc/src/CbcObjectUpdateData.hpp	534
/home/ted/COIN/trunk/Cbc/src/CbcParam.hpp	534
/home/ted/COIN/trunk/Cbc/src/CbcPartialNodeInfo.hpp	538
/home/ted/COIN/trunk/Cbc/src/CbcSimpleInteger.hpp	538
/home/ted/COIN/trunk/Cbc/src/CbcSimpleIntegerDynamicPseudoCost.hpp	539
/home/ted/COIN/trunk/Cbc/src/CbcSimpleIntegerPseudoCost.hpp	540

/home/ted/COIN/trunk/Cbc/src/CbcSolver.hpp Defines CbcSolver, the proposed top-level class for the new-style cbc solver	540
/home/ted/COIN/trunk/Cbc/src/CbcSolverAnalyze.hpp Look to see if a constraint is all-integer (variables & coeffs), or could be all integer	541
/home/ted/COIN/trunk/Cbc/src/CbcSolverExpandKnapsack.hpp Expanding possibilities of x*y, where x*y are both integers, constructing a knapsack constraint	541
/home/ted/COIN/trunk/Cbc/src/CbcSolverHeuristics.hpp Routines for doing heuristics	542
/home/ted/COIN/trunk/Cbc/src/CbcSOS.hpp	542
/home/ted/COIN/trunk/Cbc/src/CbcStatistics.hpp	542
/home/ted/COIN/trunk/Cbc/src/CbcStrategy.hpp	543
/home/ted/COIN/trunk/Cbc/src/CbcSubProblem.hpp	543
/home/ted/COIN/trunk/Cbc/src/CbcThread.hpp	543
/home/ted/COIN/trunk/Cbc/src/CbcTree.hpp	543
/home/ted/COIN/trunk/Cbc/src/CbcTreeLocal.hpp	544
/home/ted/COIN/trunk/Cbc/src/ClpAmplObjective.hpp	544
/home/ted/COIN/trunk/Cbc/src/ClpConstraintAmpl.hpp	544
/home/ted/COIN/trunk/Cbc/src/config_cbc_default.h	544
/home/ted/COIN/trunk/Cbc/src/config_default.h	545
/home/ted/COIN/trunk/Cbc/src/OsiCbc/OsiCbcSolverInterface.hpp	546

6 Namespace Documentation

6.1 CbcCbcParamUtils Namespace Reference

Functions

- void addCbcCbcParams (int &numParams, CoinParamVec ¶mVec, CbcModel *model)
- void loadCbcParamObj (const CoinParamVec paramVec, int first, int last, CbcModel *model)
- void setCbcModelDefaults (CbcModel *model)
- int pushCbcCbcDbl (CoinParam *param)
- int pushCbcCbcInt (CoinParam *param)

6.1.1 Function Documentation

- 6.1.1.1 void CbcCbcParamUtils::addCbcCbcParams (int & numParams, CoinParamVec & paramVec, CbcModel * model)
- 6.1.1.2 void CbcCbcParamUtils::loadCbcParamObj (const CoinParamVec paramVec, int first, int last, CbcModel * model)

```
6.1.1.3 void CbcCbcParamUtils::setCbcModelDefaults ( CbcModel * model )
6.1.1.4 int CbcCbcParamUtils::pushCbcCbcDbl ( CoinParam * param )
```

6.1.1.5 int CbcCbcParamUtils::pushCbcCbcInt (CoinParam * param)

6.2 CbcGenParamUtils Namespace Reference

Functions

- void addCbcGenParams (int &numParams, CoinParamVec ¶mVec, CbcGenCtlBlk *ctlBlk)
- void loadGenParamObj (const CoinParamVec paramVec, int first, int last, CbcGenCtlBlk *ctlBlk)
- void saveSolution (const OsiSolverInterface *osi, std::string fileName)
- bool readSolution (std::string fileName, int &numRows, int &numCols, double &objVal, double **rowActivity, double **dualVars, double **primalVars, double **reducedCosts)
- int doBaCParam (CoinParam *param)
- int doDebugParam (CoinParam *param)
- int doExitParam (CoinParam *param)
- int doHelpParam (CoinParam *param)
- int dolmportParam (CoinParam *param)
- int doPrintMaskParam (CoinParam *param)
- int doNothingParam (CoinParam *param)
- int doSolutionParam (CoinParam *param)
- int doUnimplementedParam (CoinParam *param)
- int doVersionParam (CoinParam *param)
- int pushCbcGenDblParam (CoinParam *param)
- int pushCbcGenIntParam (CoinParam *param)
- int pushCbcGenKwdParam (CoinParam *param)
- int pushCbcGenStrParam (CoinParam *param)
- int pushCbcGenCutParam (CoinParam *param)

6.2.1 Function Documentation

- 6.2.1.1 void CbcGenParamUtils::addCbcGenParams (int & numParams, CoinParamVec & paramVec, CbcGenCtIBIk * ctIBIk)
- 6.2.1.2 void CbcGenParamUtils::loadGenParamObj (const CoinParamVec, int first, int last, CbcGenCtlBlk * ctlBlk)
- 6.2.1.3 void CbcGenParamUtils::saveSolution (const OsiSolverInterface * osi, std::string fileName)
- 6.2.1.4 bool CbcGenParamUtils::readSolution (std::string fileName, int & numRows, int & numCols, double & objVal, double ** rowActivity, double ** dualVars, double ** primalVars, double ** reducedCosts)
- 6.2.1.5 int CbcGenParamUtils::doBaCParam (CoinParam * param)
- 6.2.1.6 int CbcGenParamUtils::doDebugParam (CoinParam * param)
- 6.2.1.7 int CbcGenParamUtils::doExitParam (CoinParam * param)
- 6.2.1.8 int CbcGenParamUtils::doHelpParam (CoinParam * param)
- 6.2.1.9 int CbcGenParamUtils::doImportParam (CoinParam * param)
- 6.2.1.10 int CbcGenParamUtils::doPrintMaskParam (CoinParam * param)

```
6.2.1.11 int CbcGenParamUtils::doNothingParam ( CoinParam * param )
6.2.1.12 int CbcGenParamUtils::doSolutionParam ( CoinParam * param )
6.2.1.13 int CbcGenParamUtils::doUnimplementedParam ( CoinParam * param )
6.2.1.14 int CbcGenParamUtils::doVersionParam ( CoinParam * param )
6.2.1.15 int CbcGenParamUtils::pushCbcGenDblParam ( CoinParam * param )
6.2.1.16 int CbcGenParamUtils::pushCbcGenIntParam ( CoinParam * param )
6.2.1.17 int CbcGenParamUtils::pushCbcGenKwdParam ( CoinParam * param )
6.2.1.18 int CbcGenParamUtils::pushCbcGenStrParam ( CoinParam * param )
6.2.1.19 int CbcGenParamUtils::pushCbcGenCutParam ( CoinParam * param )
```

6.3 CbcOsiParamUtils Namespace Reference

Functions

- void addCbcOsiParams (int &numParams, CoinParamVec ¶mVec, OsiSolverInterface *osi)
- void loadOsiParamObj (const CoinParamVec paramVec, CbcGenCtlBlk *ctlBlk)
- void setOsiSolverInterfaceDefaults (OsiSolverInterface *osi)
- int pushCbcOsiLogLevel (CoinParam *param)
- int pushCbcOsiInt (CoinParam *param)
- int pushCbcOsiDbl (CoinParam *param)
- int pushCbcOsiKwd (CoinParam *param)
- int pushCbcOsiHint (CoinParam *param)

6.3.1 Function Documentation

- 6.3.1.1 void CbcOsiParamUtils::addCbcOsiParams (int & numParams, CoinParamVec & paramVec, OsiSolverInterface * osi)
- 6.3.1.2 void CbcOsiParamUtils::loadOsiParamObj (const CoinParamVec paramVec, CbcGenCtIBIk * ctlBlk)
- $6.3.1.3 \quad \text{void CbcOsiParamUtils::setOsiSolverInterfaceDefaults (} \quad \text{OsiSolverInterface} * \textit{osi} \text{)} \\$
- 6.3.1.4 int CbcOsiParamUtils::pushCbcOsiLogLevel (CoinParam * param)
- 6.3.1.5 int CbcOsiParamUtils::pushCbcOsiInt (CoinParam * param)
- 6.3.1.6 int CbcOsiParamUtils::pushCbcOsiDbl (CoinParam * param)
- 6.3.1.7 int CbcOsiParamUtils::pushCbcOsiKwd (CoinParam * param)
- 6.3.1.8 int CbcOsiParamUtils::pushCbcOsiHint (CoinParam * param)

7 Class Documentation

7.1 ampl_info Struct Reference

```
#include <Cbc_ampl.h>
```

Public Attributes

- int numberRows
- int numberColumns
- int numberBinary
- int numberIntegers
- int numberSos
- int numberElements
- int numberArguments
- · int problemStatus
- · double direction
- · double offset
- double objValue
- double * objective
- double * rowLower
- double * rowUpper
- double * columnLower
- double * columnUpper
- int * starts
- int * rows
- double * elements
- double * primalSolution
- double * dualSolution
- int * columnStatus
- int * rowStatus
- int * priorities
- int * branchDirection
- double * pseudoDown
- double * pseudoUp
- char * sosType
- int * sosPriority
- int * sosStart
- int * sosIndices
- double * sosReference
- int * cut
- int * special
- char ** arguments
- char buffer [300]
- · int logLevel
- · int nonLinear

7.1.1 Detailed Description

Definition at line 11 of file Cbc_ampl.h.

7.1.2 Member Data Documentation

7.1.2.1 int ampl_info::numberRows

Definition at line 12 of file Cbc_ampl.h.

7.1.2.2 int ampl_info::numberColumns

Definition at line 13 of file Cbc ampl.h.

7.1.2.3 int ampl_info::numberBinary

Definition at line 14 of file Cbc_ampl.h.

7.1.2.4 int ampl_info::numberIntegers

Definition at line 15 of file Cbc ampl.h.

7.1.2.5 int ampl_info::numberSos

Definition at line 16 of file Cbc_ampl.h.

7.1.2.6 int ampl_info::numberElements

Definition at line 17 of file Cbc_ampl.h.

7.1.2.7 int ampl_info::numberArguments

Definition at line 18 of file Cbc_ampl.h.

7.1.2.8 int ampl_info::problemStatus

Definition at line 19 of file Cbc_ampl.h.

7.1.2.9 double ampl_info::direction

Definition at line 20 of file Cbc_ampl.h.

7.1.2.10 double ampl_info::offset

Definition at line 21 of file Cbc_ampl.h.

7.1.2.11 double ampl_info::objValue

Definition at line 22 of file Cbc_ampl.h.

7.1.2.12 double* ampl_info::objective

Definition at line 23 of file Cbc ampl.h.

7.1.2.13 double* ampl_info::rowLower

Definition at line 24 of file Cbc_ampl.h.

7.1.2.14 double* ampl_info::rowUpper

Definition at line 25 of file Cbc ampl.h.

7.1.2.15 double* ampl_info::columnLower

Definition at line 26 of file Cbc_ampl.h.

7.1.2.16 double* ampl_info::columnUpper

Definition at line 27 of file Cbc ampl.h.

7.1.2.17 int* ampl_info::starts

Definition at line 28 of file Cbc_ampl.h.

7.1.2.18 int* ampl_info::rows

Definition at line 29 of file Cbc ampl.h.

7.1.2.19 double* ampl_info::elements

Definition at line 30 of file Cbc_ampl.h.

7.1.2.20 double* ampl_info::primalSolution

Definition at line 31 of file Cbc_ampl.h.

7.1.2.21 double* ampl_info::dualSolution

Definition at line 32 of file Cbc_ampl.h.

7.1.2.22 int* ampl_info::columnStatus

Definition at line 33 of file Cbc_ampl.h.

7.1.2.23 int* ampl_info::rowStatus

Definition at line 34 of file Cbc_ampl.h.

7.1.2.24 int* ampl_info::priorities

Definition at line 35 of file Cbc_ampl.h.

7.1.2.25 int* ampl_info::branchDirection

Definition at line 36 of file Cbc ampl.h.

7.1.2.26 double* ampl_info::pseudoDown

Definition at line 37 of file Cbc_ampl.h.

7.1.2.27 double* ampl_info::pseudoUp

Definition at line 38 of file Cbc_ampl.h.

7.1.2.28 char* ampl_info::sosType

Definition at line 39 of file Cbc_ampl.h.

7.1.2.29 int* ampl_info::sosPriority

Definition at line 40 of file Cbc_ampl.h.

```
7.1.2.30 int* ampl_info::sosStart
```

Definition at line 41 of file Cbc_ampl.h.

7.1.2.31 int* ampl_info::sosIndices

Definition at line 42 of file Cbc_ampl.h.

7.1.2.32 double * ampl_info::sosReference

Definition at line 43 of file Cbc ampl.h.

7.1.2.33 int* ampl_info::cut

Definition at line 44 of file Cbc_ampl.h.

7.1.2.34 int* ampl_info::special

Definition at line 45 of file Cbc_ampl.h.

7.1.2.35 char** ampl_info::arguments

Definition at line 46 of file Cbc_ampl.h.

7.1.2.36 char ampl_info::buffer[300]

Definition at line 47 of file Cbc_ampl.h.

7.1.2.37 int ampl_info::logLevel

Definition at line 48 of file Cbc_ampl.h.

7.1.2.38 int ampl_info::nonLinear

Definition at line 49 of file Cbc_ampl.h.

The documentation for this struct was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/Cbc_ampl.h

7.2 CbcGenCtlBlk::babState_struct Struct Reference

State of branch-and-cut.

```
#include <CbcGenCtlBlk.hpp>
```

Public Attributes

- BACMajor majorStatus_
- BACMinor minorStatus_
- BACWhere where_
- bool haveAnswer_
- OsiSolverInterface * answerSolver_

7.2.1 Detailed Description

State of branch-and-cut.

Major and minor status codes, and a solver holding the answer, assuming we have a valid answer. See the documentation with the BACMajor, BACMinor, and BACWhere enums for the meaning of the codes.

Definition at line 718 of file CbcGenCtlBlk.hpp.

7.2.2 Member Data Documentation

7.2.2.1 BACMajor CbcGenCtlBlk::babState_struct::majorStatus_

Definition at line 719 of file CbcGenCtlBlk.hpp.

7.2.2.2 BACMinor CbcGenCtlBlk::babState_struct::minorStatus_

Definition at line 720 of file CbcGenCtlBlk.hpp.

7.2.2.3 BACWhere CbcGenCtlBlk::babState_struct::where_

Definition at line 721 of file CbcGenCtlBlk.hpp.

7.2.2.4 bool CbcGenCtlBlk::babState_struct::haveAnswer_

Definition at line 722 of file CbcGenCtlBlk.hpp.

7.2.2.5 OsiSolverInterface* CbcGenCtlBlk::babState_struct::answerSolver_

Definition at line 723 of file CbcGenCtlBlk.hpp.

The documentation for this struct was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcGenCtlBlk.hpp

7.3 CbcBaseModel Class Reference

Base model.

#include <CbcThread.hpp>

Public Member Functions

- CbcBaseModel ()
- virtual ∼CbcBaseModel ()

7.3.1 Detailed Description

Base model.

Definition at line 429 of file CbcThread.hpp.

7.3.2 Constructor & Destructor Documentation

```
7.3.2.1 CbcBaseModel::CbcBaseModel()
```

7.3.2.2 virtual CbcBaseModel::~CbcBaseModel() [inline], [virtual]

Definition at line 434 of file CbcThread.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcThread.hpp

7.4 CbcBranchAllDifferent Class Reference

Define a branch class that branches so that it is only satsified if all members have different values So cut is $x \le y-1$ or $x \ge y+1$.

#include <CbcBranchAllDifferent.hpp>

Inheritance diagram for CbcBranchAllDifferent:



Public Member Functions

- CbcBranchAllDifferent ()
- CbcBranchAllDifferent (CbcModel *model, int number, const int *which)

Useful constructor - passed set of integer variables which must all be different.

- CbcBranchAllDifferent (const CbcBranchAllDifferent &)
- virtual CbcObject * clone () const

Clone.

- CbcBranchAllDifferent & operator= (const CbcBranchAllDifferent &rhs)
- ∼CbcBranchAllDifferent ()
- virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const Infeasibility - large is 0.5.
- virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Creates a branching object.

Protected Attributes

• int numberInSet_

data

• int * which_

Which variables.

7.4.1 Detailed Description

Define a branch class that branches so that it is only satsified if all members have different values So cut is $x \le y-1$ or $x \ge y+1$.

Definition at line 22 of file CbcBranchAllDifferent.hpp.

- 7.4.2 Constructor & Destructor Documentation
- 7.4.2.1 CbcBranchAllDifferent::CbcBranchAllDifferent()
- 7.4.2.2 CbcBranchAllDifferent::CbcBranchAllDifferent (CbcModel * model, int number, const int * which)

Useful constructor - passed set of integer variables which must all be different.

- 7.4.2.3 CbcBranchAllDifferent::CbcBranchAllDifferent (const CbcBranchAllDifferent &)
- 7.4.2.4 CbcBranchAllDifferent::~CbcBranchAllDifferent()
- 7.4.3 Member Function Documentation
- 7.4.3.1 virtual CbcObject* CbcBranchAllDifferent::clone() const [virtual]

Clone.

Reimplemented from CbcBranchCut.

- 7.4.3.2 CbcBranchAllDifferent& CbcBranchAllDifferent::operator=(const CbcBranchAllDifferent & rhs)
- 7.4.3.3 virtual double CbcBranchAllDifferent::infeasibility (const OsiBranchingInformation * info, int & preferredWay) const [virtual]

Infeasibility - large is 0.5.

Reimplemented from CbcBranchCut.

7.4.3.4 virtual CbcBranchingObject* CbcBranchAllDifferent::createCbcBranch (OsiSolverInterface * solver, const OsiBranchingInformation * info, int way) [virtual]

Creates a branching object.

Reimplemented from CbcBranchCut.

- 7.4.4 Member Data Documentation
- **7.4.4.1** int CbcBranchAllDifferent::numberInSet_ [protected]

data

Number of entries

Definition at line 57 of file CbcBranchAllDifferent.hpp.

7.4.4.2 int* CbcBranchAllDifferent::which_ [protected]

Which variables.

Definition at line 59 of file CbcBranchAllDifferent.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcBranchAllDifferent.hpp

7.5 CbcBranchCut Class Reference

Define a cut branching class.

#include <CbcBranchCut.hpp>

Inheritance diagram for CbcBranchCut:



Public Member Functions

- CbcBranchCut ()
- CbcBranchCut (CbcModel *model)

In to maintain normal methods.

- CbcBranchCut (const CbcBranchCut &)
- virtual CbcObject * clone () const

Clone.

- CbcBranchCut & operator= (const CbcBranchCut &rhs)
- ∼CbcBranchCut ()
- virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const

Infeasibility.

• virtual void feasibleRegion ()

Set bounds to contain the current solution.

• virtual bool boundBranch () const

Return true if branch created by object should fix variables.

• virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Creates a branching object.

virtual CbcBranchingObject * preferredNewFeasible () const

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in the good direction.

virtual CbcBranchingObject * notPreferredNewFeasible () const

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a bad direction.

• virtual void resetBounds ()

Reset original upper and lower bound values from the solver.

Additional Inherited Members

7.5.1 Detailed Description

Define a cut branching class.

At present empty - all stuff in descendants

Definition at line 17 of file CbcBranchCut.hpp.

- 7.5.2 Constructor & Destructor Documentation
- 7.5.2.1 CbcBranchCut::CbcBranchCut()
- 7.5.2.2 CbcBranchCut::CbcBranchCut (CbcModel * model)

In to maintain normal methods.

- 7.5.2.3 CbcBranchCut::CbcBranchCut (const CbcBranchCut &)
- 7.5.2.4 CbcBranchCut::~CbcBranchCut()
- 7.5.3 Member Function Documentation
- 7.5.3.1 virtual CbcObject* CbcBranchCut::clone() const [virtual]

Clone.

Implements CbcObject.

Reimplemented in CbcBranchToFixLots, and CbcBranchAllDifferent.

- 7.5.3.2 CbcBranchCut& CbcBranchCut::operator= (const CbcBranchCut & rhs)
- 7.5.3.3 virtual double CbcBranchCut::infeasibility (const OsiBranchingInformation * info, int & preferredWay) const [virtual]

Infeasibility.

Reimplemented from CbcObject.

 $Reimplemented \ in \ CbcBranchToFixLots, \ and \ CbcBranchAllDifferent.$

7.5.3.4 virtual void CbcBranchCut::feasibleRegion() [virtual]

Set bounds to contain the current solution.

More precisely, for the variable associated with this object, take the value given in the current solution, force it within the current bounds if required, then set the bounds to fix the variable at the integer nearest the solution value.

At present this will do nothing

Implements CbcObject.

7.5.3.5 virtual bool CbcBranchCut::boundBranch () const [virtual]

Return true if branch created by object should fix variables.

7.5.3.6 virtual CbcBranchingObject* CbcBranchCut::createCbcBranch (OsiSolverInterface * solver, const OsiBranchingInformation * info, int way) [virtual]

Creates a branching object.

Reimplemented from CbcObject.

Reimplemented in CbcBranchToFixLots, and CbcBranchAllDifferent.

7.5.3.7 virtual CbcBranchingObject* CbcBranchCut::preferredNewFeasible() const [virtual]

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in the good direction.

The preferred branching object will force the variable to be +/-1 from its current value, depending on the reduced cost and objective sense. If movement in the direction which improves the objective is impossible due to bounds on the variable, the branching object will move in the other direction. If no movement is possible, the method returns NULL.

Only the bounds on this variable are considered when determining if the new point is feasible.

At present this does nothing

Reimplemented from CbcObject.

7.5.3.8 virtual CbcBranchingObject* CbcBranchCut::notPreferredNewFeasible() const [virtual]

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a bad direction.

As for preferredNewFeasible(), but the preferred branching object will force movement in a direction that degrades the objective.

At present this does nothing

Reimplemented from CbcObject.

7.5.3.9 virtual void CbcBranchCut::resetBounds() [virtual]

Reset original upper and lower bound values from the solver.

Handy for updating bounds held in this object after bounds held in the solver have been tightened.


The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcBranchCut.hpp

7.6 CbcBranchDecision Class Reference

#include <CbcBranchDecision.hpp>

Inheritance diagram for CbcBranchDecision:



Public Member Functions

CbcBranchDecision ()

Default Constructor.

- CbcBranchDecision (const CbcBranchDecision &)
- virtual ∼CbcBranchDecision ()

Destructor.

virtual CbcBranchDecision * clone () const =0

Clone.

virtual void initialize (CbcModel *model)=0

Initialize e.g. before starting to choose a branch at a node.

• virtual int betterBranch (CbcBranchingObject *thisOne, CbcBranchingObject *bestSoFar, double changeUp, int numberInfeasibilitiesUp, double changeDown, int numberInfeasibilitiesDown)=0

Compare two branching objects.

virtual int bestBranch (CbcBranchingObject **objects, int numberObjects, int numberUnsatisfied, double *changeUp, int *numberInfeasibilitiesUp, double *changeDown, int *numberInfeasibilitiesDown, double objectiveValue)

Compare N branching objects.

virtual int whichMethod ()

Says whether this method can handle both methods - 1 better, 2 best, 3 both.

virtual void saveBranchingObject (OsiBranchingObject *)

Saves a clone of current branching object.

virtual void updateInformation (OsiSolverInterface *, const CbcNode *)

Pass in information on branch just done.

virtual void setBestCriterion (double)

Sets or gets best criterion so far.

- · virtual double getBestCriterion () const
- virtual void generateCpp (FILE *)

Create C++ lines to get to current state.

• CbcModel * cbcModel () const

Model.

- OsiChooseVariable * chooseMethod () const
- void setChooseMethod (const OsiChooseVariable &method)

Set (clone) chooseMethod.

Protected Attributes

- CbcBranchingObject * object
- CbcModel * model

Pointer to model.

OsiChooseVariable * chooseMethod

7.6.1 Detailed Description

Definition at line 28 of file CbcBranchDecision.hpp.

```
7.6.2 Constructor & Destructor Documentation
7.6.2.1 CbcBranchDecision::CbcBranchDecision()
Default Constructor.
7.6.2.2 CbcBranchDecision::CbcBranchDecision ( const CbcBranchDecision & )
7.6.2.3 virtual CbcBranchDecision:: ~ CbcBranchDecision() [virtual]
Destructor.
7.6.3 Member Function Documentation
7.6.3.1 virtual CbcBranchDecision* CbcBranchDecision::clone() const [pure virtual]
Clone.
Implemented in CbcBranchDynamicDecision, and CbcBranchDefaultDecision.
7.6.3.2 virtual void CbcBranchDecision::initialize ( CbcModel * model ) [pure virtual]
Initialize e.g. before starting to choose a branch at a node.
Implemented in CbcBranchDynamicDecision, and CbcBranchDefaultDecision.
7.6.3.3 virtual int CbcBranchDecision::betterBranch ( CbcBranchingObject * thisOne, CbcBranchingObject * bestSoFar,
        double changeUp, int numberInfeasibilitiesUp, double changeDown, int numberInfeasibilitiesDown ) [pure
        virtual]
Compare two branching objects.
Return nonzero if branching using thisOne is better than branching using bestSoFar.
If bestSoFar is NULL, the routine should return a nonzero value. This routine is used only after strong branching.
Either this or bestBranch is used depending which user wants.
Implemented in CbcBranchDynamicDecision, and CbcBranchDefaultDecision.
7.6.3.4 virtual int CbcBranchDecision::bestBranch ( CbcBranchingObject ** objects, int numberObjects, int
        numberUnsatisfied, double * changeUp, int * numberInfeasibilitiesUp, double * changeDown, int *
        numberInfeasibilitiesDown, double objectiveValue ) [virtual]
Compare N branching objects.
Return index of best and sets way of branching in chosen object.
Either this or betterBranch is used depending which user wants.
Reimplemented in CbcBranchDefaultDecision.
7.6.3.5 virtual int CbcBranchDecision::whichMethod() [inline], [virtual]
```

Says whether this method can handle both methods - 1 better, 2 best, 3 both.

Reimplemented in CbcBranchDynamicDecision.

Definition at line 74 of file CbcBranchDecision.hpp.

7.6.3.6 virtual void CbcBranchDecision::saveBranchingObject (OsiBranchingObject *) [inline], [virtual] Saves a clone of current branching object. Can be used to update information on object causing branch - after branch Reimplemented in CbcBranchDynamicDecision. Definition at line 80 of file CbcBranchDecision.hpp. 7.6.3.7 virtual void CbcBranchDecision::updateInformation (OsiSolverInterface * , const CbcNode *) [inline], [virtual] Pass in information on branch just done. assumes object can get information from solver Reimplemented in CbcBranchDynamicDecision. Definition at line 83 of file CbcBranchDecision.hpp. 7.6.3.8 virtual void CbcBranchDecision::setBestCriterion (double) [inline], [virtual] Sets or gets best criterion so far. Reimplemented in CbcBranchDynamicDecision, and CbcBranchDefaultDecision. Definition at line 86 of file CbcBranchDecision.hpp. 7.6.3.9 virtual double CbcBranchDecision::getBestCriterion() const [inline], [virtual] Reimplemented in CbcBranchDynamicDecision, and CbcBranchDefaultDecision. Definition at line 87 of file CbcBranchDecision.hpp. 7.6.3.10 virtual void CbcBranchDecision::generateCpp(FILE*) [inline], [virtual] Create C++ lines to get to current state. Definition at line 91 of file CbcBranchDecision.hpp. 7.6.3.11 CbcModel* CbcBranchDecision::cbcModel() const [inline] Model. Definition at line 93 of file CbcBranchDecision.hpp. 7.6.3.12 OsiChooseVariable * CbcBranchDecision::chooseMethod() const [inline] Definition at line 107 of file CbcBranchDecision.hpp. 7.6.3.13 void CbcBranchDecision::setChooseMethod (const OsiChooseVariable & method) Set (clone) chooseMethod. 7.6.4 Member Data Documentation **7.6.4.1 CbcBranchingObject*** **CbcBranchDecision::object** [protected]

Definition at line 116 of file CbcBranchDecision.hpp.

7.6.4.2 CbcModel* CbcBranchDecision::model_ [protected]

Pointer to model.

Definition at line 118 of file CbcBranchDecision.hpp.

7.6.4.3 OsiChooseVariable* CbcBranchDecision::chooseMethod_ [protected]

Definition at line 122 of file CbcBranchDecision.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcBranchDecision.hpp

7.7 CbcBranchDefaultDecision Class Reference

Branching decision default class.

#include <CbcBranchDefaultDecision.hpp>

Inheritance diagram for CbcBranchDefaultDecision:



Public Member Functions

- CbcBranchDefaultDecision ()
- CbcBranchDefaultDecision (const CbcBranchDefaultDecision &)
- virtual ~CbcBranchDefaultDecision ()
- virtual CbcBranchDecision * clone () const

Clone.

virtual void initialize (CbcModel *model)

Initialize, e.g. before the start of branch selection at a node.

• virtual int betterBranch (CbcBranchingObject *thisOne, CbcBranchingObject *bestSoFar, double changeUp, int numInfUp, double changeDn, int numInfDn)

Compare two branching objects.

virtual void setBestCriterion (double value)

Sets or gets best criterion so far.

- · virtual double getBestCriterion () const
- virtual int bestBranch (CbcBranchingObject **objects, int numberObjects, int numberUnsatisfied, double *changeUp, int *numberInfeasibilitiesUp, double *changeDown, int *numberInfeasibilitiesDown, double objectiveValue)

Compare N branching objects.

Additional Inherited Members

7.7.1 Detailed Description

Branching decision default class.

This class implements a simple default algorithm (betterBranch()) for choosing a branching variable.

Definition at line 18 of file CbcBranchDefaultDecision.hpp.

- 7.7.2 Constructor & Destructor Documentation
- 7.7.2.1 CbcBranchDefaultDecision::CbcBranchDefaultDecision ()
- 7.7.2.2 CbcBranchDefaultDecision::CbcBranchDefaultDecision (const CbcBranchDefaultDecision &)
- 7.7.2.3 virtual CbcBranchDefaultDecision::~CbcBranchDefaultDecision() [virtual]
- 7.7.3 Member Function Documentation
- 7.7.3.1 virtual CbcBranchDecision* CbcBranchDefaultDecision::clone() const [virtual]

Clone.

Implements CbcBranchDecision.

7.7.3.2 virtual void CbcBranchDefaultDecision::initialize (CbcModel * model) [virtual]

Initialize, e.g. before the start of branch selection at a node.

Implements CbcBranchDecision.

7.7.3.3 virtual int CbcBranchDefaultDecision::betterBranch (CbcBranchingObject * thisOne, CbcBranchingObject * bestSoFar, double changeUp, int numInfUp, double changeDn, int numInfDn) [virtual]

Compare two branching objects.

Return nonzero if thisOne is better than bestSoFar.

The routine compares branches using the values supplied in <code>numInfUp</code> and <code>numInfDn</code> until a solution is found by search, after which it uses the values supplied in <code>changeUp</code> and <code>changeDn</code>. The best branching object seen so far and the associated parameter values are remembered in the <code>CbcBranchDefaultDecision</code> object. The nonzero return value is +1 if the up branch is preferred, -1 if the down branch is preferred.

As the names imply, the assumption is that the values supplied for <code>numInfUp</code> and <code>numInfDn</code> will be the number of infeasibilities reported by the branching object, and <code>changeUp</code> and <code>changeDn</code> will be the estimated change in objective. Other measures can be used if desired.

Because an CbcBranchDefaultDecision object remembers the current best branching candidate (#bestObject_) as well as the values used in the comparison, the parameter bestSoFar is redundant, hence unused.

Implements CbcBranchDecision.

7.7.3.4 virtual void CbcBranchDefaultDecision::setBestCriterion (double value) [virtual]

Sets or gets best criterion so far.

Reimplemented from CbcBranchDecision.

7.7.3.5 virtual double CbcBranchDefaultDecision::getBestCriterion() const [virtual]

Reimplemented from CbcBranchDecision.

7.7.3.6 virtual int CbcBranchDefaultDecision::bestBranch (CbcBranchingObject ** objects, int numberObjects, int numberUnsatisfied, double * changeUp, int * numberInfeasibilitiesUp, double * changeDown, int * numberInfeasibilitiesDown, double objectiveValue) [virtual]

Compare N branching objects.

Return index of best and sets way of branching in chosen object.

This routine is used only after strong branching.

Reimplemented from CbcBranchDecision.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcBranchDefaultDecision.hpp

7.8 CbcBranchDynamicDecision Class Reference

Branching decision dynamic class.

#include <CbcBranchDynamic.hpp>

Inheritance diagram for CbcBranchDynamicDecision:



Public Member Functions

- CbcBranchDynamicDecision ()
- CbcBranchDynamicDecision (const CbcBranchDynamicDecision &)
- virtual ∼CbcBranchDynamicDecision ()
- virtual CbcBranchDecision * clone () const

Clone

virtual void initialize (CbcModel *model)

Initialize, e.g. before the start of branch selection at a node.

• virtual int betterBranch (CbcBranchingObject *thisOne, CbcBranchingObject *bestSoFar, double changeUp, int numInfUp, double changeDn, int numInfDn)

Compare two branching objects.

virtual void setBestCriterion (double value)

Sets or gets best criterion so far.

- · virtual double getBestCriterion () const
- virtual int whichMethod ()

Says whether this method can handle both methods - 1 better, 2 best, 3 both.

• virtual void saveBranchingObject (OsiBranchingObject *object)

Saves a clone of current branching object.

• virtual void updateInformation (OsiSolverInterface *solver, const CbcNode *node)

Pass in information on branch just done.

Additional Inherited Members

7.8.1 Detailed Description

Branching decision dynamic class.

This class implements a simple algorithm (betterBranch()) for choosing a branching variable when dynamic pseudo costs

Definition at line 19 of file CbcBranchDynamic.hpp.

- 7.8.2 Constructor & Destructor Documentation
- 7.8.2.1 CbcBranchDynamicDecision::CbcBranchDynamicDecision ()
- 7.8.2.2 CbcBranchDynamicDecision::CbcBranchDynamicDecision (const CbcBranchDynamicDecision &)
- 7.8.2.3 virtual CbcBranchDynamicDecision:: ~ CbcBranchDynamicDecision () [virtual]
- 7.8.3 Member Function Documentation
- 7.8.3.1 virtual CbcBranchDecision* CbcBranchDynamicDecision::clone() const [virtual]

Clone.

Implements CbcBranchDecision.

7.8.3.2 virtual void CbcBranchDynamicDecision::initialize (CbcModel * model) [virtual]

Initialize, e.g. before the start of branch selection at a node.

Implements CbcBranchDecision.

7.8.3.3 virtual int CbcBranchDynamicDecision::betterBranch (CbcBranchingObject * thisOne, CbcBranchingObject * bestSoFar, double changeUp, int numInfUp, double changeDn, int numInfDn) [virtual]

Compare two branching objects.

Return nonzero if thisOne is better than bestSoFar.

The routine compares branches using the values supplied in <code>numInfUp</code> and <code>numInfDn</code> until a solution is found by search, after which it uses the values supplied in <code>changeUp</code> and <code>changeDn</code>. The best branching object seen so far and the associated parameter values are remembered in the <code>CbcBranchDynamicDecision</code> object. The nonzero return value is +1 if the up branch is preferred, -1 if the down branch is preferred.

As the names imply, the assumption is that the values supplied for <code>numInfUp</code> and <code>numInfDn</code> will be the number of infeasibilities reported by the branching object, and <code>changeUp</code> and <code>changeDn</code> will be the estimated change in objective. Other measures can be used if desired.

Because an CbcBranchDynamicDecision object remembers the current best branching candidate (#bestObject_) as well as the values used in the comparison, the parameter bestSoFar is redundant, hence unused.

Implements CbcBranchDecision.

7.8.3.4 virtual void CbcBranchDynamicDecision::setBestCriterion (double value) [virtual]

Sets or gets best criterion so far.

Reimplemented from CbcBranchDecision.

7.8.3.5 virtual double CbcBranchDynamicDecision::getBestCriterion() const [virtual]

Reimplemented from CbcBranchDecision.

7.8.3.6 virtual int CbcBranchDynamicDecision::whichMethod() [inline], [virtual]

Says whether this method can handle both methods - 1 better, 2 best, 3 both.

Reimplemented from CbcBranchDecision.

Definition at line 63 of file CbcBranchDynamic.hpp.

7.8.3.7 virtual void CbcBranchDynamicDecision::saveBranchingObject (OsiBranchingObject * object) [virtual]

Saves a clone of current branching object.

Can be used to update information on object causing branch - after branch

Reimplemented from CbcBranchDecision.

7.8.3.8 virtual void CbcBranchDynamicDecision::updateInformation (OsiSolverInterface * solver, const CbcNode * node) [virtual]

Pass in information on branch just done.

assumes object can get information from solver

Reimplemented from CbcBranchDecision.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcBranchDynamic.hpp

7.9 CbcBranchingObject Class Reference

Abstract branching object base class Now just difference with OsiBranchingObject.

#include <CbcBranchingObject.hpp>

Inheritance diagram for CbcBranchingObject:



Public Member Functions

• CbcBranchingObject ()

Default Constructor.

• CbcBranchingObject (CbcModel *model, int variable, int way, double value)

Constructor.

• CbcBranchingObject (const CbcBranchingObject &)

Copy constructor.

• CbcBranchingObject & operator= (const CbcBranchingObject &rhs)

Assignment operator.

• virtual CbcBranchingObject * clone () const =0

Clone

• virtual ~CbcBranchingObject ()

Destructor.

virtual int fillStrongInfo (CbcStrongInfo &)

Some branchingObjects may claim to be able to skip strong branching.

void resetNumberBranchesLeft ()

Reset number of branches left to original.

void setNumberBranches (int value)

Set number of branches to do.

• virtual double branch ()=0

Execute the actions required to branch, as specified by the current state of the branching object, and advance the object's state.

virtual double branch (OsiSolverInterface *)

Execute the actions required to branch, as specified by the current state of the branching object, and advance the object's state.

virtual void fix (OsiSolverInterface *, double *, double *, int) const

Update bounds in solver as in 'branch' and update given bounds.

virtual bool tighten (OsiSolverInterface *)

Change (tighten) bounds in object to reflect bounds in solver.

• virtual void previousBranch ()

Reset every information so that the branching object appears to point to the previous child.

• virtual void print () const

Print something about branch - only if log level high.

· int variable () const

Index identifying the associated CbcObject within its class.

• int way () const

Get the state of the branching object.

void way (int way)

Set the state of the branching object.

void setModel (CbcModel *model)

update model

• CbcModel * model () const

Return model.

• CbcObject * object () const

Return pointer back to object which created.

void setOriginalObject (CbcObject *object)

Set pointer back to object which created.

virtual CbcBranchObjType type () const =0

Return the type (an integer identifier) of this.

virtual int compareOriginalObject (const CbcBranchingObject *brObj) const

Compare the original object of this with the original object of brobj.

 virtual CbcRangeCompare compareBranchingObject (const CbcBranchingObject *brObj, const bool replaceIf-Overlap=false)=0

Compare the this with brObj.

Protected Attributes

CbcModel * model_

The model that owns this branching object.

CbcObject * originalCbcObject_

Pointer back to object which created.

int variable_

Branching variable (0 is first integer)

int way

The state of the branching object.

7.9.1 Detailed Description

Abstract branching object base class Now just difference with OsiBranchingObject.

In the abstract, an CbcBranchingObject contains instructions for how to branch. We want an abstract class so that we can describe how to branch on simple objects (*e.g.*, integers) and more exotic objects (*e.g.*, cliques or hyperplanes).

The branch() method is the crucial routine: it is expected to be able to step through a set of branch arms, executing the actions required to create each subproblem in turn. The base class is primarily virtual to allow for a wide range of problem modifications.

See CbcObject for an overview of the three classes (CbcObject, CbcBranchingObject, and CbcBranchDecision) which make up cbc's branching model.

Definition at line 53 of file CbcBranchingObject.hpp.

```
7.9.2 Constructor & Destructor Documentation
```

7.9.2.1 CbcBranchingObject::CbcBranchingObject()

Default Constructor.

7.9.2.2 CbcBranchingObject::CbcBranchingObject (CbcModel * model, int variable, int way, double value)

Constructor.

7.9.2.3 CbcBranchingObject::CbcBranchingObject (const CbcBranchingObject &)

Copy constructor.

7.9.2.4 virtual CbcBranchingObject::~CbcBranchingObject() [virtual]

Destructor.

7.9.3 Member Function Documentation

7.9.3.1 CbcBranchingObject & CbcBranchingObject & rhs)

Assignment operator.

7.9.3.2 virtual CbcBranchingObject* CbcBranchingObject::clone() const [pure virtual]

Clone.

Implemented in CbcIntegerPseudoCostBranchingObject, CbcLongCliqueBranchingObject, CbcSOSBranchingObject, CbcLotsizeBranchingObject, CbcCliqueBranchingObject, CbcDynamicPseudoCostBranchingObject, CbcCutBranchingObject, CbcNWayBranchingObject, CbcFixingBranchingObject, CbcIntegerBranchingObject, and Cbc-DummyBranchingObject.

7.9.3.3 virtual int CbcBranchingObject::fillStrongInfo (CbcStrongInfo &) [inline], [virtual]

Some branchingObjects may claim to be able to skip strong branching.

If so they have to fill in CbcStrongInfo. The object mention in incoming CbcStrongInfo must match. Returns nonzero if skip is wanted

Reimplemented in CbcDynamicPseudoCostBranchingObject.

Definition at line 79 of file CbcBranchingObject.hpp.

7.9.3.4 void CbcBranchingObject::resetNumberBranchesLeft() [inline]

Reset number of branches left to original.

Definition at line 83 of file CbcBranchingObject.hpp.

7.9.3.5 void CbcBranchingObject::setNumberBranches (int value) [inline]

Set number of branches to do.

Definition at line 87 of file CbcBranchingObject.hpp.

```
7.9.3.6 virtual double CbcBranchingObject::branch() [pure virtual]
```

Execute the actions required to branch, as specified by the current state of the branching object, and advance the object's state.

Mainly for diagnostics, whether it is true branch or strong branching is also passed. Returns change in guessed objective on next branch

Implemented in CbcIntegerPseudoCostBranchingObject, CbcLongCliqueBranchingObject, CbcSOSBranchingObject, CbcLotsizeBranchingObject, CbcCliqueBranchingObject, CbcDynamicPseudoCostBranchingObject, CbcCutBranchingObject, CbcNWayBranchingObject, CbcFixingBranchingObject, CbcIntegerBranchingObject, and Cbc-DummyBranchingObject.

```
7.9.3.7 virtual double CbcBranchingObject::branch ( OsiSolverInterface * ) [inline], [virtual]
```

Execute the actions required to branch, as specified by the current state of the branching object, and advance the object's state.

Mainly for diagnostics, whether it is true branch or strong branching is also passed. Returns change in guessed objective on next branch

Definition at line 105 of file CbcBranchingObject.hpp.

```
7.9.3.8 virtual void CbcBranchingObject::fix ( OsiSolverInterface * , double * , double * , int ) const [inline], [virtual]
```

Update bounds in solver as in 'branch' and update given bounds.

branchState is -1 for 'down' +1 for 'up'

Reimplemented in CbcSOSBranchingObject, and CbcIntegerBranchingObject.

Definition at line 110 of file CbcBranchingObject.hpp.

```
7.9.3.9 virtual bool CbcBranchingObject::tighten ( OsiSolverInterface * ) [inline], [virtual]
```

Change (tighten) bounds in object to reflect bounds in solver.

Return true if now fixed

Reimplemented in CbcIntegerBranchingObject.

Definition at line 116 of file CbcBranchingObject.hpp.

```
7.9.3.10 virtual void CbcBranchingObject::previousBranch() [inline], [virtual]
```

Reset every information so that the branching object appears to point to the previous child.

This method does not need to modify anything in any solver.

Reimplemented in CbcSOSBranchingObject.

Definition at line 121 of file CbcBranchingObject.hpp.

```
7.9.3.11 virtual void CbcBranchingObject::print() const [inline], [virtual]
```

Print something about branch - only if log level high.

Definition at line 130 of file CbcBranchingObject.hpp.

```
7.9.3.12 int CbcBranchingObject::variable ( ) const [inline]
```

Index identifying the associated CbcObject within its class.

The name is misleading, and typically the index will *not* refer directly to a variable. Rather, it identifies an CbcObject within the class of similar CbcObjects

E.g., for an CbcSimpleInteger, variable() is the index of the integer variable in the set of integer variables (*not* the index of the variable in the set of all variables).

Definition at line 143 of file CbcBranchingObject.hpp.

```
7.9.3.13 int CbcBranchingObject::way ( ) const [inline]
```

Get the state of the branching object.

Returns a code indicating the active arm of the branching object. The precise meaning is defined in the derived class.

See Also

way_

Definition at line 154 of file CbcBranchingObject.hpp.

```
7.9.3.14 void CbcBranchingObject::way (int way) [inline]
```

Set the state of the branching object.

See way()

Definition at line 162 of file CbcBranchingObject.hpp.

```
7.9.3.15 void CbcBranchingObject::setModel ( CbcModel * model ) [inline]
```

update model

Definition at line 167 of file CbcBranchingObject.hpp.

```
7.9.3.16 CbcModel* CbcBranchingObject::model( )const [inline]
```

Return model.

Definition at line 171 of file CbcBranchingObject.hpp.

```
7.9.3.17 CbcObject* CbcBranchingObject::object( ) const [inline]
```

Return pointer back to object which created.

Definition at line 176 of file CbcBranchingObject.hpp.

```
7.9.3.18 void CbcBranchingObject::setOriginalObject ( CbcObject * object ) [inline]
```

Set pointer back to object which created.

Definition at line 180 of file CbcBranchingObject.hpp.

7.9.3.19 virtual CbcBranchObjType CbcBranchingObject::type() const [pure virtual]

Return the type (an integer identifier) of this.

See definition of CbcBranchObjType above for possibilities

Implemented in CbcIntegerPseudoCostBranchingObject, CbcLongCliqueBranchingObject, CbcSOSBranchingObject, CbcLotsizeBranchingObject, CbcCliqueBranchingObject, CbcDynamicPseudoCostBranchingObject, CbcCutBranchingObject, CbcNWayBranchingObject, CbcIntegerBranchingObject, CbcFixingBranchingObject, and Cbc-DummyBranchingObject.

7.9.3.20 virtual int CbcBranchingObject::compareOriginalObject (const CbcBranchingObject * brObj) const [inline], [virtual]

Compare the original object of this with the original object of brObj.

Assumes that there is an ordering of the original objects. This method should be invoked only if this and brObj are of the same type. Return negative/0/positive depending on whether this is smaller/same/larger than the argument.

Reimplemented in CbcLongCliqueBranchingObject, CbcSOSBranchingObject, CbcCliqueBranchingObject, CbcCut-BranchingObject, CbcNWayBranchingObject, CbcFixingBranchingObject, and CbcDummyBranchingObject.

Definition at line 199 of file CbcBranchingObject.hpp.

7.9.3.21 virtual CbcRangeCompare CbcBranchingObject::compareBranchingObject (const CbcBranchingObject * brObj, const bool replaceIfOverlap = false) [pure virtual]

Compare the this with brObj.

this and brobj must be of the same type and must have the same original object, but they may have different feasible regions. Return the appropriate CbcRangeCompare value (first argument being the sub/superset if that's the case). In case of overlap (and if replaceIfOverlap is true) replace the current branching object with one whose feasible region is the overlap.

Implemented in CbcIntegerPseudoCostBranchingObject, CbcLongCliqueBranchingObject, CbcSOSBranchingObject, CbcLotsizeBranchingObject, CbcCliqueBranchingObject, CbcCutBranchingObject, CbcNWayBranchingObject, CbcIntegerBranchingObject, CbcFixingBranchingObject, and CbcDummyBranchingObject.

7.9.4 Member Data Documentation

7.9.4.1 CbcModel* CbcBranchingObject::model_ [protected]

The model that owns this branching object.

Definition at line 218 of file CbcBranchingObject.hpp.

7.9.4.2 CbcObject* CbcBranchingObject::originalCbcObject_ [protected]

Pointer back to object which created.

Definition at line 220 of file CbcBranchingObject.hpp.

7.9.4.3 int CbcBranchingObject::variable_ [protected]

Branching variable (0 is first integer)

Definition at line 223 of file CbcBranchingObject.hpp.

7.9.4.4 int CbcBranchingObject::way_ [protected]

The state of the branching object.

Specifies the active arm of the branching object. Coded as -1 to take the 'down' arm, +1 for the 'up' arm. 'Down' and 'up' are defined based on the natural meaning (floor and ceiling, respectively) for a simple integer. The precise meaning is defined in the derived class.

Definition at line 232 of file CbcBranchingObject.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcBranchingObject.hpp

7.10 CbcBranchToFixLots Class Reference

Define a branch class that branches so that one way variables are fixed while the other way cuts off that solution.

#include <CbcBranchToFixLots.hpp>

Inheritance diagram for CbcBranchToFixLots:



Public Member Functions

- CbcBranchToFixLots ()
- CbcBranchToFixLots (CbcModel *model, double djTolerance, double fractionFixed, int depth, int numberClean=0, const char *mark=NULL, bool alwaysCreate=false)

Useful constructor - passed reduced cost tolerance and fraction we would like fixed.

- CbcBranchToFixLots (const CbcBranchToFixLots &)
- virtual CbcObject * clone () const

Clone

- CbcBranchToFixLots & operator= (const CbcBranchToFixLots &rhs)
- ∼CbcBranchToFixLots ()
- int shallWe () const

Does a lot of the work, Returns 0 if no good, 1 if dj, 2 if clean, 3 if both FIXME: should use enum or equivalent to make these numbers clearer.

- virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const
 - Infeasibility for an integer variable large is 0.5, but also can be infinity when known infeasible.
- virtual bool canDoHeuristics () const

Return true if object can take part in normal heuristics.

virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Creates a branching object.

virtual void redoSequenceEtc (CbcModel *model, int numberColumns, const int *originalColumns)

Redoes data when sequence numbers change.

Protected Attributes

double diTolerance

data

double fractionFixed_

We only need to make sure this fraction fixed.

• char * mark

Never fix ones marked here.

CoinPackedMatrix matrixByRow_

Matrix by row.

int depth

Do if depth multiple of this.

int numberClean

number of ==1 rows which need to be clean

bool alwaysCreate_

If true then always create branch.

7.10.1 Detailed Description

Define a branch class that branches so that one way variables are fixed while the other way cuts off that solution.

a) On reduced cost b) When enough ==1 or <=1 rows have been satisfied (not fixed - satisfied)

Definition at line 23 of file CbcBranchToFixLots.hpp.

- 7.10.2 Constructor & Destructor Documentation
- 7.10.2.1 CbcBranchToFixLots::CbcBranchToFixLots ()
- 7.10.2.2 CbcBranchToFixLots::CbcBranchToFixLots (CbcModel * model, double djTolerance, double fractionFixed, int depth, int numberClean = 0, const char * mark = NULL, bool alwaysCreate = false)

Useful constructor - passed reduced cost tolerance and fraction we would like fixed.

Also depth level to do at. Also passed number of 1 rows which when clean triggers fix Always does if all 1 rows cleaned up and number>0 or if fraction columns reached Also whether to create branch if can't reach fraction.

- 7.10.2.3 CbcBranchToFixLots::CbcBranchToFixLots (const CbcBranchToFixLots &)
- 7.10.2.4 CbcBranchToFixLots::~CbcBranchToFixLots()
- 7.10.3 Member Function Documentation
- 7.10.3.1 virtual CbcObject* CbcBranchToFixLots::clone() const [virtual]

Clone.

Reimplemented from CbcBranchCut.

7.10.3.2 CbcBranchToFixLots& CbcBranchToFixLots & rhs)

7.10.3.3 int CbcBranchToFixLots::shallWe () const

Does a lot of the work, Returns 0 if no good, 1 if dj, 2 if clean, 3 if both FIXME: should use enum or equivalent to make these numbers clearer.

7.10.3.4 virtual double CbcBranchToFixLots::infeasibility (const OsiBranchingInformation * info, int & preferredWay) const [virtual]

Infeasibility for an integer variable - large is 0.5, but also can be infinity when known infeasible.

Reimplemented from CbcBranchCut.

7.10.3.5 virtual bool CbcBranchToFixLots::canDoHeuristics () const [inline], [virtual]

Return true if object can take part in normal heuristics.

Definition at line 65 of file CbcBranchToFixLots.hpp.

7.10.3.6 virtual CbcBranchingObject* CbcBranchToFixLots::createCbcBranch (OsiSolverInterface * solver, const OsiBranchingInformation * info, int way) [virtual]

Creates a branching object.

Reimplemented from CbcBranchCut.

7.10.3.7 virtual void CbcBranchToFixLots::redoSequenceEtc (CbcModel * model, int numberColumns, const int * originalColumns) [virtual]

Redoes data when sequence numbers change.

Reimplemented from CbcObject.

7.10.4 Member Data Documentation

7.10.4.1 double CbcBranchToFixLots::djTolerance [protected]

data

Reduced cost tolerance i.e. dj has to be >= this before fixed

Definition at line 79 of file CbcBranchToFixLots.hpp.

7.10.4.2 double CbcBranchToFixLots::fractionFixed_ [protected]

We only need to make sure this fraction fixed.

Definition at line 81 of file CbcBranchToFixLots.hpp.

7.10.4.3 char* CbcBranchToFixLots::mark [protected]

Never fix ones marked here.

Definition at line 83 of file CbcBranchToFixLots.hpp.

7.10.4.4 CoinPackedMatrix CbcBranchToFixLots::matrixByRow [protected]

Matrix by row.

Definition at line 85 of file CbcBranchToFixLots.hpp.

7.10.4.5 int CbcBranchToFixLots::depth_ [protected]

Do if depth multiple of this.

Definition at line 87 of file CbcBranchToFixLots.hpp.

7.10.4.6 int CbcBranchToFixLots::numberClean_ [protected]

number of ==1 rows which need to be clean

Definition at line 89 of file CbcBranchToFixLots.hpp.

7.10.4.7 bool CbcBranchToFixLots::alwaysCreate_ [protected]

If true then always create branch.

Definition at line 91 of file CbcBranchToFixLots.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcBranchToFixLots.hpp

7.11 CbcCbcParam Class Reference

Class for control parameters that act on a CbcModel object.

#include <CbcGenCbcParam.hpp>

Inheritance diagram for CbcCbcParam:



Public Types

Subtypes

enum CbcCbcParamCode {
 CBCCBC_FIRSTPARAM = CbcGenParam::CBCGEN_LASTPARAM + 1, ALLOWABLEGAP, COSTSTRATE-GY, CUTDEPTH,

CUTOFF, CUTPASS, DIRECTION, GAPRATIO,

INCREMENT, INFEASIBILITYWEIGHT, INTEGERTOLERANCE, LOGLEVEL,

MAXIMIZE, MAXNODES, MINIMIZE, MIPOPTIONS,

MOREMIPOPTIONS, NUMBERANALYZE, NUMBERBEFORE, NUMBERMINI,

STRONGBRANCHING, TIMELIMIT BAB, CBCCBC LASTPARAM }

Enumeration for parameters that control a CbcModel object.

Public Member Functions

Constructors and Destructors

Be careful how you specify parameters for the constructors! There's great potential for confusion.

• CbcCbcParam ()

Default constructor.

CbcCbcParam (CbcCbcParamCode code, std::string name, std::string help, double lower, double upper, double dflt=0.0, bool display=true)

Constructor for a parameter with a double value.

CbcCbcParam (CbcCbcParamCode code, std::string name, std::string help, int lower, int upper, int dflt=0, bool display=true)

Constructor for a parameter with an integer value.

CbcCbcParam (CbcCbcParamCode code, std::string name, std::string help, std::string firstValue, int dflt, bool display=true)

Constructor for a parameter with keyword values.

- CbcCbcParam (CbcCbcParamCode code, std::string name, std::string help, std::string dflt, bool display=true)

 Constructor for a string parameter.
- CbcCbcParam (CbcCbcParamCode code, std::string name, std::string help, bool display=true)

Constructor for an action parameter.

CbcCbcParam (const CbcCbcParam &orig)

Copy constructor.

CbcCbcParam * clone ()

Clone

CbcCbcParam & operator= (const CbcCbcParam &rhs)

Assignment.

∼CbcCbcParam ()

Destructor.

Methods to query and manipulate a parameter object

CbcCbcParamCode paramCode () const

Get the parameter code.

void setParamCode (CbcCbcParamCode code)

Set the parameter code.

CbcModel * obj () const

Get the underlying CbcModel object.

void setObj (CbcModel *obj)

Set the underlying CbcModel object.

7.11.1 Detailed Description

Class for control parameters that act on a CbcModel object.

Adds parameter type codes and push/pull functions to the generic parameter object.

Definition at line 31 of file CbcGenCbcParam.hpp.

7.11.2 Member Enumeration Documentation

7.11.2.1 enum CbcCbcParam::CbcCbcParamCode

Enumeration for parameters that control a CbcModel object.

These are parameters that control the operation of a CbcModel object. CBCCBC_FIRSTPARAM and CBCCBC_LAST-PARAM are markers to allow convenient separation of parameter groups.

Enumerator

CBCCBC_FIRSTPARAM

ALLOWABLEGAP

COSTSTRATEGY

CUTDEPTH

CUTOFF

CUTPASS

DIRECTION

GAPRATIO

INCREMENT

INFEASIBILITYWEIGHT

INTEGERTOLERANCE

LOGLEVEL

MAXIMIZE

MAXNODES

MINIMIZE

MIPOPTIONS

MOREMIPOPTIONS

NUMBERANALYZE

NUMBERBEFORE

NUMBERMINI

STRONGBRANCHING

TIMELIMIT_BAB

CBCCBC_LASTPARAM

Definition at line 45 of file CbcGenCbcParam.hpp.

7.11.3 Constructor & Destructor Documentation

7.11.3.1 CbcCbcParam::CbcCbcParam()

Default constructor.

7.11.3.2 CbcCbcParam::CbcCbcParam (CbcCbcParamCode code, std::string name, std::string help, double lower, double upper, double dflt = 0 . 0, bool display = true)

Constructor for a parameter with a double value.

The default value is 0.0. Be careful to clearly indicate that lower and upper are real (double) values to distinguish this constructor from the constructor for an integer parameter.

7.11.3.3 CbcCbcParam::CbcCbcParam (CbcCbcParamCode code, std::string name, std::string help, int lower, int upper, int dflt = 0, bool display = true)

Constructor for a parameter with an integer value.

The default value is 0.

7.11.3.4 CbcCbcParam::CbcCbcParam (CbcCbcParamCode code, std::string name, std::string help, std::string firstValue, int dfit, bool display = true)

Constructor for a parameter with keyword values.

The string supplied as firstValue becomes the first keyword. Additional keywords can be added using append-Kwd(). Keywords are numbered from zero. It's necessary to specify both the first keyword (firstValue) and the default keyword index (dflt) in order to distinguish this constructor from the string and action parameter constructors.

7.11.3.5 CbcCbcParam::CbcCbcParam (CbcCbcParamCode code, std::string name, std::string help, std::string dflt, bool display = true)

Constructor for a string parameter.

The default string value must be specified explicitly to distinguish a string constructor from an action parameter constructor.

7.11.3.6 CbcCbcParam::CbcCbcParam (CbcCbcParamCode code, std::string name, std::string help, bool display = true)

Constructor for an action parameter.

7.11.3.7 CbcCbcParam::CbcCbcParam (const CbcCbcParam & orig)

Copy constructor.

7.11.3.8 CbcCbcParam::~CbcCbcParam()

Destructor.

7.11.4 Member Function Documentation

7.11.4.1 CbcCbcParam * CbcCbcParam::clone ()

Clone.

7.11.4.2 CbcCbcParam& CbcCbcParam::operator= (const CbcCbcParam & rhs)

Assignment.

7.11.4.3 CbcCbcParamCode CbcCbcParam::paramCode () const [inline]

Get the parameter code.

Definition at line 139 of file CbcGenCbcParam.hpp.

7.11.4.4 void CbcCbcParam::setParamCode (CbcCbcParamCode code) [inline]

Set the parameter code.

Definition at line 145 of file CbcGenCbcParam.hpp.

7.11.4.5 CbcModel* CbcCbcParam::obj()const [inline]

Get the underlying CbcModel object.

Definition at line 151 of file CbcGenCbcParam.hpp.

7.11.4.6 void CbcCbcParam::setObj (CbcModel * obj) [inline]

Set the underlying CbcModel object.

Definition at line 157 of file CbcGenCbcParam.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcGenCbcParam.hpp

7.12 CbcClique Class Reference

Branching object for cliques.

#include <CbcClique.hpp>

Inheritance diagram for CbcClique:



Public Member Functions

• CbcClique ()

Default Constructor.

CbcClique (CbcModel *model, int cliqueType, int numberMembers, const int *which, const char *type, int identifier, int slack=-1)

Useful constructor (which are integer indices) slack can denote a slack in set.

CbcClique (const CbcClique &)

Copy constructor.

virtual CbcObject * clone () const

Clone

• CbcClique & operator= (const CbcClique &rhs)

Assignment operator.

virtual ∼CbcClique ()

Destructor.

• virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const

Infeasibility - large is 0.5.

virtual void feasibleRegion ()

This looks at solution and sets bounds to contain solution.

virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Creates a branching object.

· int numberMembers () const

Number of members.

• int numberNonSOSMembers () const

Number of variables with -1 coefficient.

• const int * members () const

Members (indices in range 0 ... numberIntegers_-1)

• char type (int index) const

Type of each member, i.e., which way is strong.

int cliqueType () const

```
Clique type: 0 is \leq=, 1 is ==.
```

virtual void redoSequenceEtc (CbcModel *model, int numberColumns, const int *originalColumns)

Redoes data when sequence numbers change.

Protected Attributes

int numberMembers

data Number of members

int numberNonSOSMembers

Number of Non SOS members i.e. fixing to zero is strong.

int * members

Members (indices in range 0 ... numberIntegers_-1)

char * type_

Strong value for each member.

int cliqueType_

Clique type.

int slack_

Slack variable for the clique.

7.12.1 Detailed Description

Branching object for cliques.

A clique is defined to be a set of binary variables where fixing any one variable to its 'strong' value fixes all other variables. An example is the most common SOS1 construction: a set of binary variables x_j s.t. SUM{j} $x_j = 1$. Setting any one variable to 1 forces all other variables to 0. (See comments for CbcSOS below.)

Other configurations are possible, however: Consider $x1-x2+x3 \le 0$. Setting x1 (x3) to 1 forces x2 to 1 and x3 (x1) to 0. Setting x2 to 0 forces x1 and x3 to 0.

The proper point of view to take when interpreting CbcClique is 'generalisation of SOS1 on binary variables.' To get into the proper frame of mind, here's an example.

Consider the following sequence, where $x_j = (1-y_j)$:

```
x1 + x2 + x3 \le 1 all strong at 1

x1 - y2 + x3 \le 0 y2 strong at 0; x1, x3 strong at 1

-y1 - y2 + x3 \le -1 y1, y2 strong at 0, x3 strong at 1

-y1 - y2 - y3 \le -2 all strong at 0
```

The first line is a standard SOS1 on binary variables.

Variables with +1 coefficients are 'SOS-style' and variables with -1 coefficients are 'non-SOS-style'. So numberNonSO-SMembers_ simply tells you how many variables have -1 coefficients. The implicit rhs for a clique is 1-numberNonSOS-Members .

Definition at line 41 of file CbcClique.hpp.

```
7.12.2 Constructor & Destructor Documentation
7.12.2.1 CbcClique::CbcClique()
Default Constructor.
7.12.2.2 CbcClique::CbcClique ( CbcModel * model, int cliqueType, int numberMembers, const int * which, const char * type,
         int identifier, int slack = -1)
Useful constructor (which are integer indices) slack can denote a slack in set.
If type == NULL then as if 1
7.12.2.3 CbcClique::CbcClique ( const CbcClique & )
Copy constructor.
7.12.2.4 virtual CbcClique::~CbcClique( ) [virtual]
Destructor.
7.12.3 Member Function Documentation
7.12.3.1 virtual CbcObject* CbcClique::clone() const [virtual]
Clone.
Implements CbcObject.
7.12.3.2 CbcClique& CbcClique::operator= ( const CbcClique & rhs )
Assignment operator.
7.12.3.3 virtual double CbcClique::infeasibility ( const OsiBranchingInformation * info, int & preferredWay ) const [virtual]
Infeasibility - large is 0.5.
Reimplemented from CbcObject.
7.12.3.4 virtual void CbcClique::feasibleRegion() [virtual]
This looks at solution and sets bounds to contain solution.
Implements CbcObject.
7.12.3.5 virtual CbcBranchingObject* CbcClique::createCbcBranch ( OsiSolverInterface * solver, const
         OsiBranchingInformation * info, int way ) [virtual]
Creates a branching object.
Reimplemented from CbcObject.
7.12.3.6 int CbcClique::numberMembers ( ) const [inline]
Number of members.
Definition at line 78 of file CbcClique.hpp.
```

7.12.3.7 int CbcClique::numberNonSOSMembers () const [inline]

Number of variables with -1 coefficient.

Number of non-SOS members, i.e., fixing to zero is strong. See comments at head of class, and comments for type_. Definition at line 86 of file CbcClique.hpp.

7.12.3.8 const int* CbcClique::members () const [inline]

Members (indices in range 0 ... numberIntegers_-1)

Definition at line 91 of file CbcClique.hpp.

7.12.3.9 char CbcClique::type (int index) const [inline]

Type of each member, i.e., which way is strong.

This also specifies whether a variable has a +1 or -1 coefficient.

- 0 => -1 coefficient, 0 is strong value
- 1 => +1 coefficient, 1 is strong value If unspecified, all coefficients are assumed to be positive.

Indexed as 0 .. numberMembers -1

Definition at line 104 of file CbcClique.hpp.

7.12.3.10 int CbcClique::cliqueType() const [inline]

Clique type: 0 is \leq =, 1 is ==.

Definition at line 110 of file CbcClique.hpp.

7.12.3.11 virtual void CbcClique::redoSequenceEtc (CbcModel * model, int numberColumns, const int * originalColumns)
[virtual]

Redoes data when sequence numbers change.

Reimplemented from CbcObject.

7.12.4 Member Data Documentation

7.12.4.1 int CbcClique::numberMembers_ [protected]

data Number of members

Definition at line 119 of file CbcClique.hpp.

7.12.4.2 int CbcClique::numberNonSOSMembers_ [protected]

Number of Non SOS members i.e. fixing to zero is strong.

Definition at line 122 of file CbcClique.hpp.

7.12.4.3 int* CbcClique::members_ [protected]

Members (indices in range 0 ... numberIntegers -1)

Definition at line 125 of file CbcClique.hpp.

7.12.4.4 char* CbcClique::type_ [protected]

Strong value for each member.

This also specifies whether a variable has a +1 or -1 coefficient.

- 0 => -1 coefficient, 0 is strong value
- 1 => +1 coefficient, 1 is strong value If unspecified, all coefficients are assumed to be positive.

Indexed as 0 .. numberMembers_-1

Definition at line 136 of file CbcClique.hpp.

7.12.4.5 int CbcClique::cliqueType_ [protected]

Clique type.

0 defines a \leq = relation, 1 an equality. The assumed value of the rhs is numberNonSOSMembers_+1. (See comments for the class.)

Definition at line 143 of file CbcClique.hpp.

7.12.4.6 int CbcClique::slack_ [protected]

Slack variable for the clique.

Identifies the slack variable for the clique (typically added to convert a <= relation to an equality). Value is sequence number within clique menbers.

Definition at line 151 of file CbcClique.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcClique.hpp

7.13 CbcCliqueBranchingObject Class Reference

Branching object for unordered cliques.

#include <CbcClique.hpp>

Inheritance diagram for CbcCliqueBranchingObject:



Public Member Functions

- CbcCliqueBranchingObject ()
- CbcCliqueBranchingObject (CbcModel *model, const CbcClique *clique, int way, int numberOnDownSide, const int *down, int numberOnUpSide, const int *up)

- CbcCliqueBranchingObject (const CbcCliqueBranchingObject &)
- CbcCliqueBranchingObject & operator= (const CbcCliqueBranchingObject &rhs)
- virtual CbcBranchingObject * clone () const

Clone.

- virtual ~CbcCliqueBranchingObject ()
- virtual double branch ()

Does next branch and updates state.

· virtual void print ()

Print something about branch - only if log level high.

virtual CbcBranchObjType type () const

Return the type (an integer identifier) of this.

virtual int compareOriginalObject (const CbcBranchingObject *brObj) const

Compare the original object of this with the original object of brobj.

 virtual CbcRangeCompare compareBranchingObject (const CbcBranchingObject *brObj, const bool replaceIf-Overlap=false)

Compare the this with brobj.

Additional Inherited Members

7.13.1 Detailed Description

Branching object for unordered cliques.

Intended for cliques which are long enough to make it worthwhile but <= 64 members. There will also be ones for long cliques.

Variable_ is the clique id number (redundant, as the object also holds a pointer to the clique.

Definition at line 162 of file CbcClique.hpp.

- 7.13.2 Constructor & Destructor Documentation
- 7.13.2.1 CbcCliqueBranchingObject::CbcCliqueBranchingObject()
- 7.13.2.2 CbcCliqueBranchingObject::CbcCliqueBranchingObject (CbcModel * model, const CbcClique * clique, int way, int numberOnDownSide, const int * down, int numberOnUpSide, const int * up)
- 7.13.2.3 CbcCliqueBranchingObject::CbcCliqueBranchingObject (const CbcCliqueBranchingObject &)
- 7.13.2.4 virtual CbcCliqueBranchingObject::~CbcCliqueBranchingObject() [virtual]
- 7.13.3 Member Function Documentation
- 7.13.3.1 CbcCliqueBranchingObject& CbcCliqueBranchingObject::operator=(const CbcCliqueBranchingObject & rhs)
- 7.13.3.2 virtual CbcBranchingObject* CbcCliqueBranchingObject::clone() const [virtual]

Clone.

Implements CbcBranchingObject.

7.13.3.3 virtual double CbcCliqueBranchingObject::branch() [virtual]

Does next branch and updates state.

Implements CbcBranchingObject.

7.13.3.4 virtual void CbcCliqueBranchingObject::print() [virtual]

Print something about branch - only if log level high.

7.13.3.5 virtual CbcBranchObjType CbcCliqueBranchingObject::type() const [inline], [virtual]

Return the type (an integer identifier) of ${\tt this}$.

Implements CbcBranchingObject.

Definition at line 197 of file CbcClique.hpp.

7.13.3.6 virtual int CbcCliqueBranchingObject::compareOriginalObject (const CbcBranchingObject * brObj) const [virtual]

Compare the original object of this with the original object of brobj.

Assumes that there is an ordering of the original objects. This method should be invoked only if this and brObj are of the same type. Return negative/0/positive depending on whether this is smaller/same/larger than the argument.

Reimplemented from CbcBranchingObject.

7.13.3.7 virtual CbcRangeCompare CbcCliqueBranchingObject::compareBranchingObject (const CbcBranchingObject * brObj, const bool replacelfOverlap = false) [virtual]

Compare the this with brObj.

this and brobj must be of the same type and must have the same original object, but they may have different feasible regions. Return the appropriate CbcRangeCompare value (first argument being the sub/superset if that's the case). In case of overlap (and if replaceIfOverlap is true) replace the current branching object with one whose feasible region is the overlap.

Implements CbcBranchingObject.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcClique.hpp

7.14 CbcCompare Class Reference

#include <CbcCompare.hpp>

Public Member Functions

- CbcCompare ()
- virtual ∼CbcCompare ()
- bool operator() (CbcNode *x, CbcNode *y)
- bool compareNodes (CbcNode *x, CbcNode *y)
- bool alternateTest (CbcNode *x, CbcNode *y)

This is alternate test function.

CbcCompareBase * comparisonObject () const

return comparison object

Public Attributes

CbcCompareBase * test

7.14.1 Detailed Description

Definition at line 11 of file CbcCompare.hpp.

7.14.2 Constructor & Destructor Documentation

7.14.2.1 CbcCompare::CbcCompare() [inline]

Definition at line 15 of file CbcCompare.hpp.

7.14.2.2 virtual CbcCompare::~CbcCompare() [inline], [virtual]

Definition at line 19 of file CbcCompare.hpp.

7.14.3 Member Function Documentation

7.14.3.1 bool CbcCompare::operator() (CbcNode * x, CbcNode * y) [inline]

Definition at line 21 of file CbcCompare.hpp.

7.14.3.2 bool CbcCompare::compareNodes (CbcNode * x, CbcNode * y) [inline]

Definition at line 24 of file CbcCompare.hpp.

7.14.3.3 bool CbcCompare::alternateTest (CbcNode * x, CbcNode * y) [inline]

This is alternate test function.

Definition at line 28 of file CbcCompare.hpp.

7.14.3.4 CbcCompareBase* CbcCompare::comparisonObject() const [inline]

return comparison object

Definition at line 33 of file CbcCompare.hpp.

7.14.4 Member Data Documentation

7.14.4.1 CbcCompareBase* CbcCompare::test_

Definition at line 13 of file CbcCompare.hpp.


The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcCompare.hpp

7.15 CbcCompareBase Class Reference

#include <CbcCompareBase.hpp>

Inheritance diagram for CbcCompareBase:



Public Member Functions

- CbcCompareBase ()
- virtual bool newSolution (CbcModel *)

Reconsider behaviour after discovering a new solution.

virtual bool newSolution (CbcModel *, double, int)

Reconsider behaviour after discovering a new solution.

- virtual bool every1000Nodes (CbcModel *, int)
- virtual bool fullScan () const

Returns true if wants code to do scan with alternate criterion NOTE - this is temporarily disabled.

- virtual ∼CbcCompareBase ()
- virtual void generateCpp (FILE *)

Create C++ lines to get to current state.

- CbcCompareBase (const CbcCompareBase &rhs)
- CbcCompareBase & operator= (const CbcCompareBase &rhs)
- virtual CbcCompareBase * clone () const

Clone.

virtual bool test (CbcNode *, CbcNode *)

This is test function.

virtual bool alternateTest (CbcNode *x, CbcNode *y)

This is alternate test function.

- bool operator() (CbcNode *x, CbcNode *y)
- bool equalityTest (CbcNode *x, CbcNode *y) const

Further test if everything else equal.

• void sayThreaded ()

Say threaded.

Protected Attributes

- CbcCompareBase * test_
- bool threaded

7.15.1 Detailed Description

Definition at line 27 of file CbcCompareBase.hpp.

7.15.2 Constructor & Destructor Documentation

7.15.2.1 CbcCompareBase::CbcCompareBase() [inline]

Definition at line 30 of file CbcCompareBase.hpp.

7.15.2.2 virtual CbcCompareBase::~CbcCompareBase() [inline], [virtual]

Definition at line 75 of file CbcCompareBase.hpp.

7.15.2.3 CbcCompareBase::CbcCompareBase (const CbcCompareBase & rhs) [inline]

Definition at line 80 of file CbcCompareBase.hpp.

7.15.3 Member Function Documentation

7.15.3.1 virtual bool CbcCompareBase::newSolution (CbcModel *) [inline], [virtual]

Reconsider behaviour after discovering a new solution.

This allows any method to change its behaviour. It is called after each solution.

The method should return true if changes are made which will alter the evaluation criteria applied to a node. (So that in cases where the search tree is sorted, it can be properly rebuilt.)

Definition at line 45 of file CbcCompareBase.hpp.

7.15.3.2 virtual bool CbcCompareBase::newSolution (CbcModel *, double, int) [inline], [virtual]

Reconsider behaviour after discovering a new solution.

This allows any method to change its behaviour. It is called after each solution.

The method should return true if changes are made which will alter the evaluation criteria applied to a node. (So that in cases where the search tree is sorted, it can be properly rebuilt.)

Reimplemented in CbcCompareDefault.

Definition at line 57 of file CbcCompareBase.hpp.

7.15.3.3 virtual bool CbcCompareBase::every1000Nodes (CbcModel *, int) [inline], [virtual]

Reimplemented in CbcCompareDefault.

Definition at line 64 of file CbcCompareBase.hpp.

7.15.3.4 virtual bool CbcCompareBase::fullScan() const [inline], [virtual]

Returns true if wants code to do scan with alternate criterion NOTE - this is temporarily disabled.

Definition at line 71 of file CbcCompareBase.hpp.

7.15.3.5 virtual void CbcCompareBase::generateCpp (FILE *) [inline], [virtual]

Create C++ lines to get to current state.

Reimplemented in CbcCompareDefault, CbcCompareEstimate, CbcCompareObjective, and CbcCompareDepth.

Definition at line 77 of file CbcCompareBase.hpp.

7.15.3.6 CbcCompareBase& CbcCompareBase::operator=(const CbcCompareBase & rhs) [inline]

Definition at line 86 of file CbcCompareBase.hpp.

7.15.3.7 virtual CbcCompareBase* CbcCompareBase::clone() const [inline], [virtual]

Clone.

Reimplemented in CbcCompareDefault, CbcCompareEstimate, CbcCompareObjective, and CbcCompareDepth.

Definition at line 95 of file CbcCompareBase.hpp.

```
7.15.3.8 virtual bool CbcCompareBase::test ( CbcNode * , CbcNode * ) [inline], [virtual]
```

This is test function.

Reimplemented in CbcCompareDefault, CbcCompareObjective, CbcCompareDepth, and CbcCompareEstimate.

Definition at line 101 of file CbcCompareBase.hpp.

```
7.15.3.9 virtual bool CbcCompareBase::alternateTest ( CbcNode * x, CbcNode * y ) [inline], [virtual]
```

This is alternate test function.

Definition at line 106 of file CbcCompareBase.hpp.

```
7.15.3.10 bool CbcCompareBase::operator() ( CbcNode * x, CbcNode * y ) [inline]
```

Definition at line 110 of file CbcCompareBase.hpp.

```
7.15.3.11 bool CbcCompareBase::equalityTest ( CbcNode * x, CbcNode * y ) const [inline]
```

Further test if everything else equal.

Definition at line 114 of file CbcCompareBase.hpp.

```
7.15.3.12 void CbcCompareBase::sayThreaded() [inline]
```

Say threaded.

Definition at line 132 of file CbcCompareBase.hpp.

7.15.4 Member Data Documentation

```
7.15.4.1 CbcCompareBase* CbcCompareBase::test_ [protected]
```

Definition at line 136 of file CbcCompareBase.hpp.

```
7.15.4.2 bool CbcCompareBase::threaded_ [protected]
```

Definition at line 138 of file CbcCompareBase.hpp.


The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcCompareBase.hpp

7.16 CbcCompareDefault Class Reference

```
#include <CbcCompareDefault.hpp>
```

Inheritance diagram for CbcCompareDefault:



Public Member Functions

· CbcCompareDefault ()

Default Constructor.

• CbcCompareDefault (double weight)

Constructor with weight.

CbcCompareDefault (const CbcCompareDefault &rhs)

Copy constructor.

CbcCompareDefault & operator= (const CbcCompareDefault &rhs)

Assignment operator.

virtual CbcCompareBase * clone () const

Clone.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

- ∼CbcCompareDefault ()
- virtual bool test (CbcNode *x, CbcNode *y)

This is test function.

 virtual bool newSolution (CbcModel *model, double objectiveAtContinuous, int numberInfeasibilitiesAt-Continuous)

This allows method to change behavior as it is called after each solution.

virtual bool every1000Nodes (CbcModel *model, int numberNodes)

This allows method to change behavior Return true if want tree re-sorted.

- double getWeight () const
- void setWeight (double weight)
- double getCutoff () const

Cutoff.

- void setCutoff (double cutoff)
- double getBestPossible () const

Best possible solution.

- void setBestPossible (double bestPossible)
- void setBreadthDepth (int value)

Depth above which want to explore first.

void startDive (CbcModel *model)

Start dive.

· void cleanDive ()

Clean up diving (i.e. switch off or prepare)

Protected Attributes

double weight

Weight for each infeasibility.

double saveWeight

Weight for each infeasibility - computed from solution.

double cutoff

Cutoff.

double bestPossible

Best possible solution.

int numberSolutions

Number of solutions.

int treeSize

Tree size (at last check)

· int breadthDepth_

Depth above which want to explore first.

• int startNodeNumber_

Chosen node from estimated (-1 is off)

int afterNodeNumber

Node number when dive started.

bool setupForDiving_

Indicates doing setup for diving.

7.16.1 Detailed Description

Definition at line 31 of file CbcCompareDefault.hpp.

- 7.16.2 Constructor & Destructor Documentation
- 7.16.2.1 CbcCompareDefault::CbcCompareDefault ()

Default Constructor.

7.16.2.2 CbcCompareDefault::CbcCompareDefault (double weight)

Constructor with weight.

7.16.2.3 CbcCompareDefault::CbcCompareDefault (const CbcCompareDefault & rhs)

Copy constructor.

- 7.16.2.4 CbcCompareDefault::~CbcCompareDefault ()
- 7.16.3 Member Function Documentation
- 7.16.3.1 CbcCompareDefault& CbcCompareDefault::operator= (const CbcCompareDefault & rhs)

Assignment operator.

```
7.16.3.2 virtual CbcCompareBase* CbcCompareDefault::clone( )const [virtual]
Clone.
Reimplemented from CbcCompareBase.
7.16.3.3 virtual void CbcCompareDefault::generateCpp (FILE * fp ) [virtual]
Create C++ lines to get to current state.
Reimplemented from CbcCompareBase.
7.16.3.4 virtual bool CbcCompareDefault::test ( CbcNode * , CbcNode * ) [virtual]
This is test function.
Reimplemented from CbcCompareBase.
7.16.3.5 virtual bool CbcCompareDefault::newSolution ( CbcModel * model, double objectiveAtContinuous, int
        numberInfeasibilitiesAtContinuous ) [virtual]
This allows method to change behavior as it is called after each solution.
Reimplemented from CbcCompareBase.
7.16.3.6 virtual bool CbcCompareDefault::every1000Nodes ( CbcModel * model, int numberNodes ) [virtual]
This allows method to change behavior Return true if want tree re-sorted.
Reimplemented from CbcCompareBase.
7.16.3.7 double CbcCompareDefault::getWeight() const [inline]
Definition at line 68 of file CbcCompareDefault.hpp.
7.16.3.8 void CbcCompareDefault::setWeight ( double weight ) [inline]
Definition at line 71 of file CbcCompareDefault.hpp.
7.16.3.9 double CbcCompareDefault::getCutoff() const [inline]
Cutoff.
Definition at line 75 of file CbcCompareDefault.hpp.
7.16.3.10 void CbcCompareDefault::setCutoff ( double cutoff ) [inline]
Definition at line 78 of file CbcCompareDefault.hpp.
7.16.3.11 double CbcCompareDefault::getBestPossible() const [inline]
Best possible solution.
Definition at line 82 of file CbcCompareDefault.hpp.
7.16.3.12 void CbcCompareDefault::setBestPossible ( double bestPossible ) [inline]
Definition at line 85 of file CbcCompareDefault.hpp.
```

```
7.16.3.13 void CbcCompareDefault::setBreadthDepth (int value ) [inline]
Depth above which want to explore first.
Definition at line 89 of file CbcCompareDefault.hpp.
7.16.3.14 void CbcCompareDefault::startDive ( CbcModel * model )
Start dive.
7.16.3.15 void CbcCompareDefault::cleanDive ( )
Clean up diving (i.e. switch off or prepare)
7.16.4 Member Data Documentation
7.16.4.1 double CbcCompareDefault::weight_ [protected]
Weight for each infeasibility.
Definition at line 98 of file CbcCompareDefault.hpp.
7.16.4.2 double CbcCompareDefault::saveWeight_ [protected]
Weight for each infeasibility - computed from solution.
Definition at line 100 of file CbcCompareDefault.hpp.
7.16.4.3 double CbcCompareDefault::cutoff_ [protected]
Cutoff.
Definition at line 102 of file CbcCompareDefault.hpp.
7.16.4.4 double CbcCompareDefault::bestPossible_ [protected]
Best possible solution.
Definition at line 104 of file CbcCompareDefault.hpp.
7.16.4.5 int CbcCompareDefault::numberSolutions_ [protected]
Number of solutions.
Definition at line 106 of file CbcCompareDefault.hpp.
7.16.4.6 int CbcCompareDefault::treeSize_ [protected]
Tree size (at last check)
Definition at line 108 of file CbcCompareDefault.hpp.
7.16.4.7 int CbcCompareDefault::breadthDepth_ [protected]
Depth above which want to explore first.
Definition at line 110 of file CbcCompareDefault.hpp.
```

7.16.4.8 int CbcCompareDefault::startNodeNumber_ [protected]

Chosen node from estimated (-1 is off)

Definition at line 112 of file CbcCompareDefault.hpp.

7.16.4.9 int CbcCompareDefault::afterNodeNumber_ [protected]

Node number when dive started.

Definition at line 114 of file CbcCompareDefault.hpp.

7.16.4.10 bool CbcCompareDefault::setupForDiving_ [protected]

Indicates doing setup for diving.

Definition at line 116 of file CbcCompareDefault.hpp.


The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcCompareDefault.hpp

7.17 CbcCompareDepth Class Reference

#include <CbcCompareDepth.hpp>

Inheritance diagram for CbcCompareDepth:



Public Member Functions

- CbcCompareDepth ()
- ∼CbcCompareDepth ()
- CbcCompareDepth (const CbcCompareDepth &rhs)
- CbcCompareDepth & operator= (const CbcCompareDepth &rhs)
- virtual CbcCompareBase * clone () const

Clone.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual bool test (CbcNode *x, CbcNode *y)

This is test function.

Additional Inherited Members

7.17.1 Detailed Description

Definition at line 25 of file CbcCompareDepth.hpp.

```
7.17.2 Constructor & Destructor Documentation
```

- 7.17.2.1 CbcCompareDepth::CbcCompareDepth ()
- 7.17.2.2 CbcCompareDepth:: ~ CbcCompareDepth ()
- 7.17.2.3 CbcCompareDepth::CbcCompareDepth (const CbcCompareDepth & rhs)
- 7.17.3 Member Function Documentation
- 7.17.3.1 CbcCompareDepth& CbcCompareDepth::operator= (const CbcCompareDepth & rhs)
- 7.17.3.2 virtual CbcCompareBase* CbcCompareDepth::clone() const [virtual]

Clone.

Reimplemented from CbcCompareBase.

7.17.3.3 virtual void CbcCompareDepth::generateCpp (FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcCompareBase.

7.17.3.4 virtual bool CbcCompareDepth::test (CbcNode * , CbcNode *) [virtual]

This is test function.

Reimplemented from CbcCompareBase.


The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcCompareDepth.hpp

7.18 CbcCompareEstimate Class Reference

#include <CbcCompareEstimate.hpp>

Inheritance diagram for CbcCompareEstimate:



Public Member Functions

- CbcCompareEstimate ()
- ∼CbcCompareEstimate ()
- CbcCompareEstimate (const CbcCompareEstimate &rhs)
- CbcCompareEstimate & operator= (const CbcCompareEstimate &rhs)
- virtual CbcCompareBase * clone () const

Clone.

virtual void generateCpp (FILE *fp)

```
    Create C++ lines to get to current state.
    virtual bool test (CbcNode *x, CbcNode *y)
    This is test function.
```

Additional Inherited Members

7.18.1 Detailed Description

Definition at line 27 of file CbcCompareEstimate.hpp.

```
7.18.2 Constructor & Destructor Documentation
```

```
7.18.2.1 CbcCompareEstimate::CbcCompareEstimate ( )
```

```
7.18.2.2 CbcCompareEstimate::~CbcCompareEstimate()
```

7.18.2.3 CbcCompareEstimate::CbcCompareEstimate (const CbcCompareEstimate & rhs)

```
7.18.3 Member Function Documentation
```

7.18.3.1 CbcCompareEstimate & CbcCompareEstimate & rhs)

```
7.18.3.2 virtual CbcCompareBase* CbcCompareEstimate::clone( )const [virtual]
```

Clone.

Reimplemented from CbcCompareBase.

```
7.18.3.3 virtual void CbcCompareEstimate::generateCpp (FILE * fp ) [virtual]
```

Create C++ lines to get to current state.

Reimplemented from CbcCompareBase.

```
7.18.3.4 virtual bool CbcCompareEstimate::test ( CbcNode * , CbcNode * ) [virtual]
```

This is test function.

Reimplemented from CbcCompareBase.


The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcCompareEstimate.hpp

7.19 CbcCompareObjective Class Reference

```
#include <CbcCompareObjective.hpp>
```

Inheritance diagram for CbcCompareObjective:



Public Member Functions

```
    CbcCompareObjective ()
```

- virtual ∼CbcCompareObjective ()
- CbcCompareObjective (const CbcCompareObjective &rhs)
- CbcCompareObjective & operator= (const CbcCompareObjective &rhs)
- virtual CbcCompareBase * clone () const

Clone.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual bool test (CbcNode *x, CbcNode *y)

This is test function.

Additional Inherited Members

7.19.1 Detailed Description

Definition at line 26 of file CbcCompareObjective.hpp.

```
7.19.2 Constructor & Destructor Documentation
```

```
7.19.2.1 CbcCompareObjective::CbcCompareObjective ( )
```

```
7.19.2.2 virtual CbcCompareObjective::~CbcCompareObjective() [virtual]
```

 $7.19.2.3 \quad \textbf{CbcCompareObjective::} \textbf{CbcCompareObjective (const CbcCompareObjective \& \textit{rhs} \)}$

7.19.3 Member Function Documentation

7.19.3.1 CbcCompareObjective& CbcCompareObjective::operator= (const CbcCompareObjective & rhs)

7.19.3.2 virtual CbcCompareBase* CbcCompareObjective::clone()const [virtual]

Clone.

Reimplemented from CbcCompareBase.

7.19.3.3 virtual void CbcCompareObjective::generateCpp (FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcCompareBase.

7.19.3.4 virtual bool CbcCompareObjective::test (CbcNode * , CbcNode *) [virtual]

This is test function.

Reimplemented from CbcCompareBase.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcCompareObjective.hpp

7.20 CbcConsequence Class Reference

Abstract base class for consequent bounds.

#include <CbcConsequence.hpp>

Inheritance diagram for CbcConsequence:



Public Member Functions

- CbcConsequence ()
- CbcConsequence (const CbcConsequence &rhs)
- CbcConsequence & operator= (const CbcConsequence &rhs)
- virtual CbcConsequence * clone () const =0

Clone

virtual ∼CbcConsequence ()

Destructor.

virtual void applyToSolver (OsiSolverInterface *solver, int state) const =0

Apply to an LP solver.

7.20.1 Detailed Description

Abstract base class for consequent bounds.

When a variable is branched on it normally interacts with other variables by means of equations. There are cases where we want to step outside LP and do something more directly e.g. fix bounds. This class is for that.

At present it need not be virtual as only instance is CbcFixVariable, but ...

Definition at line 22 of file CbcConsequence.hpp.

- 7.20.2 Constructor & Destructor Documentation
- 7.20.2.1 CbcConsequence::CbcConsequence()
- 7.20.2.2 CbcConsequence::CbcConsequence (const CbcConsequence & rhs)
- **7.20.2.3** virtual CbcConsequence:: \sim CbcConsequence() [virtual]

Destructor.

- 7.20.3 Member Function Documentation
- 7.20.3.1 CbcConsequence& CbcConsequence::operator= (const CbcConsequence & rhs)

7.20.3.2 virtual CbcConsequence* CbcConsequence::clone() const [pure virtual]

Clone.

Implemented in CbcFixVariable.

7.20.3.3 virtual void CbcConsequence::applyToSolver(OsiSolverInterface * solver, int state) const [pure virtual]

Apply to an LP solver.

Action depends on state

Implemented in CbcFixVariable.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcConsequence.hpp

7.21 CbcCountRowCut Class Reference

OsiRowCut augmented with bookkeeping.

#include <CbcCountRowCut.hpp>

Inheritance diagram for CbcCountRowCut:



Public Member Functions

void increment (int change=1)

Increment the number of references.

• int decrement (int change=1)

Decrement the number of references and return the number left.

void setInfo (CbcNodeInfo *, int whichOne)

Set the information associating this cut with a node.

• int numberPointingToThis ()

Number of other CbcNodeInfo objects pointing to this row cut.

• int whichCutGenerator () const

Which generator for cuts - as user order.

• bool canDropCut (const OsiSolverInterface *solver, int row) const

Returns true if can drop cut if slack basic.

Constructors & destructors

• CbcCountRowCut ()

Default Constructor.

• CbcCountRowCut (const OsiRowCut &)

'Copy' constructor using an OsiRowCut

 CbcCountRowCut (const OsiRowCut &, CbcNodeInfo *, int whichOne, int whichGenerator=-1, int number-PointingToThis=0)

'Copy' constructor using an OsiRowCut and an CbcNodeInfo

virtual ∼CbcCountRowCut ()

Destructor.

7.21.1 Detailed Description

OsiRowCut augmented with bookkeeping.

CbcCountRowCut is an OsiRowCut object augmented with bookkeeping information: a reference count and information that specifies the the generator that created the cut and the node to which it's associated.

The general principles for handling the reference count are as follows:

- Once it's determined how the node will branch, increment the reference count under the assumption that all children will use all cuts currently tight at the node and will survive to be placed in the search tree.
- As this assumption is proven incorrect (a cut becomes loose, or a child is fathomed), decrement the reference count accordingly.

When all possible uses of a cut have been demonstrated to be unnecessary, the reference count (#numberPointingTo-This_) will fall to zero. The CbcCountRowCut object (and its included OsiRowCut object) are then deleted.

Definition at line 35 of file CbcCountRowCut.hpp.

```
7.21.2 Constructor & Destructor Documentation
7.21.2.1 CbcCountRowCut::CbcCountRowCut ( )
Default Constructor.
7.21.2.2 CbcCountRowCut::CbcCountRowCut ( const OsiRowCut & )
'Copy' constructor using an OsiRowCut
7.21.2.3 CbcCountRowCut::CbcCountRowCut ( const OsiRowCut & , CbcNodeInfo * , int whichOne, int whichGenerator = -1, int numberPointingToThis = 0 )
'Copy' constructor using an OsiRowCut and an CbcNodeInfo
```

7.21.2.4 virtual CbcCountRowCut::~CbcCountRowCut() [virtual]

Destructor.

Note

The destructor will reach out (via #owner_) and NULL the reference to the cut in the owner's cuts_ list.

7.21.3 Member Function Documentation

7.21.3.1 void CbcCountRowCut::increment (int change = 1)

Increment the number of references.

7.21.3.2 int CbcCountRowCut::decrement (int change = 1)

Decrement the number of references and return the number left.

7.21.3.3 void CbcCountRowCut::setInfo (CbcNodeInfo * , int whichOne)

Set the information associating this cut with a node.

An CbcNodeInfo object and an index in the cut set of the node. For locally valid cuts, the node will be the search tree node where the cut was generated. For globally valid cuts, it's the node where the cut was activated.

7.21.3.4 int CbcCountRowCut::numberPointingToThis() [inline]

Number of other CbcNodeInfo objects pointing to this row cut.

Definition at line 77 of file CbcCountRowCut.hpp.

7.21.3.5 int CbcCountRowCut::whichCutGenerator() const [inline]

Which generator for cuts - as user order.

Definition at line 82 of file CbcCountRowCut.hpp.

7.21.3.6 bool CbcCountRowCut::canDropCut (const OsiSolverInterface * solver, int row) const

Returns true if can drop cut if slack basic.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcCountRowCut.hpp

7.22 CbcCutBranchingObject Class Reference

Cut branching object.

#include <CbcBranchCut.hpp>

Inheritance diagram for CbcCutBranchingObject:



Public Member Functions

• CbcCutBranchingObject ()

Default constructor.

CbcCutBranchingObject (CbcModel *model, OsiRowCut &down, OsiRowCut &up, bool canFix)

Create a cut branching object.

CbcCutBranchingObject (const CbcCutBranchingObject &)

Copy constructor.

• CbcCutBranchingObject & operator= (const CbcCutBranchingObject &rhs)

Assignment operator.

virtual CbcBranchingObject * clone () const

Clone

virtual ∼CbcCutBranchingObject ()

Destructor.

virtual double branch ()

Sets the bounds for variables or adds a cut depending on the current arm of the branch and advances the object state to the next arm.

· virtual void print ()

Print something about branch - only if log level high.

· virtual bool boundBranch () const

Return true if branch should fix variables.

virtual CbcBranchObjType type () const

Return the type (an integer identifier) of this.

virtual int compareOriginalObject (const CbcBranchingObject *brObj) const

Compare the original object of this with the original object of brobj.

 virtual CbcRangeCompare compareBranchingObject (const CbcBranchingObject *brObj, const bool replaceIf-Overlap=false)

Compare the this with brobj.

Protected Attributes

OsiRowCut down_

Cut for the down arm (way_ = -1)

OsiRowCut up_

Cut for the up arm (way_ = 1)

· bool canFix_

True if one way can fix variables.

7.22.1 Detailed Description

Cut branching object.

This object can specify a two-way branch in terms of two cuts

Definition at line 108 of file CbcBranchCut.hpp.

7.22.2 Constructor & Destructor Documentation

7.22.2.1 CbcCutBranchingObject::CbcCutBranchingObject ()

Default constructor.

7.22.2.2 CbcCutBranchingObject::CbcCutBranchingObject (CbcModel * model, OsiRowCut & down, OsiRowCut & up, bool canFix)

Create a cut branching object.

Cut down will applied on way=-1, up on way==1 Assumed down will be first so way set to -1

7.22.2.3 CbcCutBranchingObject::CbcCutBranchingObject (const CbcCutBranchingObject &)

Copy constructor.

7.22.2.4 virtual CbcCutBranchingObject::~CbcCutBranchingObject() [virtual]

Destructor.

7.22.3 Member Function Documentation

7.22.3.1 CbcCutBranchingObject & CbcCutBranchingObject :: operator= (const CbcCutBranchingObject & rhs)

Assignment operator.

7.22.3.2 virtual CbcBranchingObject* CbcCutBranchingObject::clone() const [virtual]

Clone.

Implements CbcBranchingObject.

7.22.3.3 virtual double CbcCutBranchingObject::branch() [virtual]

Sets the bounds for variables or adds a cut depending on the current arm of the branch and advances the object state to the next arm.

Returns change in guessed objective on next branch

Implements CbcBranchingObject.

7.22.3.4 virtual void CbcCutBranchingObject::print() [virtual]

Print something about branch - only if log level high.

7.22.3.5 virtual bool CbcCutBranchingObject::boundBranch () const [virtual]

Return true if branch should fix variables.

7.22.3.6 virtual CbcBranchObjType CbcCutBranchingObject::type()const [inline], [virtual]

Return the type (an integer identifier) of this.

Implements CbcBranchingObject.

Definition at line 151 of file CbcBranchCut.hpp.

7.22.3.7 virtual int CbcCutBranchingObject::compareOriginalObject (const CbcBranchingObject * brObj) const [virtual]

Compare the original object of this with the original object of brObj.

Assumes that there is an ordering of the original objects. This method should be invoked only if this and brObj are of the same type. Return negative/0/positive depending on whether this is smaller/same/larger than the argument.

Reimplemented from CbcBranchingObject.

7.22.3.8 virtual CbcRangeCompare CbcCutBranchingObject::compareBranchingObject (const CbcBranchingObject * brObj, const bool replacelfOverlap = false) [virtual]

Compare the this with brObj.

this and brObj must be os the same type and must have the same original object, but they may have different feasible regions. Return the appropriate CbcRangeCompare value (first argument being the sub/superset if that's the case). In case of overlap (and if replaceIfOverlap is true) replace the current branching object with one whose feasible region is the overlap.

Implements CbcBranchingObject.

7.22.4 Member Data Documentation

7.22.4.1 OsiRowCut CbcCutBranchingObject::down_ [protected]

Cut for the down arm (way = -1)

Definition at line 177 of file CbcBranchCut.hpp.

7.22.4.2 OsiRowCut CbcCutBranchingObject::up [protected]

Cut for the up arm (way_ = 1)

Definition at line 179 of file CbcBranchCut.hpp.

7.22.4.3 bool CbcCutBranchingObject::canFix_ [protected]

True if one way can fix variables.

Definition at line 181 of file CbcBranchCut.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcBranchCut.hpp

7.23 CbcCutGenerator Class Reference

Interface between Cbc and Cut Generation Library.

```
#include <CbcCutGenerator.hpp>
```

Public Member Functions

Generate Cuts

• bool generateCuts (OsiCuts &cs, int fullScan, OsiSolverInterface *solver, CbcNode *node)

Generate cuts for the client model.

Constructors and destructors

• CbcCutGenerator ()

Default constructor.

• CbcCutGenerator (CbcModel *model, CglCutGenerator *generator, int howOften=1, const char *name=NU-LL, bool normal=true, bool atSolution=false, bool infeasible=false, int howOftenInsub=-100, int whatDepth=-1, int whatDepthInSub=-1, int switchOffIfLessThan=0)

Normal constructor.

CbcCutGenerator (const CbcCutGenerator &)

Copy constructor.

CbcCutGenerator & operator= (const CbcCutGenerator &rhs)

Assignment operator.

∼CbcCutGenerator ()

Destructor.

Gets and sets

void refreshModel (CbcModel *model)

Set the client model.

const char * cutGeneratorName () const

return name of generator

void generateTuning (FILE *fp)

Create C++ lines to show how to tune.

void setHowOften (int value)

Set the cut generation interval.

• int howOften () const

Get the cut generation interval.

• int howOftenInSub () const

Get the cut generation interval.in sub tree.

• int inaccuracy () const

Get level of cut inaccuracy (0 means exact e.g. cliques)

void setInaccuracy (int level)

Set level of cut inaccuracy (0 means exact e.g. cliques)

void setWhatDepth (int value)

Set the cut generation depth.

void setWhatDepthInSub (int value)

Set the cut generation depth in sub tree.

int whatDepth () const

Get the cut generation depth criterion.

int whatDepthInSub () const

Get the cut generation depth criterion.in sub tree.

void setMaximumTries (int value)

Set maximum number of times to enter.

• int maximumTries () const

Get maximum number of times to enter.

· int switches () const

Get switches (for debug)

· bool normal () const

Get whether the cut generator should be called in the normal place.

void setNormal (bool value)

Set whether the cut generator should be called in the normal place.

bool atSolution () const

Get whether the cut generator should be called when a solution is found.

void setAtSolution (bool value)

Set whether the cut generator should be called when a solution is found.

• bool whenInfeasible () const

Get whether the cut generator should be called when the subproblem is found to be infeasible.

void setWhenInfeasible (bool value)

Set whether the cut generator should be called when the subproblem is found to be infeasible.

· bool timing () const

Get whether the cut generator is being timed.

void setTiming (bool value)

Set whether the cut generator is being timed.

double timeInCutGenerator () const

Return time taken in cut generator.

- void incrementTimeInCutGenerator (double value)
- CglCutGenerator * generator () const

Get the CglCutGenerator corresponding to this CbcCutGenerator.

int numberTimesEntered () const

Number times cut generator entered.

- void setNumberTimesEntered (int value)
- void incrementNumberTimesEntered (int value=1)
- int numberCutsInTotal () const

Total number of cuts added.

- void setNumberCutsInTotal (int value)
- void incrementNumberCutsInTotal (int value=1)
- int numberElementsInTotal () const

Total number of elements added.

- void setNumberElementsInTotal (int value)
- void incrementNumberElementsInTotal (int value=1)
- int numberColumnCuts () const

Total number of column cuts.

- void setNumberColumnCuts (int value)
- void incrementNumberColumnCuts (int value=1)
- int numberCutsActive () const

Total number of cuts active after (at end of n cut passes at each node)

- void setNumberCutsActive (int value)
- void incrementNumberCutsActive (int value=1)
- void setSwitchOffIfLessThan (int value)
- int switchOffIfLessThan () const
- bool needsOptimalBasis () const

Say if optimal basis needed.

void setNeedsOptimalBasis (bool yesNo)

Set if optimal basis needed.

• bool mustCallAgain () const

Whether generator MUST be called again if any cuts (i.e. ignore break from loop)

void setMustCallAgain (bool yesNo)

Set whether generator MUST be called again if any cuts (i.e. ignore break from loop)

• bool switchedOff () const

Whether generator switched off for moment.

void setSwitchedOff (bool yesNo)

Set whether generator switched off for moment.

• bool ineffectualCuts () const

Whether last round of cuts did little.

void setIneffectualCuts (bool yesNo)

Set whether last round of cuts did little.

• bool whetherToUse () const

Whether to use if any cuts generated.

void setWhetherToUse (bool yesNo)

Set whether to use if any cuts generated.

• bool whetherInMustCallAgainMode () const

Whether in must call again mode (or after others)

void setWhetherInMustCallAgainMode (bool yesNo)

Set whether in must call again mode (or after others)

• bool whetherCallAtEnd () const

Whether to call at end.

void setWhetherCallAtEnd (bool yesNo)

Set whether to call at end.

• int numberCutsAtRoot () const

Number of cuts generated at root.

- void setNumberCutsAtRoot (int value)
- · int numberActiveCutsAtRoot () const

Number of cuts active at root.

- void setNumberActiveCutsAtRoot (int value)
- int numberShortCutsAtRoot () const

Number of short cuts at root.

- void setNumberShortCutsAtRoot (int value)
- void setModel (CbcModel *model)

Set model.

bool globalCutsAtRoot () const

Whether global cuts at root.

void setGlobalCutsAtRoot (bool yesNo)

Set whether global cuts at root.

bool globalCuts () const

Whether global cuts.

void setGlobalCuts (bool yesNo)

Set whether global cuts.

void addStatistics (const CbcCutGenerator *other)

Add in statistics from other.

· void scaleBackStatistics (int factor)

Scale back statistics by factor.

7.23.1 Detailed Description

Interface between Cbc and Cut Generation Library.

CbcCutGenerator is intended to provide an intelligent interface between Cbc and the cutting plane algorithms in the CGL. A CbcCutGenerator is bound to a CglCutGenerator and to an CbcModel. It contains parameters which control when and how the generateCuts method of the CglCutGenerator will be called.

The builtin decision criteria available to use when deciding whether to generate cuts are limited: every X nodes, when a solution is found, and when a subproblem is found to be infeasible. The idea is that the class will grow more intelligent with time.

Todo Add a pointer to function member which will allow a client to install their own decision algorithm to decide whether or not to call the CGL generateCuts method. Create a default decision method that looks at the builtin criteria.

Todo It strikes me as not good that generateCuts contains code specific to individual CGL algorithms. Another set of pointer to function members, so that the client can specify the cut generation method as well as pre- and post-generation methods? Taken a bit further, should this class contain a bunch of pointer to function members, one for each of the places where the cut generator might be referenced? Initialization, root node, search tree node, discovery of solution, and termination all come to mind. Initialization and termination would also be useful for instrumenting cbc.

Definition at line 49 of file CbcCutGenerator.hpp.

7.23.2 Constructor & Destructor Documentation

7.23.2.1 CbcCutGenerator::CbcCutGenerator()

Default constructor.

7.23.2.2 CbcCutGenerator::CbcCutGenerator (CbcModel * model, CglCutGenerator * generator, int howOften = 1, const char * name = NULL, bool normal = true, bool atSolution = false, bool infeasible = false, int howOftenInsub = -100, int whatDepth = -1, int whatDepthInSub = -1, int switchOfflfLessThan = 0)

Normal constructor.

7.23.2.3 CbcCutGenerator::CbcCutGenerator (const CbcCutGenerator &)

Copy constructor.

7.23.2.4 CbcCutGenerator::~CbcCutGenerator()

Destructor.

7.23.3 Member Function Documentation

7.23.3.1 bool CbcCutGenerator::generateCuts (OsiCuts & cs, int fullScan, OsiSolverInterface * solver, CbcNode * node)

Generate cuts for the client model.

Evaluate the state of the client model and decide whether to generate cuts. The generated cuts are inserted into and returned in the collection of cuts cs.

If fullScan is !=0, the generator is obliged to call the CGL generateCuts routine. Otherwise, it is free to make a local decision. Negative fullScan says things like at integer solution The current implementation uses whenCut-Generator_to decide.

The routine returns true if reoptimisation is needed (because the state of the solver interface has been modified).

If node then can find out depth

7.23.3.2 CbcCutGenerator& CbcCutGenerator::operator= (const CbcCutGenerator & rhs)

Assignment operator.

7.23.3.3 void CbcCutGenerator::refreshModel (CbcModel * model)

Set the client model.

In addition to setting the client model, refreshModel also calls the refreshSolver method of the CglCutGenerator object.

7.23.3.4 const char* CbcCutGenerator::cutGeneratorName() const [inline]

return name of generator

Definition at line 108 of file CbcCutGenerator.hpp.

7.23.3.5 void CbcCutGenerator::generateTuning (FILE * fp)

Create C++ lines to show how to tune.

7.23.3.6 void CbcCutGenerator::setHowOften (int value)

Set the cut generation interval.

Set the number of nodes evaluated between calls to the Cgl object's generateCuts routine.

If value is positive, cuts will always be generated at the specified interval. If value is negative, cuts will initially be generated at the specified interval, but Cbc may adjust the value depending on the success of cuts produced by this generator.

A value of -100 disables the generator, while a value of -99 means just at root.

```
7.23.3.7 int CbcCutGenerator::howOften()const [inline]
Get the cut generation interval.
Definition at line 131 of file CbcCutGenerator.hpp.
7.23.3.8 int CbcCutGenerator::howOftenInSub()const [inline]
Get the cut generation interval.in sub tree.
Definition at line 135 of file CbcCutGenerator.hpp.
7.23.3.9 int CbcCutGenerator::inaccuracy() const [inline]
Get level of cut inaccuracy (0 means exact e.g. cliques)
Definition at line 139 of file CbcCutGenerator.hpp.
7.23.3.10 void CbcCutGenerator::setInaccuracy (int level) [inline]
Set level of cut inaccuracy (0 means exact e.g. cliques)
Definition at line 143 of file CbcCutGenerator.hpp.
7.23.3.11 void CbcCutGenerator::setWhatDepth (int value)
Set the cut generation depth.
Set the depth criterion for calls to the Cgl object's generateCuts routine. Only active if > 0.
If whenCutGenerator is positive and this is positive then this overrides. If whenCutGenerator is -1 then this is used as
criterion if any cuts were generated at root node. If whenCutGenerator is anything else this is ignored.
7.23.3.12 void CbcCutGenerator::setWhatDepthInSub (int value)
Set the cut generation depth in sub tree.
7.23.3.13 int CbcCutGenerator::whatDepth()const [inline]
Get the cut generation depth criterion.
Definition at line 161 of file CbcCutGenerator.hpp.
7.23.3.14 int CbcCutGenerator::whatDepthInSub() const [inline]
Get the cut generation depth criterion.in sub tree.
Definition at line 165 of file CbcCutGenerator.hpp.
7.23.3.15 void CbcCutGenerator::setMaximumTries (int value) [inline]
Set maximum number of times to enter.
Definition at line 169 of file CbcCutGenerator.hpp.
7.23.3.16 int CbcCutGenerator::maximumTries ( ) const [inline]
```

Get maximum number of times to enter.

Definition at line 172 of file CbcCutGenerator.hpp.

7.23.3.17 int CbcCutGenerator::switches () const [inline]

Get switches (for debug)

Definition at line 176 of file CbcCutGenerator.hpp.

7.23.3.18 bool CbcCutGenerator::normal() const [inline]

Get whether the cut generator should be called in the normal place.

Definition at line 180 of file CbcCutGenerator.hpp.

7.23.3.19 void CbcCutGenerator::setNormal(bool value) [inline]

Set whether the cut generator should be called in the normal place.

Definition at line 184 of file CbcCutGenerator.hpp.

7.23.3.20 bool CbcCutGenerator::atSolution () const [inline]

Get whether the cut generator should be called when a solution is found.

Definition at line 189 of file CbcCutGenerator.hpp.

7.23.3.21 void CbcCutGenerator::setAtSolution (bool value) [inline]

Set whether the cut generator should be called when a solution is found.

Definition at line 193 of file CbcCutGenerator.hpp.

7.23.3.22 bool CbcCutGenerator::whenInfeasible() const [inline]

Get whether the cut generator should be called when the subproblem is found to be infeasible.

Definition at line 200 of file CbcCutGenerator.hpp.

7.23.3.23 void CbcCutGenerator::setWhenInfeasible (bool value) [inline]

Set whether the cut generator should be called when the subproblem is found to be infeasible.

Definition at line 206 of file CbcCutGenerator.hpp.

7.23.3.24 bool CbcCutGenerator::timing () const [inline]

Get whether the cut generator is being timed.

Definition at line 211 of file CbcCutGenerator.hpp.

7.23.3.25 void CbcCutGenerator::setTiming (bool value) [inline]

Set whether the cut generator is being timed.

Definition at line 215 of file CbcCutGenerator.hpp.

7.23.3.26 double CbcCutGenerator::timeInCutGenerator() const [inline]

Return time taken in cut generator.

Definition at line 221 of file CbcCutGenerator.hpp.

```
7.23.3.27 void CbcCutGenerator::incrementTimeInCutGenerator ( double value ) [inline]
Definition at line 224 of file CbcCutGenerator.hpp.
7.23.3.28 CglCutGenerator* CbcCutGenerator::generator() const [inline]
Get the CglCutGenerator corresponding to this CbcCutGenerator.
Definition at line 228 of file CbcCutGenerator.hpp.
7.23.3.29 int CbcCutGenerator::numberTimesEntered ( ) const [inline]
Number times cut generator entered.
Definition at line 232 of file CbcCutGenerator.hpp.
7.23.3.30 void CbcCutGenerator::setNumberTimesEntered (int value) [inline]
Definition at line 235 of file CbcCutGenerator.hpp.
7.23.3.31 void CbcCutGenerator::incrementNumberTimesEntered ( int value = 1 ) [inline]
Definition at line 238 of file CbcCutGenerator.hpp.
7.23.3.32 int CbcCutGenerator::numberCutsInTotal() const [inline]
Total number of cuts added.
Definition at line 242 of file CbcCutGenerator.hpp.
7.23.3.33 void CbcCutGenerator::setNumberCutsInTotal (int value) [inline]
Definition at line 245 of file CbcCutGenerator.hpp.
7.23.3.34 void CbcCutGenerator::incrementNumberCutsInTotal (int value = 1) [inline]
Definition at line 248 of file CbcCutGenerator.hpp.
7.23.3.35 int CbcCutGenerator::numberElementsInTotal() const [inline]
Total number of elements added.
Definition at line 252 of file CbcCutGenerator.hpp.
7.23.3.36 void CbcCutGenerator::setNumberElementsInTotal (int value) [inline]
Definition at line 255 of file CbcCutGenerator.hpp.
7.23.3.37 void CbcCutGenerator::incrementNumberElementsInTotal (int value = 1) [inline]
Definition at line 258 of file CbcCutGenerator.hpp.
7.23.3.38 int CbcCutGenerator::numberColumnCuts ( ) const [inline]
Total number of column cuts.
Definition at line 262 of file CbcCutGenerator.hpp.
```

```
7.23.3.39 void CbcCutGenerator::setNumberColumnCuts (int value) [inline]
Definition at line 265 of file CbcCutGenerator.hpp.
7.23.3.40 void CbcCutGenerator::incrementNumberColumnCuts (int value = 1) [inline]
Definition at line 268 of file CbcCutGenerator.hpp.
7.23.3.41 int CbcCutGenerator::numberCutsActive() const [inline]
Total number of cuts active after (at end of n cut passes at each node)
Definition at line 272 of file CbcCutGenerator.hpp.
7.23.3.42 void CbcCutGenerator::setNumberCutsActive(int value) [inline]
Definition at line 275 of file CbcCutGenerator.hpp.
7.23.3.43 void CbcCutGenerator::incrementNumberCutsActive(int value = 1) [inline]
Definition at line 278 of file CbcCutGenerator.hpp.
7.23.3.44 void CbcCutGenerator::setSwitchOfflfLessThan (int value) [inline]
Definition at line 281 of file CbcCutGenerator.hpp.
7.23.3.45 int CbcCutGenerator::switchOfflfLessThan ( ) const [inline]
Definition at line 284 of file CbcCutGenerator.hpp.
7.23.3.46 bool CbcCutGenerator::needsOptimalBasis ( ) const [inline]
Say if optimal basis needed.
Definition at line 288 of file CbcCutGenerator.hpp.
7.23.3.47 void CbcCutGenerator::setNeedsOptimalBasis (bool yesNo) [inline]
Set if optimal basis needed.
Definition at line 292 of file CbcCutGenerator.hpp.
7.23.3.48 bool CbcCutGenerator::mustCallAgain ( ) const [inline]
Whether generator MUST be called again if any cuts (i.e. ignore break from loop)
Definition at line 297 of file CbcCutGenerator.hpp.
7.23.3.49 void CbcCutGenerator::setMustCallAgain (bool yesNo) [inline]
Set whether generator MUST be called again if any cuts (i.e. ignore break from loop)
Definition at line 301 of file CbcCutGenerator.hpp.
7.23.3.50 bool CbcCutGenerator::switchedOff() const [inline]
Whether generator switched off for moment.
Definition at line 306 of file CbcCutGenerator.hpp.
```

```
7.23.3.51 void CbcCutGenerator::setSwitchedOff(bool yesNo) [inline]
Set whether generator switched off for moment.
Definition at line 310 of file CbcCutGenerator.hpp.
7.23.3.52 bool CbcCutGenerator::ineffectualCuts ( ) const [inline]
Whether last round of cuts did little.
Definition at line 315 of file CbcCutGenerator.hpp.
7.23.3.53 void CbcCutGenerator::setIneffectualCuts (bool yesNo) [inline]
Set whether last round of cuts did little.
Definition at line 319 of file CbcCutGenerator.hpp.
7.23.3.54 bool CbcCutGenerator::whetherToUse() const [inline]
Whether to use if any cuts generated.
Definition at line 324 of file CbcCutGenerator.hpp.
7.23.3.55 void CbcCutGenerator::setWhetherToUse (bool yesNo) [inline]
Set whether to use if any cuts generated.
Definition at line 328 of file CbcCutGenerator.hpp.
7.23.3.56 bool CbcCutGenerator::whetherInMustCallAgainMode ( ) const [inline]
Whether in must call again mode (or after others)
Definition at line 333 of file CbcCutGenerator.hpp.
7.23.3.57 void CbcCutGenerator::setWhetherInMustCallAgainMode (bool yesNo) [inline]
Set whether in must call again mode (or after others)
Definition at line 337 of file CbcCutGenerator.hpp.
7.23.3.58 bool CbcCutGenerator::whetherCallAtEnd() const [inline]
Whether to call at end.
Definition at line 342 of file CbcCutGenerator.hpp.
7.23.3.59 void CbcCutGenerator::setWhetherCallAtEnd(bool yesNo) [inline]
Set whether to call at end.
Definition at line 346 of file CbcCutGenerator.hpp.
7.23.3.60 int CbcCutGenerator::numberCutsAtRoot()const [inline]
Number of cuts generated at root.
Definition at line 351 of file CbcCutGenerator.hpp.
```

```
7.23.3.61 void CbcCutGenerator::setNumberCutsAtRoot (int value) [inline]
Definition at line 354 of file CbcCutGenerator.hpp.
7.23.3.62 int CbcCutGenerator::numberActiveCutsAtRoot() const [inline]
Number of cuts active at root.
Definition at line 358 of file CbcCutGenerator.hpp.
7.23.3.63 void CbcCutGenerator::setNumberActiveCutsAtRoot (int value ) [inline]
Definition at line 361 of file CbcCutGenerator.hpp.
7.23.3.64 int CbcCutGenerator::numberShortCutsAtRoot()const [inline]
Number of short cuts at root.
Definition at line 365 of file CbcCutGenerator.hpp.
7.23.3.65 void CbcCutGenerator::setNumberShortCutsAtRoot (int value ) [inline]
Definition at line 368 of file CbcCutGenerator.hpp.
7.23.3.66 void CbcCutGenerator::setModel ( CbcModel * model ) [inline]
Set model.
Definition at line 372 of file CbcCutGenerator.hpp.
7.23.3.67 bool CbcCutGenerator::globalCutsAtRoot() const [inline]
Whether global cuts at root.
Definition at line 376 of file CbcCutGenerator.hpp.
7.23.3.68 void CbcCutGenerator::setGlobalCutsAtRoot (bool yesNo ) [inline]
Set whether global cuts at root.
Definition at line 380 of file CbcCutGenerator.hpp.
7.23.3.69 bool CbcCutGenerator::globalCuts ( ) const [inline]
Whether global cuts.
Definition at line 385 of file CbcCutGenerator.hpp.
7.23.3.70 void CbcCutGenerator::setGlobalCuts (bool yesNo) [inline]
Set whether global cuts.
Definition at line 389 of file CbcCutGenerator.hpp.
7.23.3.71 void CbcCutGenerator::addStatistics ( const CbcCutGenerator * other )
Add in statistics from other.
7.23.3.72 void CbcCutGenerator::scaleBackStatistics (int factor)
Scale back statistics by factor.
```

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcCutGenerator.hpp

7.24 CbcCutModifier Class Reference

Abstract cut modifier base class.

```
#include <CbcCutModifier.hpp>
```

Inheritance diagram for CbcCutModifier:



Public Member Functions

• CbcCutModifier ()

Default Constructor.

- CbcCutModifier (const CbcCutModifier &)
- virtual ∼CbcCutModifier ()

Destructor.

• CbcCutModifier & operator= (const CbcCutModifier &rhs)

Assignment.

• virtual CbcCutModifier * clone () const =0

Clone.

• virtual int modify (const OsiSolverInterface *solver, OsiRowCut &cut)=0

Returns 0 unchanged 1 strengthened 2 weakened 3 deleted.

virtual void generateCpp (FILE *)

Create C++ lines to get to current state.

7.24.1 Detailed Description

Abstract cut modifier base class.

In exotic circumstances - cuts may need to be modified a) strengthened - changed b) weakened - changed c) deleted - set to NULL d) unchanged

Definition at line 27 of file CbcCutModifier.hpp.

7.24.2 Constructor & Destructor Documentation

7.24.2.1 CbcCutModifier::CbcCutModifier()

Default Constructor.

7.24.2.2 CbcCutModifier::CbcCutModifier (const CbcCutModifier &)

7.24.2.3 virtual CbcCutModifier::~CbcCutModifier() [virtual]

Destructor.

7.24.3 Member Function Documentation

7.24.3.1 CbcCutModifier& CbcCutModifier::operator= (const CbcCutModifier & rhs)

Assignment.

7.24.3.2 virtual CbcCutModifier* CbcCutModifier::clone() const [pure virtual]

Clone.

Implemented in CbcCutSubsetModifier.

7.24.3.3 virtual int CbcCutModifier::modify (const OsiSolverInterface * solver, OsiRowCut & cut) [pure virtual]

Returns 0 unchanged 1 strengthened 2 weakened 3 deleted.

Implemented in CbcCutSubsetModifier.

7.24.3.4 virtual void CbcCutModifier::generateCpp (FILE *) [inline], [virtual]

Create C++ lines to get to current state.

Reimplemented in CbcCutSubsetModifier.

Definition at line 51 of file CbcCutModifier.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcCutModifier.hpp

7.25 CbcCutSubsetModifier Class Reference

Simple cut modifier base class.

#include <CbcCutSubsetModifier.hpp>

Inheritance diagram for CbcCutSubsetModifier:



Public Member Functions

CbcCutSubsetModifier ()

Default Constructor.

CbcCutSubsetModifier (int firstOdd)

Useful Constructor.

• CbcCutSubsetModifier (const CbcCutSubsetModifier &)

virtual ~CbcCutSubsetModifier ()

Destructor.

CbcCutSubsetModifier & operator= (const CbcCutSubsetModifier &rhs)

Assignment.

virtual CbcCutModifier * clone () const

Clone.

virtual int modify (const OsiSolverInterface *solver, OsiRowCut &cut)

Returns 0 unchanged 1 strengthened 2 weakened 3 deleted.

virtual void generateCpp (FILE *)

Create C++ lines to get to current state.

Protected Attributes

int firstOdd

data First odd variable

7.25.1 Detailed Description

Simple cut modifier base class.

In exotic circumstances - cuts may need to be modified a) strengthened - changed b) weakened - changed c) deleted - set to NULL d) unchanged

initially get rid of cuts with variables >= k could weaken

Definition at line 31 of file CbcCutSubsetModifier.hpp.

7.25.2 Constructor & Destructor Documentation

7.25.2.1 CbcCutSubsetModifier::CbcCutSubsetModifier()

Default Constructor.

7.25.2.2 CbcCutSubsetModifier::CbcCutSubsetModifier (int firstOdd)

Useful Constructor.

7.25.2.3 CbcCutSubsetModifier::CbcCutSubsetModifier (const CbcCutSubsetModifier &)

7.25.2.4 virtual CbcCutSubsetModifier::~CbcCutSubsetModifier() [virtual]

Destructor.

7.25.3 Member Function Documentation

7.25.3.1 CbcCutSubsetModifier & CbcCutSubsetModifier & rhs)

Assignment.

7.25.3.2 virtual CbcCutModifier* CbcCutSubsetModifier::clone() const [virtual]

Clone.

Implements CbcCutModifier.

7.25.3.3 virtual int CbcCutSubsetModifier::modify (const OsiSolverInterface * solver, OsiRowCut & cut) [virtual]

Returns 0 unchanged 1 strengthened 2 weakened 3 deleted.

Implements CbcCutModifier.

7.25.3.4 virtual void CbcCutSubsetModifier::generateCpp(FILE *) [inline], [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcCutModifier.

Definition at line 58 of file CbcCutSubsetModifier.hpp.

7.25.4 Member Data Documentation

7.25.4.1 int CbcCutSubsetModifier::firstOdd_ [protected]

data First odd variable

Definition at line 62 of file CbcCutSubsetModifier.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcCutSubsetModifier.hpp

7.26 CbcDummyBranchingObject Class Reference

Dummy branching object.

#include <CbcDummyBranchingObject.hpp>

Inheritance diagram for CbcDummyBranchingObject:



Public Member Functions

CbcDummyBranchingObject (CbcModel *model=NULL)

Default constructor.

CbcDummyBranchingObject (const CbcDummyBranchingObject &)

Copy constructor.

CbcDummyBranchingObject & operator= (const CbcDummyBranchingObject &rhs)

Assignment operator.

virtual CbcBranchingObject * clone () const

Clone

virtual ~CbcDummyBranchingObject ()

Destructor.

virtual double branch ()

Dummy branch.

virtual void print ()

Print something about branch - only if log level high.

• virtual CbcBranchObjType type () const

Return the type (an integer identifier) of this.

• virtual int compareOriginalObject (const CbcBranchingObject *brObj) const

Compare the original object of this with the original object of brobj.

 virtual CbcRangeCompare compareBranchingObject (const CbcBranchingObject *brObj, const bool replaceIf-Overlap=false)

Compare the this with brObj.

Additional Inherited Members

7.26.1 Detailed Description

Dummy branching object.

This object specifies a one-way dummy branch. This is so one can carry on branching even when it looks feasible Definition at line 18 of file CbcDummyBranchingObject.hpp.

7.26.2 Constructor & Destructor Documentation

7.26.2.1 CbcDummyBranchingObject::CbcDummyBranchingObject (CbcModel * model = NULL)

Default constructor.

7.26.2.2 CbcDummyBranchingObject::CbcDummyBranchingObject (const CbcDummyBranchingObject &)

Copy constructor.

7.26.2.3 virtual CbcDummyBranchingObject::~CbcDummyBranchingObject() [virtual]

Destructor.

7.26.3 Member Function Documentation

7.26.3.1 CbcDummyBranchingObject& CbcDummyBranchingObject::operator= (const CbcDummyBranchingObject & rhs)

Assignment operator.

7.26.3.2 virtual CbcBranchingObject* CbcDummyBranchingObject::clone() const [virtual]

Clone.

Implements CbcBranchingObject.

7.26.3.3 virtual double CbcDummyBranchingObject::branch() [virtual]

Dummy branch.

Implements CbcBranchingObject.

7.26.3.4 virtual void CbcDummyBranchingObject::print() [virtual]

Print something about branch - only if log level high.

7.26.3.5 virtual CbcBranchObjType CbcDummyBranchingObject::type() const [inline], [virtual]

Return the type (an integer identifier) of this.

Implements CbcBranchingObject.

Definition at line 56 of file CbcDummyBranchingObject.hpp.

7.26.3.6 virtual int CbcDummyBranchingObject::compareOriginalObject (const CbcBranchingObject * brObj) const [virtual]

Compare the original object of this with the original object of brobj.

Assumes that there is an ordering of the original objects. This method should be invoked only if this and brObj are of the same type. Return negative/0/positive depending on whether this is smaller/same/larger than the argument.

Reimplemented from CbcBranchingObject.

7.26.3.7 virtual CbcRangeCompare CbcDummyBranchingObject::compareBranchingObject (const CbcBranchingObject * brObj, const bool replacelfOverlap = false) [virtual]

Compare the this with brObj.

this and brobj must be os the same type and must have the same original object, but they may have different feasible regions. Return the appropriate CbcRangeCompare value (first argument being the sub/superset if that's the case). In case of overlap (and if replaceIfoverlap is true) replace the current branching object with one whose feasible region is the overlap.

Implements CbcBranchingObject.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcDummyBranchingObject.hpp

7.27 CbcDynamicPseudoCostBranchingObject Class Reference

Simple branching object for an integer variable with pseudo costs.

#include <CbcBranchDynamic.hpp>

Inheritance diagram for CbcDynamicPseudoCostBranchingObject:



Public Member Functions

CbcDynamicPseudoCostBranchingObject ()

Default constructor.

 CbcDynamicPseudoCostBranchingObject (CbcModel *model, int variable, int way, double value, CbcSimple-IntegerDynamicPseudoCost *object)

Create a standard floor/ceiling branch object.

CbcDynamicPseudoCostBranchingObject (CbcModel *model, int variable, int way, double lowerValue, double upperValue)

Create a degenerate branch object.

CbcDynamicPseudoCostBranchingObject (const CbcDynamicPseudoCostBranchingObject &)

Copy constructor.

CbcDynamicPseudoCostBranchingObject & operator= (const CbcDynamicPseudoCostBranchingObject &rhs)

Assignment operator.

virtual CbcBranchingObject * clone () const

Clone

virtual ~CbcDynamicPseudoCostBranchingObject ()

Destructor.

void fillPart (int variable, int way, double value, CbcSimpleIntegerDynamicPseudoCost *object)

Does part of constructor.

• virtual double branch ()

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

· virtual int fillStrongInfo (CbcStrongInfo &info)

Some branchingObjects may claim to be able to skip strong branching.

· double changeInGuessed () const

Change in guessed.

void setChangeInGuessed (double value)

Set change in guessed.

CbcSimpleIntegerDynamicPseudoCost * object () const

Return object.

void setObject (CbcSimpleIntegerDynamicPseudoCost *object)

Set object.

• virtual CbcBranchObjType type () const

Return the type (an integer identifier) of this.

Protected Attributes

• double changeInGuessed_

Change in guessed objective value for next branch.

CbcSimpleIntegerDynamicPseudoCost * object_

Pointer back to object.

7.27.1 Detailed Description

Simple branching object for an integer variable with pseudo costs.

This object can specify a two-way branch on an integer variable. For each arm of the branch, the upper and lower bounds on the variable can be independently specified.

Variable_holds the index of the integer variable in the integerVariable_array of the model.

Definition at line 111 of file CbcBranchDynamic.hpp.

- 7.27.2 Constructor & Destructor Documentation
- 7.27.2.1 CbcDynamicPseudoCostBranchingObject::CbcDynamicPseudoCostBranchingObject ()

Default constructor.

7.27.2.2 CbcDynamicPseudoCostBranchingObject::CbcDynamicPseudoCostBranchingObject (CbcModel * model, int variable, int way, double value, CbcSimpleIntegerDynamicPseudoCost * object)

Create a standard floor/ceiling branch object.

Specifies a simple two-way branch. Let value = x*. One arm of the branch will be is $lb \le x \le loor(x*)$, the other $ceil(x*) \le x \le loor(x*)$. Specify way = -1 to set the object state to perform the down arm first, way = 1 for the up arm.

7.27.2.3 CbcDynamicPseudoCostBranchingObject::CbcDynamicPseudoCostBranchingObject (CbcModel * model, int variable, int way, double lowerValue, double upperValue)

Create a degenerate branch object.

Specifies a 'one-way branch'. Calling $\frac{branch()}{branch()}$ for this object will always result in lowerValue $\le x \le y$ upperValue. Used to fix a variable when lowerValue = upperValue.

7.27.2.4 CbcDynamicPseudoCostBranchingObject::CbcDynamicPseudoCostBranchingObject (const CbcDynamicPseudoCostBranchingObject &)

Copy constructor.

7.27.2.5 virtual CbcDynamicPseudoCostBranchingObject::~CbcDynamicPseudoCostBranchingObject() [virtual]

Destructor.

- 7.27.3 Member Function Documentation
- 7.27.3.1 CbcDynamicPseudoCostBranchingObject& CbcDynamicPseudoCostBranchingObject::operator= (const CbcDynamicPseudoCostBranchingObject & rhs)

Assignment operator.

7.27.3.2 virtual CbcBranchingObject* CbcDynamicPseudoCostBranchingObject::clone()const [virtual]

Clone.

Reimplemented from CbcIntegerBranchingObject.

7.27.3.3 void CbcDynamicPseudoCostBranchingObject::fillPart (int *variable*, int *way*, double *value*, CbcSimpleIntegerDynamicPseudoCost * *object*)

Does part of constructor.

7.27.3.4 virtual double CbcDynamicPseudoCostBranchingObject::branch() [virtual]

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next

This version also changes guessed objective value

Reimplemented from CbcIntegerBranchingObject.

7.27.3.5 virtual int CbcDynamicPseudoCostBranchingObject::fillStrongInfo (CbcStrongInfo & info) [virtual]

Some branchingObjects may claim to be able to skip strong branching.

If so they have to fill in CbcStrongInfo. The object mention in incoming CbcStrongInfo must match. Returns nonzero if skip is wanted

Reimplemented from CbcBranchingObject.

7.27.3.6 double CbcDynamicPseudoCostBranchingObject::changeInGuessed () const [inline]

Change in guessed.

Definition at line 170 of file CbcBranchDynamic.hpp.

7.27.3.7 void CbcDynamicPseudoCostBranchingObject::setChangeInGuessed (double value) [inline]

Set change in guessed.

Definition at line 174 of file CbcBranchDynamic.hpp.

7.27.3.8 CbcSimpleIntegerDynamicPseudoCost* CbcDynamicPseudoCostBranchingObject::object () const [inline]

Return object.

Definition at line 178 of file CbcBranchDynamic.hpp.

7.27.3.9 void CbcDynamicPseudoCostBranchingObject::setObject (CbcSimpleIntegerDynamicPseudoCost * object) [inline]

Set object.

Definition at line 182 of file CbcBranchDynamic.hpp.

7.27.3.10 virtual CbcBranchObjType CbcDynamicPseudoCostBranchingObject::type() const [inline], [virtual]

Return the type (an integer identifier) of this.

Reimplemented from CbcIntegerBranchingObject.

Definition at line 187 of file CbcBranchDynamic.hpp.

7.27.4 Member Data Documentation

7.27.4.1 double CbcDynamicPseudoCostBranchingObject::changeInGuessed_ [protected]

Change in guessed objective value for next branch.

Definition at line 199 of file CbcBranchDynamic.hpp.

7.27.4.2 CbcSimpleIntegerDynamicPseudoCost* CbcDynamicPseudoCostBranchingObject::object_ [protected]

Pointer back to object.

Definition at line 201 of file CbcBranchDynamic.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcBranchDynamic.hpp

7.28 CbcEventHandler Class Reference

Base class for Cbc event handling.

```
#include <CbcEventHandler.hpp>
```

Public Types

enum CbcEvent {
 node = 200, treeStatus, solution, heuristicSolution,
 beforeSolution1, beforeSolution2, afterHeuristic, smallBranchAndBound,
 heuristicPass, endSearch }

Events known to cbc.

enum CbcAction {
 noAction = -1, stop = 0, restart, restartRoot,
 addCuts, killSolution, takeAction }

Action codes returned by the event handler.

typedef std::map < CbcEvent,
 CbcAction > eaMapPair

Data type for event/action pairs.

Public Member Functions

Event Processing

• virtual CbcAction event (CbcEvent whichEvent)

Return the action to be taken for an event.

virtual CbcAction event (CbcEvent whichEvent, void *data)

Return the action to be taken for an event - and modify data.

Constructors and destructors

CbcEventHandler (CbcModel *model=0)

Default constructor.

CbcEventHandler (const CbcEventHandler &orig)

Copy constructor.

CbcEventHandler & operator= (const CbcEventHandler &rhs)

Assignment

virtual CbcEventHandler * clone () const

Clone (virtual) constructor.

virtual ∼CbcEventHandler ()

Destructor.

Set/Get methods

void setModel (CbcModel *model)

Set model.

const CbcModel * getModel () const

Get model.

void setDfltAction (CbcAction action)

Set the default action.

void setAction (CbcEvent event, CbcAction action)

Set the action code associated with an event.

Protected Attributes

Data members

Protected (as opposed to private) to allow access by derived classes.

CbcModel * model

Pointer to associated CbcModel.

CbcAction dfltAction_

Default action.

eaMapPair * eaMap

Pointer to a map that holds non-default event/action pairs.

7.28.1 Detailed Description

Base class for Cbc event handling.

Up front: We're not talking about unanticipated events here. We're talking about anticipated events, in the sense that the code is going to make a call to event() and is prepared to obey the return value that it receives.

The general pattern for usage is as follows:

- 1. Create a CbcEventHandler object. This will be initialised with a set of default actions for every recognised event.
- 2. Attach the event handler to the CbcModel object.
- 3. When execution reaches the point where an event occurs, call the event handler as CbcEventHandler::event(the event). The return value will specify what the code should do in response to the event.

The return value associated with an event can be changed at any time.

Definition at line 81 of file CbcEventHandler.hpp.

7.28.2 Member Typedef Documentation

7.28.2.1 typedef std::map < CbcEvent, CbcAction > CbcEventHandler::eaMapPair

Data type for event/action pairs.

Definition at line 135 of file CbcEventHandler.hpp.

7.28.3 Member Enumeration Documentation

7.28.3.1 enum CbcEventHandler::CbcEvent

Events known to cbc.

Enumerator

node Processing of the current node is complete.

treeStatus A tree status interval has arrived.

solution A solution has been found.

heuristicSolution A heuristic solution has been found.

before Solution 1 A solution will be found unless user takes action (first check).

beforeSolution2 A solution will be found unless user takes action (thorough check).

afterHeuristic After failed heuristic.

smallBranchAndBound On entry to small branch and bound.

heuristicPass After a pass of heuristic.

endSearch End of search.

Definition at line 87 of file CbcEventHandler.hpp.

7.28.3.2 enum CbcEventHandler::CbcAction

Action codes returned by the event handler.

Specific values are chosen to match ClpEventHandler return codes.

Enumerator

```
noAction Continue — no action required.
```

stop Stop — abort the current run at the next opportunity.

restart — restart branch-and-cut search; do not undo root node processing.

restartRoot RestartRoot — undo root node and start branch-and-cut afresh.

addCuts Add special cuts.

killSolution Pretend solution never happened.

takeAction Take action on modified data.

Definition at line 114 of file CbcEventHandler.hpp.

7.28.4 Constructor & Destructor Documentation

7.28.4.1 CbcEventHandler::CbcEventHandler (CbcModel * model = 0)

Default constructor.

7.28.4.2 CbcEventHandler::CbcEventHandler (const CbcEventHandler & orig)

Copy constructor.

7.28.4.3 virtual CbcEventHandler::~CbcEventHandler() [virtual]

Destructor.

7.28.5 Member Function Documentation

7.28.5.1 virtual CbcAction CbcEventHandler::event (CbcEvent whichEvent) [virtual]

Return the action to be taken for an event.

Return the action that should be taken in response to the event passed as the parameter. The default implementation simply reads a return code from a map.

7.28.5.2 virtual CbcAction CbcEventHandler::event(CbcEvent whichEvent, void * data) [virtual]

Return the action to be taken for an event - and modify data.

Return the action that should be taken in response to the event passed as the parameter. The default implementation simply reads a return code from a map.

7.28.5.3 CbcEventHandler& CbcEventHandler::operator= (const CbcEventHandler & rhs)

Assignment.

7.28.5.4 virtual CbcEventHandler* CbcEventHandler::clone() const [virtual]

Clone (virtual) constructor.

7.28.5.5 void CbcEventHandler::setModel (CbcModel * model) [inline]

Set model.

Definition at line 190 of file CbcEventHandler.hpp.

7.28.5.6 const CbcModel* CbcEventHandler::getModel() const [inline]

Get model.

Definition at line 196 of file CbcEventHandler.hpp.

7.28.5.7 void CbcEventHandler::setDfltAction (CbcAction action) [inline]

Set the default action.

Definition at line 202 of file CbcEventHandler.hpp.

7.28.5.8 void CbcEventHandler::setAction (CbcEvent event, CbcAction action) [inline]

Set the action code associated with an event.

Definition at line 208 of file CbcEventHandler.hpp.

7.28.6 Member Data Documentation

7.28.6.1 CbcModel* CbcEventHandler::model_ [protected]

Pointer to associated CbcModel.

Definition at line 228 of file CbcEventHandler.hpp.

7.28.6.2 CbcAction CbcEventHandler::dfltAction_ [protected]

Default action.

Definition at line 232 of file CbcEventHandler.hpp.

7.28.6.3 eaMapPair* CbcEventHandler::eaMap_ [protected]

Pointer to a map that holds non-default event/action pairs.

Definition at line 236 of file CbcEventHandler.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcEventHandler.hpp

7.29 CbcFathom Class Reference

Fathom base class.

#include <CbcFathom.hpp>

Inheritance diagram for CbcFathom:



Public Member Functions

- CbcFathom ()
- CbcFathom (CbcModel &model)
- virtual ∼CbcFathom ()
- virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

virtual CbcFathom * clone () const =0

Clone.

virtual void resetModel (CbcModel *model)=0

Resets stuff if model changes.

virtual int fathom (double *&newSolution)=0

returns 0 if no fathoming attempted, 1 fully fathomed, 2 incomplete search, 3 incomplete search but treat as complete.

• bool possible () const

Protected Attributes

CbcModel * model_

Model.

bool possible

Possible - if this method of fathoming can be used.

7.29.1 Detailed Description

Fathom base class.

The idea is that after some branching the problem will be effectively smaller than the original problem and maybe there will be a more specialized technique which can completely fathom this branch quickly.

One method is to presolve the problem to give a much smaller new problem and then do branch and cut on that. Another might be dynamic programming.

Definition at line 32 of file CbcFathom.hpp.

```
7.29.2.1 CbcFathom::CbcFathom()
7.29.2.2 CbcFathom::CbcFathom(CbcModel & model)
7.29.2.3 virtual CbcFathom::~CbcFathom() [virtual]
7.29.3 Member Function Documentation
7.29.3.1 virtual void CbcFathom::setModel(CbcModel * model) [virtual]
update model(This is needed if cliques update matrix etc)
Reimplemented in CbcFathomDynamicProgramming.
7.29.3.2 virtual CbcFathom* CbcFathom::clone() const [pure virtual]
Clone.
Implemented in CbcFathomDynamicProgramming.
7.29.3.3 virtual void CbcFathom::resetModel(CbcModel * model) [pure virtual]
Resets stuff if model changes.
Implemented in CbcFathomDynamicProgramming.
```

7.29.3.4 virtual int CbcFathom::fathom (double *& newSolution) [pure virtual]

returns 0 if no fathoming attempted, 1 fully fathomed, 2 incomplete search, 3 incomplete search but treat as complete.

If solution then newSolution will not be NULL and will be freed by CbcModel. It is expected that the solution is better than best so far but CbcModel will double check.

If returns 3 then of course there is no guarantee of global optimum

Implemented in CbcFathomDynamicProgramming.

```
7.29.3.5 bool CbcFathom::possible() const [inline]
```

Definition at line 62 of file CbcFathom.hpp.

7.29.4 Member Data Documentation

7.29.4.1 CbcModel* CbcFathom::model_ [protected]

Model.

Definition at line 69 of file CbcFathom.hpp.

7.29.4.2 bool CbcFathom::possible_ [protected]

Possible - if this method of fathoming can be used.

Definition at line 71 of file CbcFathom.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcFathom.hpp

7.30 CbcFathomDynamicProgramming Class Reference

FathomDynamicProgramming class.

#include <CbcFathomDynamicProgramming.hpp>

Inheritance diagram for CbcFathomDynamicProgramming:



Public Member Functions

- CbcFathomDynamicProgramming ()
- CbcFathomDynamicProgramming (CbcModel &model)
- CbcFathomDynamicProgramming (const CbcFathomDynamicProgramming &rhs)
- virtual ~CbcFathomDynamicProgramming ()
- virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

virtual CbcFathom * clone () const

Clone.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

• virtual int fathom (double *&newSolution)

returns 0 if no fathoming attempted, 1 fully fathomed, 2 incomplete search, 3 incomplete search but treat as complete.

• int maximumSize () const

Maximum size allowed.

- void setMaximumSize (int value)
- int checkPossible (int allowableSize=0)

Returns type of algorithm and sets up arrays.

- · void setAlgorithm (int value)
- bool tryColumn (int numberElements, const int *rows, const double *coefficients, double cost, int upper=COIN_I-NT_MAX)

Tries a column returns true if was used in making any changes.

• const double * cost () const

Returns cost array.

const int * back () const

Returns back array.

· int target () const

Gets bit pattern for target result.

• void setTarget (int value)

Sets bit pattern for target result.

Protected Attributes

int size

Size of states (power of 2 unless just one constraint)

• int type_

Type - 0 coefficients and rhs all 1, 1 - coefficients > 1 or rhs > 1.

double * cost_

Space for states.

int * back_

Which state produced this cheapest one.

int * lookup_

Some rows may be satisified so we need a lookup.

int * indices_

Space for sorted indices.

· int numberActive_

Number of active rows.

• int maximumSizeAllowed_

Maximum size allowed.

int * startBit

Start bit for each active row.

int * numberBits_

Number bits for each active row.

int * rhs

Effective rhs.

int * coefficients_

Space for sorted coefficients.

int target_

Target pattern.

int numberNonOne

Number of Non 1 rhs.

· int bitPattern_

Current bit pattern.

• int algorithm_

Current algorithm.

7.30.1 Detailed Description

FathomDynamicProgramming class.

The idea is that after some branching the problem will be effectively smaller than the original problem and maybe there will be a more specialized technique which can completely fathom this branch quickly.

This is a dynamic programming implementation which is very fast for some specialized problems. It expects small integral rhs, an all integer problem and positive integral coefficients. At present it can not do general set covering problems just set partitioning. It can find multiple optima for various rhs combinations.

The main limiting factor is size of state space. Each 1 rhs doubles the size of the problem. 2 or 3 rhs quadruples, 4,5,6,7 by 8 etc.

Definition at line 28 of file CbcFathomDynamicProgramming.hpp.

```
7.30.2 Constructor & Destructor Documentation
7.30.2.1 CbcFathomDynamicProgramming::CbcFathomDynamicProgramming ( )
7.30.2.2 CbcFathomDynamicProgramming::CbcFathomDynamicProgramming ( CbcModel & model )
7.30.2.3 CbcFathomDynamicProgramming::CbcFathomDynamicProgramming ( const CbcFathomDynamicProgramming &
        rhs )
7.30.2.4 virtual CbcFathomDynamicProgramming::~CbcFathomDynamicProgramming() [virtual]
7.30.3 Member Function Documentation
7.30.3.1 virtual void CbcFathomDynamicProgramming::setModel ( CbcModel * model ) [virtual]
update model (This is needed if cliques update matrix etc)
Reimplemented from CbcFathom.
7.30.3.2 virtual CbcFathom* CbcFathomDynamicProgramming::clone() const [virtual]
Clone.
Implements CbcFathom.
7.30.3.3 virtual void CbcFathomDynamicProgramming::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcFathom.
7.30.3.4 virtual int CbcFathomDynamicProgramming::fathom(double *& newSolution) [virtual]
```

returns 0 if no fathoming attempted, 1 fully fathomed, 2 incomplete search, 3 incomplete search but treat as complete.

If solution then newSolution will not be NULL and will be freed by CbcModel. It is expected that the solution is better

Implements CbcFathom.

than best so far but CbcModel will double check.

If returns 3 then of course there is no guarantee of global optimum

```
7.30.3.5 int CbcFathomDynamicProgramming::maximumSize ( ) const [inline]
Maximum size allowed.
Definition at line 60 of file CbcFathomDynamicProgramming.hpp.
7.30.3.6 void CbcFathomDynamicProgramming::setMaximumSize(int value) [inline]
Definition at line 63 of file CbcFathomDynamicProgramming.hpp.
7.30.3.7 int CbcFathomDynamicProgramming::checkPossible ( int allowableSize = 0 )
Returns type of algorithm and sets up arrays.
7.30.3.8 void CbcFathomDynamicProgramming::setAlgorithm (int value) [inline]
Definition at line 69 of file CbcFathomDynamicProgramming.hpp.
7.30.3.9 bool CbcFathomDynamicProgramming::tryColumn ( int numberElements, const int * rows, const double * coefficients,
        double cost, int upper = COIN_INT_MAX )
Tries a column returns true if was used in making any changes.
7.30.3.10 const double* CbcFathomDynamicProgramming::cost() const [inline]
Returns cost array.
Definition at line 79 of file CbcFathomDynamicProgramming.hpp.
7.30.3.11 const int* CbcFathomDynamicProgramming::back( ) const [inline]
Returns back array.
Definition at line 83 of file CbcFathomDynamicProgramming.hpp.
7.30.3.12 int CbcFathomDynamicProgramming::target() const [inline]
Gets bit pattern for target result.
Definition at line 87 of file CbcFathomDynamicProgramming.hpp.
7.30.3.13 void CbcFathomDynamicProgramming::setTarget (int value) [inline]
Sets bit pattern for target result.
Definition at line 91 of file CbcFathomDynamicProgramming.hpp.
7.30.4 Member Data Documentation
7.30.4.1 int CbcFathomDynamicProgramming::size_ [protected]
Size of states (power of 2 unless just one constraint)
Definition at line 128 of file CbcFathomDynamicProgramming.hpp.
7.30.4.2 int CbcFathomDynamicProgramming::type_ [protected]
Type - 0 coefficients and rhs all 1, 1 - coefficients > 1 or rhs > 1.
```

Definition at line 132 of file CbcFathomDynamicProgramming.hpp.

7.30.4.3 double* CbcFathomDynamicProgramming::cost_ [protected]

Space for states.

Definition at line 134 of file CbcFathomDynamicProgramming.hpp.

7.30.4.4 int* CbcFathomDynamicProgramming::back_ [protected]

Which state produced this cheapest one.

Definition at line 136 of file CbcFathomDynamicProgramming.hpp.

7.30.4.5 int* CbcFathomDynamicProgramming::lookup_ [protected]

Some rows may be satisified so we need a lookup.

Definition at line 138 of file CbcFathomDynamicProgramming.hpp.

7.30.4.6 int* CbcFathomDynamicProgramming::indices_ [protected]

Space for sorted indices.

Definition at line 140 of file CbcFathomDynamicProgramming.hpp.

7.30.4.7 int CbcFathomDynamicProgramming::numberActive_ [protected]

Number of active rows.

Definition at line 142 of file CbcFathomDynamicProgramming.hpp.

7.30.4.8 int CbcFathomDynamicProgramming::maximumSizeAllowed_ [protected]

Maximum size allowed.

Definition at line 144 of file CbcFathomDynamicProgramming.hpp.

7.30.4.9 int* CbcFathomDynamicProgramming::startBit_ [protected]

Start bit for each active row.

Definition at line 146 of file CbcFathomDynamicProgramming.hpp.

7.30.4.10 int* CbcFathomDynamicProgramming::numberBits_ [protected]

Number bits for each active row.

Definition at line 148 of file CbcFathomDynamicProgramming.hpp.

7.30.4.11 int* CbcFathomDynamicProgramming::rhs_ [protected]

Effective rhs.

Definition at line 150 of file CbcFathomDynamicProgramming.hpp.

7.30.4.12 int* CbcFathomDynamicProgramming::coefficients_ [protected]

Space for sorted coefficients.

Definition at line 152 of file CbcFathomDynamicProgramming.hpp.

7.30.4.13 int CbcFathomDynamicProgramming::target_ [protected]

Target pattern.

Definition at line 154 of file CbcFathomDynamicProgramming.hpp.

7.30.4.14 int CbcFathomDynamicProgramming::numberNonOne_ [protected]

Number of Non 1 rhs.

Definition at line 156 of file CbcFathomDynamicProgramming.hpp.

7.30.4.15 int CbcFathomDynamicProgramming::bitPattern_ [protected]

Current bit pattern.

Definition at line 158 of file CbcFathomDynamicProgramming.hpp.

7.30.4.16 int CbcFathomDynamicProgramming::algorithm_ [protected]

Current algorithm.

Definition at line 160 of file CbcFathomDynamicProgramming.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcFathomDynamicProgramming.hpp

7.31 CbcFeasibilityBase Class Reference

```
#include <CbcFeasibilityBase.hpp>
```

Public Member Functions

- · CbcFeasibilityBase ()
- virtual int feasible (CbcModel *, int)

On input mode: 0 - called after a solve but before any cuts -1 - called after strong branching Returns: 0 - no opinion -1 pretend infeasible 1 pretend integer solution.

- virtual ∼CbcFeasibilityBase ()
- CbcFeasibilityBase (const CbcFeasibilityBase &)
- CbcFeasibilityBase & operator= (const CbcFeasibilityBase &)
- virtual CbcFeasibilityBase * clone () const

Clone.

7.31.1 Detailed Description

Definition at line 22 of file CbcFeasibilityBase.hpp.

7.31.2 Constructor & Destructor Documentation

7.31.2.1 CbcFeasibilityBase::CbcFeasibilityBase() [inline]

Definition at line 25 of file CbcFeasibilityBase.hpp.

7.31.2.2 virtual CbcFeasibilityBase::~CbcFeasibilityBase() [inline], [virtual]

Definition at line 40 of file CbcFeasibilityBase.hpp.

7.31.2.3 CbcFeasibilityBase::CbcFeasibilityBase (const CbcFeasibilityBase &) [inline]

Definition at line 43 of file CbcFeasibilityBase.hpp.

7.31.3 Member Function Documentation

7.31.3.1 virtual int CbcFeasibilityBase::feasible (CbcModel *, int) [inline], [virtual]

On input mode: 0 - called after a solve but before any cuts -1 - called after strong branching Returns: 0 - no opinion -1 pretend infeasible 1 pretend integer solution.

Definition at line 36 of file CbcFeasibilityBase.hpp.

7.31.3.2 CbcFeasibilityBase& CbcFeasibilityBase::operator=(const CbcFeasibilityBase &) [inline]

Definition at line 46 of file CbcFeasibilityBase.hpp.

7.31.3.3 virtual CbcFeasibilityBase * CbcFeasibilityBase::clone()const [inline],[virtual]

Clone.

Definition at line 51 of file CbcFeasibilityBase.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcFeasibilityBase.hpp

7.32 CbcFixingBranchingObject Class Reference

General Branching Object class.

#include <CbcFollowOn.hpp>

Inheritance diagram for CbcFixingBranchingObject:



Public Member Functions

- CbcFixingBranchingObject ()
- CbcFixingBranchingObject (CbcModel *model, int way, int numberOnDownSide, const int *down, int numberOn-UpSide, const int *up)
- CbcFixingBranchingObject (const CbcFixingBranchingObject &)
- CbcFixingBranchingObject & operator= (const CbcFixingBranchingObject &rhs)

```
    virtual CbcBranchingObject * clone () const

          Clone.

    virtual ~CbcFixingBranchingObject ()

    • virtual double branch ()
          Does next branch and updates state.
    · virtual void print ()
          Print something about branch - only if log level high.
    • virtual CbcBranchObjType type () const
          Return the type (an integer identifier) of this.

    virtual int compareOriginalObject (const CbcBranchingObject *brObj) const

          Compare the original object of this with the original object of brobj.
    • virtual CbcRangeCompare compareBranchingObject (const CbcBranchingObject *brObj, const bool replaceIf-
      Overlap=false)
          Compare the this with brobj.
Additional Inherited Members
7.32.1 Detailed Description
General Branching Object class.
Each way fixes some variables to lower bound
Definition at line 74 of file CbcFollowOn.hpp.
7.32.2 Constructor & Destructor Documentation
7.32.2.1 CbcFixingBranchingObject::CbcFixingBranchingObject()
7.32.2.2 CbcFixingBranchingObject::CbcFixingBranchingObject ( CbcModel * model, int way, int numberOnDownSide, const int
         * down, int numberOnUpSide, const int * up )
7.32.2.3 CbcFixingBranchingObject::CbcFixingBranchingObject ( const CbcFixingBranchingObject & )
7.32.2.4 virtual CbcFixingBranchingObject::~CbcFixingBranchingObject() [virtual]
7.32.3 Member Function Documentation
7.32.3.1 CbcFixingBranchingObject & CbcFixingBranchingObject const CbcFixingBranchingObject & rhs )
7.32.3.2 virtual CbcBranchingObject* CbcFixingBranchingObject::clone( )const [virtual]
Clone.
Implements CbcBranchingObject.
7.32.3.3 virtual double CbcFixingBranchingObject::branch() [virtual]
Does next branch and updates state.
Implements CbcBranchingObject.
7.32.3.4 virtual void CbcFixingBranchingObject::print() [virtual]
```

Print something about branch - only if log level high.

7.32.3.5 virtual CbcBranchObjType CbcFixingBranchingObject::type() const [inline], [virtual]

Return the type (an integer identifier) of this.

Implements CbcBranchingObject.

Definition at line 117 of file CbcFollowOn.hpp.

7.32.3.6 virtual int CbcFixingBranchingObject::compareOriginalObject (const CbcBranchingObject * brObj) const [virtual]

Compare the original object of this with the original object of brobj.

Assumes that there is an ordering of the original objects. This method should be invoked only if this and brObj are of the same type. Return negative/0/positive depending on whether this is smaller/same/larger than the argument.

Reimplemented from CbcBranchingObject.

7.32.3.7 virtual CbcRangeCompare CbcFixingBranchingObject::compareBranchingObject (const CbcBranchingObject * brObj, const bool replacelfOverlap = false) [virtual]

Compare the this with brObj.

this and brobj must be os the same type and must have the same original object, but they may have different feasible regions. Return the appropriate CbcRangeCompare value (first argument being the sub/superset if that's the case). In case of overlap (and if replaceIfOverlap is true) replace the current branching object with one whose feasible region is the overlap.

Implements CbcBranchingObject.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcFollowOn.hpp

7.33 CbcFixVariable Class Reference

Class for consequent bounds.

#include <CbcFixVariable.hpp>

Inheritance diagram for CbcFixVariable:



Public Member Functions

- CbcFixVariable ()
- CbcFixVariable (int numberStates, const int *states, const int *numberNewLower, const int **newLowerValue, const int **newUpperValue, const int **newUpperValue, const int **upperColumn)
- CbcFixVariable (const CbcFixVariable &rhs)
- CbcFixVariable & operator= (const CbcFixVariable &rhs)
- virtual CbcConsequence * clone () const

Clone.

```
    virtual ∼CbcFixVariable ()
```

Destructor.

virtual void applyToSolver (OsiSolverInterface *solver, int state) const

Apply to an LP solver.

Protected Attributes

int numberStates

Number of states.

int * states

Values of integers for various states.

int * startLower

Start of information for each state (setting new lower)

int * startUpper

Start of information for each state (setting new upper)

double * newBound

For each variable new bounds.

int * variable

Variable.

7.33.1 Detailed Description

Class for consequent bounds.

When a variable is branched on it normally interacts with other variables by means of equations. There are cases where we want to step outside LP and do something more directly e.g. fix bounds. This class is for that.

A state of -9999 means at LB, +9999 means at UB, others mean if fixed to that value.

Definition at line 22 of file CbcFixVariable.hpp.

- 7.33.2 Constructor & Destructor Documentation
- 7.33.2.1 CbcFixVariable::CbcFixVariable ()
- 7.33.2.2 CbcFixVariable::CbcFixVariable (int *numberStates*, const int * states, const int * numberNewLower, const int ** newLowerValue, const int ** lowerColumn, const int * numberNewUpper, const int ** newUpperValue, const int ** upperColumn)
- 7.33.2.3 CbcFixVariable::CbcFixVariable (const CbcFixVariable & rhs)
- 7.33.2.4 virtual CbcFixVariable::~CbcFixVariable() [virtual]

Destructor.

- 7.33.3 Member Function Documentation
- 7.33.3.1 CbcFixVariable & CbcFixVariable::operator= (const CbcFixVariable & rhs)
- 7.33.3.2 virtual CbcConsequence* CbcFixVariable::clone() const [virtual]

Clone.

Implements CbcConsequence.

7.33.3.3 virtual void CbcFixVariable::applyToSolver(OsiSolverInterface * solver, int state) const [virtual]

Apply to an LP solver.

Action depends on state

Implements CbcConsequence.

7.33.4 Member Data Documentation

7.33.4.1 int CbcFixVariable::numberStates_ [protected]

Number of states.

Definition at line 53 of file CbcFixVariable.hpp.

7.33.4.2 int* CbcFixVariable::states_ [protected]

Values of integers for various states.

Definition at line 55 of file CbcFixVariable.hpp.

7.33.4.3 int* CbcFixVariable::startLower_ [protected]

Start of information for each state (setting new lower)

Definition at line 57 of file CbcFixVariable.hpp.

7.33.4.4 int* CbcFixVariable::startUpper_ [protected]

Start of information for each state (setting new upper)

Definition at line 59 of file CbcFixVariable.hpp.

7.33.4.5 double* CbcFixVariable::newBound_ [protected]

For each variable new bounds.

Definition at line 61 of file CbcFixVariable.hpp.

7.33.4.6 int* CbcFixVariable::variable_ [protected]

Variable.

Definition at line 63 of file CbcFixVariable.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcFixVariable.hpp

7.34 CbcFollowOn Class Reference

Define a follow on class.

#include <CbcFollowOn.hpp>

Inheritance diagram for CbcFollowOn:



Public Member Functions

- CbcFollowOn ()
- CbcFollowOn (CbcModel *model)

Useful constructor.

- CbcFollowOn (const CbcFollowOn &)
- virtual CbcObject * clone () const

Clone.

- CbcFollowOn & operator= (const CbcFollowOn &rhs)
- ∼CbcFollowOn ()
- virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const

Infeasibility - large is 0.5.

• virtual void feasibleRegion ()

This looks at solution and sets bounds to contain solution.

virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Creates a branching object.

• virtual int gutsOfFollowOn (int &otherRow, int &preferredWay) const

As some computation is needed in more than one place - returns row.

Protected Attributes

CoinPackedMatrix matrix

data Matrix

CoinPackedMatrix matrixByRow_

Matrix by row.

• int * rhs_

Possible rhs (if 0 then not possible)

7.34.1 Detailed Description

Define a follow on class.

The idea of this is that in air-crew scheduling problems crew may fly in on flight A and out on flight B or on some other flight. A useful branch is one which on one side fixes all which go out on flight B to 0, while the other branch fixes all those that do NOT go out on flight B to 0.

This branching rule should be in addition to normal rules and have a high priority.

Definition at line 25 of file CbcFollowOn.hpp.

```
7.34.2 Constructor & Destructor Documentation
7.34.2.1 CbcFollowOn::CbcFollowOn()
7.34.2.2 CbcFollowOn::CbcFollowOn ( CbcModel * model )
Useful constructor.
7.34.2.3 CbcFollowOn::CbcFollowOn ( const CbcFollowOn & )
7.34.2.4 CbcFollowOn::~CbcFollowOn()
7.34.3 Member Function Documentation
7.34.3.1 virtual CbcObject* CbcFollowOn::clone() const [virtual]
Clone.
Implements CbcObject.
7.34.3.2 CbcFollowOn& CbcFollowOn::operator= ( const CbcFollowOn & rhs )
7.34.3.3 virtual double CbcFollowOn::infeasibility ( const OsiBranchingInformation * info, int & preferredWay ) const
         [virtual]
Infeasibility - large is 0.5.
Reimplemented from CbcObject.
7.34.3.4 virtual void CbcFollowOn::feasibleRegion() [virtual]
This looks at solution and sets bounds to contain solution.
Implements CbcObject.
7.34.3.5 virtual CbcBranchingObject* CbcFollowOn::createCbcBranch (OsiSolverInterface * solver, const
         OsiBranchingInformation * info, int way ) [virtual]
Creates a branching object.
Reimplemented from CbcObject.
7.34.3.6 virtual int CbcFollowOn::gutsOfFollowOn ( int & otherRow, int & preferredWay ) const [virtual]
As some computation is needed in more than one place - returns row.
7.34.4 Member Data Documentation
7.34.4.1 CoinPackedMatrix CbcFollowOn::matrix [protected]
data Matrix
Definition at line 64 of file CbcFollowOn.hpp.
7.34.4.2 CoinPackedMatrix CbcFollowOn::matrixByRow_ [protected]
Matrix by row.
Definition at line 66 of file CbcFollowOn.hpp.
```

7.34.4.3 int* CbcFollowOn::rhs_ [protected]

Possible rhs (if 0 then not possible)

Definition at line 68 of file CbcFollowOn.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcFollowOn.hpp

7.35 CbcFullNodeInfo Class Reference

Information required to recreate the subproblem at this node.

#include <CbcFullNodeInfo.hpp>

Inheritance diagram for CbcFullNodeInfo:



Public Member Functions

 virtual void applyToModel (CbcModel *model, CoinWarmStartBasis *&basis, CbcCountRowCut **addCuts, int ¤tNumberCuts) const

Modify model according to information at node.

• virtual int applyBounds (int iColumn, double &lower, double &upper, int force)

Just apply bounds to one variable - force means overwrite by lower,upper (1=>infeasible)

• virtual CbcNodeInfo * buildRowBasis (CoinWarmStartBasis &basis) const

Builds up row basis backwards (until original model).

- CbcFullNodeInfo ()
- CbcFullNodeInfo (CbcModel *model, int numberRowsAtContinuous)

Constructor from continuous or satisfied.

- CbcFullNodeInfo (const CbcFullNodeInfo &)
- ∼CbcFullNodeInfo ()
- virtual CbcNodeInfo * clone () const

Clone

• const double * lower () const

Lower bounds.

• void setColLower (int sequence, double value)

Set a bound.

double * mutableLower () const

Mutable lower bounds.

const double * upper () const

Upper bounds.

void setColUpper (int sequence, double value)

Set a bound.

double * mutableUpper () const

Mutable upper bounds.

Protected Attributes

CoinWarmStartBasis * basis_

Full basis.

- int numberIntegers
- double * lower
- double * upper_

7.35.1 Detailed Description

Information required to recreate the subproblem at this node.

When a subproblem is initially created, it is represented by a CbcNode object and an attached CbcNodeInfo object.

The CbcNode contains information needed while the subproblem remains live. The CbcNode is deleted when the last branch arm has been evaluated.

The CbcNodeInfo contains information required to maintain the branch-and-cut search tree structure (links and reference counts) and to recreate the subproblem for this node (basis, variable bounds, cutting planes). A CbcNodeInfo object remains in existence until all nodes have been pruned from the subtree rooted at this node.

The principle used to maintain the reference count is that the reference count is always the sum of all potential and actual children of the node. Specifically,

- Once it's determined how the node will branch, the reference count is set to the number of potential children (*i.e.*, the number of arms of the branch).
- As each child is created by CbcNode::branch() (converting a potential child to the active subproblem), the reference count is decremented.
- If the child survives and will become a node in the search tree (converting the active subproblem into an actual child), increment the reference count.

Notice that the active subproblem lives in a sort of limbo, neither a potential or an actual node in the branch-and-cut tree

CbcNodeInfo objects come in two flavours. A CbcFullNodeInfo object contains a full record of the information required to recreate a subproblem. A CbcPartialNodeInfo object expresses this information in terms of differences from the parent.Holds complete information for recreating a subproblem.

A CbcFullNodeInfo object contains all necessary information (bounds, basis, and cuts) required to recreate a subproblem.

Todo While there's no explicit statement, the code often makes the implicit assumption that an CbcFullNodeInfo structure will appear only at the root node of the search tree. Things will break if this assumption is violated.

Definition at line 81 of file CbcFullNodeInfo.hpp.

- 7.35.2 Constructor & Destructor Documentation
- 7.35.2.1 CbcFullNodeInfo::CbcFullNodeInfo()
- 7.35.2.2 CbcFullNodeInfo::CbcFullNodeInfo (CbcModel * model, int numberRowsAtContinuous)

Constructor from continuous or satisfied.

```
7.35.2.3 CbcFullNodeInfo::CbcFullNodeInfo ( const CbcFullNodeInfo & )
7.35.2.4 CbcFullNodeInfo::~CbcFullNodeInfo()
7.35.3 Member Function Documentation
7.35.3.1 virtual void CbcFullNodeInfo::applyToModeI ( CbcModeI * model, CoinWarmStartBasis *& basis, CbcCountRowCut
         ** addCuts, int & currentNumberCuts ) const [virtual]
Modify model according to information at node.
The routine modifies the model according to bound information at node, creates a new basis according to information at
node, but with the size passed in through basis, and adds any cuts to the addCuts array.
Note
     The basis passed in via basis is solely a vehicle for passing in the desired basis size. It will be deleted and a new
     basis returned.
Implements CbcNodeInfo.
7.35.3.2 virtual int CbcFullNodeInfo::applyBounds (int iColumn, double & lower, double & upper, int force ) [virtual]
Just apply bounds to one variable - force means overwrite by lower,upper (1=>infeasible)
Implements CbcNodeInfo.
7.35.3.3 virtual CbcNodeInfo* CbcFullNodeInfo::buildRowBasis ( CoinWarmStartBasis & basis ) const [virtual]
Builds up row basis backwards (until original model).
Returns NULL or previous one to apply . Depends on Free being 0 and impossible for cuts
Implements CbcNodeInfo.
7.35.3.4 virtual CbcNodeInfo* CbcFullNodeInfo::clone() const [virtual]
Clone.
Implements CbcNodeInfo.
7.35.3.5 const double* CbcFullNodeInfo::lower( ) const [inline]
Lower bounds.
Definition at line 123 of file CbcFullNodeInfo.hpp.
7.35.3.6 void CbcFullNodeInfo::setColLower (int sequence, double value ) [inline]
Set a bound.
Definition at line 127 of file CbcFullNodeInfo.hpp.
7.35.3.7 double* CbcFullNodeInfo::mutableLower( ) const [inline]
```

Mutable lower bounds.

Definition at line 130 of file CbcFullNodeInfo.hpp.

7.35.3.8 const double* CbcFullNodeInfo::upper() const [inline]

Upper bounds.

Definition at line 134 of file CbcFullNodeInfo.hpp.

7.35.3.9 void CbcFullNodeInfo::setColUpper (int sequence, double value) [inline]

Set a bound.

Definition at line 138 of file CbcFullNodeInfo.hpp.

7.35.3.10 double* CbcFullNodeInfo::mutableUpper() const [inline]

Mutable upper bounds.

Definition at line 141 of file CbcFullNodeInfo.hpp.

7.35.4 Member Data Documentation

7.35.4.1 CoinWarmStartBasis* **CbcFullNodeInfo::basis**_ [protected]

Full basis.

This MUST BE A POINTER to avoid cutting extra information in derived warm start classes.

Definition at line 151 of file CbcFullNodeInfo.hpp.

7.35.4.2 int CbcFullNodeInfo::numberIntegers_ [protected]

Definition at line 152 of file CbcFullNodeInfo.hpp.

7.35.4.3 double* CbcFullNodeInfo::lower_ [protected]

Definition at line 154 of file CbcFullNodeInfo.hpp.

7.35.4.4 double* CbcFullNodeInfo::upper_ [protected]

Definition at line 155 of file CbcFullNodeInfo.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcFullNodeInfo.hpp

7.36 CbcGenCtlBlk Class Reference

#include <CbcGenCtlBlk.hpp>

Classes

struct babState_struct

State of branch-and-cut.

struct cbcParamsInfo_struct

Start and end of CbcModel parameters in parameter vector.

struct chooseStrongCtl_struct

Control variables for a strong branching method.

• struct debugSolInfo_struct

Array of primal variable values for debugging.

struct djFixCtl_struct

Control use of reduced cost fixing prior to B&C.

struct genParamsInfo_struct

Start and end of cbc-generic parameters in parameter vector.

struct osiParamsInfo_struct

Start and end of OsiSolverInterface parameters in parameter vector.

Public Types

Enumeration types used for cbc-generic control variables

```
enum IPPControl {
 IPPOff = 0, IPPOn, IPPSave, IPPEqual,
 IPPSOS, IPPTrySOS, IPPEqualAll, IPPStrategy }
     Codes to control integer preprocessing.
enum CGControl {
 CGOff, CGOn, CGRoot, CGIfMove,
 CGForceOn, CGForceBut, CGMarker }
     Codes to control the use of cut generators and heuristics.

    enum BPControl { BPOff, BPCost, BPOrder, BPExt }

     Codes to specify the assignment of branching priorities.
enum BACMajor {
 BACInvalid = -1, BACFinish = 0, BACStop = 1, BACAbandon = 2,
 BACNotRun, BACUser = 5 }
     Major status codes for branch-and-cut.
enum BACMinor {
 BACmInvalid = -1, BACmFinish = 0, BACmInfeas, BACmUbnd,
 BACmGap, BACmNodeLimit, BACmTimeLimit, BACmSolnLimit,
 BACmUser, BACmOther }
     Minor status codes.
• enum BACWhere {
 BACwInvalid = -1, BACwNotStarted = 0, BACwBareRoot, BACwIPP,
 BACwIPPRelax, BACwBAC }
     Codes to specify where branch-and-cut stopped.
```

Public Member Functions

Constructors and destructors

CbcGenCtlBlk ()
 Default constructor.
 ~CbcGenCtlBlk ()

Destructor.

Access and Control Functions for Cut Generators and Heuristics

Control functions, plus lazy creation functions for cut generators and heuristics

cbc-generic avoids creating objects for cut generators and heuristics unless they're actually used. For cut generators, a prototype is created and reused. For heuristics, the default is to create a new object with each call, because the

model may have changed. The object is returned through the reference parameter. The return value of the function is the current action state.

Cut generator and heuristic objects created by these calls will be deleted with the destruction of the CbcGenCtlBlk object.

• int getCutDepth ()

Get cut depth setting.

void setCutDepth (int cutDepth)

Set cut depth setting.

- IPPControl getIPPAction ()
- void setIPPAction (IPPControl action)

Set action state for use of integer preprocessing.

CGControl getProbing (CglCutGenerator *&gen)

Obtain a prototype for a probing cut generator.

void setProbingAction (CGControl action)

Set action state for use of probing cut generator.

CGControl getClique (CglCutGenerator *&gen)

Obtain a prototype for a clique cut generator.

void setCliqueAction (CGControl action)

Set action state for use of clique cut generator.

CGControl getFlow (CglCutGenerator *&gen)

Obtain a prototype for a flow cover cut generator.

void setFlowAction (CGControl action)

Set action state for use of flow cover cut generator.

CGControl getGomory (CglCutGenerator *&gen)

Obtain a prototype for a Gomory cut generator.

void setGomoryAction (CGControl action)

Set action state for use of Gomory cut generator.

CGControl getKnapsack (CglCutGenerator *&gen)

Obtain a prototype for a knapsack cover cut generator.

void setKnapsackAction (CGControl action)

Set action state for use of knapsack cut generator.

CGControl getMir (CglCutGenerator *&gen)

Obtain a prototype for a mixed integer rounding (MIR) cut generator.

void setMirAction (CGControl action)

Set action state for use of MIR cut generator.

CGControl getRedSplit (CglCutGenerator *&gen)

Obtain a prototype for a reduce and split cut generator.

void setRedSplitAction (CGControl action)

Set action state for use of reduce and split cut generator.

CGControl getTwomir (CglCutGenerator *&gen)

Obtain a prototype for a 2-MIR cut generator.

void setTwomirAction (CGControl action)

Set action state for use of 2-MIR cut generator.

• CGControl getFPump (CbcHeuristic *&gen, CbcModel *model, bool alwaysCreate=true)

Obtain a feasibility pump heuristic.

void setFPumpAction (CGControl action)

Set action state for use of feasibility pump heuristic.

CGControl getCombine (CbcHeuristic *&gen, CbcModel *model, bool alwaysCreate=true)

Obtain a local search/combine heuristic.

· void setCombineAction (CGControl action)

Set action state for use of local search/combine heuristic.

CGControl getGreedyCover (CbcHeuristic *&gen, CbcModel *model, bool alwaysCreate=true)

Obtain a greedy cover heuristic.

void setGreedyCoverAction (CGControl action)

Set action state for use of greedy cover heuristic.

CGControl getGreedyEquality (CbcHeuristic *&gen, CbcModel *model, bool alwaysCreate=true)

Obtain a greedy equality heuristic.

void setGreedyEqualityAction (CGControl action)

Set action state for use of greedy equality heuristic.

CGControl getRounding (CbcHeuristic *&gen, CbcModel *model, bool alwaysCreate=true)

Obtain a simple rounding heuristic.

void setRoundingAction (CGControl action)

Set action state for use of simple rounding heuristic.

CGControl getTreeLocal (CbcTreeLocal *&localTree, CbcModel *model, bool alwaysCreate=true)

Obtain a local search tree object.

void setTreeLocalAction (CGControl action)

Set action state for use of local tree.

Status Functions

Convenience routines for status codes.

 void setBaBStatus (BACMajor majorStatus, BACMinor minorStatus, BACWhere where, bool haveAnswer, Osi-SolverInterface *answerSolver)

Set the result of branch-and-cut search.

 void setBaBStatus (const CbcModel *model, BACWhere where, bool haveAnswer=false, OsiSolverInterface *answerSolver=0)

Set the result of branch-and-cut search.

BACMajor translateMajor (int status)

Translate CbcModel major status to BACMajor.

BACMinor translateMinor (int status)

Translate CbcModel minor status to BACMinor.

• BACMinor translateMinor (const OsiSolverInterface *osi)

Translate OsiSolverInterface status to BACMinor.

void printBaBStatus ()

Print the status block.

Public Attributes

Parameter parsing and input/output.

• std::string version_

cbc-generic version

std::string dfltDirectory_

Default directory prefix.

std::string lastMpsIn_

Last MPS input file.

bool allowImportErrors_

Allow/disallow errors when importing a model.

std::string lastSolnOut_

Last solution output file.

int printMode

Solution printing mode.

std::string printMask_

Print mask.

CoinParamVec * paramVec_

The parameter vector.

struct

CbcGenCtlBlk::genParamsInfo struct genParams

struct

CbcGenCtlBlk::cbcParamsInfo struct cbcParams

struct

CbcGenCtlBlk::osiParamsInfo struct osiParams

int verbose

Verbosity level for help messages.

int paramsProcessed_

Number of parameters processed.

std::vector< bool > setByUser_

Record of parameters changed by user command.

· bool defaultSettings_

False if the user has made nontrivial modifications to the default control settings.

std::string debugCreate_

Control debug file creation.

std::string debugFile_

Last debug input file.

struct

CbcGenCtlBlk::debugSolInfo_struct debugSol_

double totalTime

Total elapsed time for this run.

Models of various flavours

• CbcModel * model

The reference CbcModel object.

OsiSolverInterface * dfltSolver

The current default LP solver.

· bool goodModel_

True if we have a valid model loaded, false otherwise.

· struct

CbcGenCtlBlk::babState struct bab

Various algorithm control variables and settings

struct

CbcGenCtlBlk::djFixCtl_struct djFix_

BPControl priorityAction_

Control the assignment of branching priorities to integer variables.

Branching Method Control

Usage control and prototypes for branching methods.

Looking to the future, this covers only OsiChoose methods.

· struct

CbcGenCtlBlk::chooseStrongCtl_struct chooseStrong_

Friends

void CbcGenParamUtils::addCbcGenParams (int &numParams, CoinParamVec ¶mVec, CbcGenCtlBlk *ctl-Blk)

Messages and statistics

int printOpt

When greater than 0, integer presolve gives more information and branch-and-cut provides statistics.

CoinMessageHandler & message (CbcGenMsgCode inID)

Print a message.

void passInMessageHandler (CoinMessageHandler *handler)

Supply a new message handler.

CoinMessageHandler * messageHandler () const

Return a pointer to the message handler.

void setMessages (CoinMessages::Language lang=CoinMessages::us_en)

Set up messages in the specified language.

void setLogLevel (int lvl)

Set log level.

int logLevel () const

Get log level.

7.36.1 Detailed Description

Definition at line 67 of file CbcGenCtlBlk.hpp.

7.36.2 Member Enumeration Documentation

7.36.2.1 enum CbcGenCtlBlk::IPPControl

Codes to control integer preprocessing.

- IPPOff: Integer preprocessing is off.
- · IPPOn: Integer preprocessing is on.
- IPPSave: IPPOn, plus preprocessed system will be saved to presolved.mps.
- IPPEqual: IPPOn, plus '<=' cliques are converted to '=' cliques.
- IPPSOS: IPPOn, plus will create SOS sets (see below).
- IPPTrySOS: IPPOn, plus will create SOS sets (see below).
- IPPEqualAll: IPPOn, plus turns all valid inequalities into equalities with integer slacks.
- IPPStrategy: look to CbcStrategy object for instructions.

IPPSOS will create SOS sets if all binary variables (except perhaps one) can be covered by SOS sets with no overlap between sets. IPPTrySOS will allow any number of binary variables to be uncovered.

Enumerator

IPPOff

IPPOn

IPPSave

IPPEqual

IPPSOS
IPPTrySOS
IPPEqualAll
IPPStrategy

Definition at line 99 of file CbcGenCtlBlk.hpp.

7.36.2.2 enum CbcGenCtlBlk::CGControl

Codes to control the use of cut generators and heuristics.

- · CGOff: the cut generator will not be installed
- · CGOn: the cut generator will be installed; exactly how often it's activated depends on the settings at installation
- · CGRoot: the cut generator will be installed with settings that restrict it to activation at the root node only.
- CGIfMove: the cut generator will be installed with settings that allow it to remain active only so long as it's generating cuts that tighten the relaxation.
- CGForceOn: the cut generator will be installed with settings that force it to be called at every node
- CGForceBut: the cut generator will be installed with settings that force it to be called at every node, but more active at root (probing only)
- CGMarker: a convenience to mark the end of the codes.

The same codes are used for heuristics.

Enumerator

CGOff

CGOn

CGRoot

CGIfMove

CGForceOn

CGForceBut

CGMarker

Definition at line 129 of file CbcGenCtlBlk.hpp.

7.36.2.3 enum CbcGenCtlBlk::BPControl

Codes to specify the assignment of branching priorities.

- BPOff: no priorities are passed to cbc
- · BPCost: a priority vector is constructed based on objective coefficients
- · BPOrder: a priority vector is constructed based on column order
- BPExt: the user has provided a priority vector

Enumerator

BPOff

BPCost BPOrder BPExt

Definition at line 141 of file CbcGenCtlBlk.hpp.

7.36.2.4 enum CbcGenCtlBlk::BACMajor

Major status codes for branch-and-cut.

- · BACInvalid: status not yet set
- · BACNotRun: branch-and-cut has not yet run for the current problem
- · BACFinish: branch-and-cut has finished normally
- BACStop: branch-and-cut has stopped on a limit
- BACAbandon: branch-and-cut abandoned the problem
- · BACUser: branch-and-cut stopped on user signal

Consult minorStatus_ for details.

These codes are (mostly) set to match the codes used by CbcModel. Additions to CbcModel codes should be reflected here and in translateMajor.

Enumerator

BACInvalid

BACFinish

BACStop

BACAbandon

BACNotRun

BACUser

Definition at line 158 of file CbcGenCtlBlk.hpp.

7.36.2.5 enum CbcGenCtIBIk::BACMinor

Minor status codes.

- BACmInvalid status not yet set
- · BACmFinish search exhausted the tree; optimal solution found
- · BACmInfeas problem is infeasible
- BACmUbnd problem is unbounded
- · BACmGap stopped on integrality gap
- · BACmNodeLimit stopped on node limit
- · BACmTimeLimit stopped on time limit
- BACmSolnLimit stopped on number of solutions limit

- · BACmUser stopped due to user event
- · BACmOther nothing else is appropriate

It's not possible to make these codes agree with CbcModel. The meaning varies according to context: if the BACWhere code specifies a relaxation, then the minor status reflects the underlying OSI solver. Otherwise, it reflects the integer problem.

Enumerator

BACmInvalid

BACmFinish

BACmInfeas

BACmUbnd

BACmGap

BACmNodeLimit

BACmTimeLimit

BACmSoInLimit

BACmUser

BACmOther

Definition at line 181 of file CbcGenCtlBlk.hpp.

7.36.2.6 enum CbcGenCtlBlk::BACWhere

Codes to specify where branch-and-cut stopped.

- · BACwNotStarted stopped before we ever got going
- BACwBareRoot stopped after initial solve of root relaxation
- BACwIPP stopped after integer preprocessing
- BACwIPPRelax stopped after initial solve of preprocessed problem
- · BACwBAC stopped at some point in branch-and-cut

Enumerator

BACwInvalid

BACwNotStarted

BACwBareRoot

BACWIPP

BACwIPPRelax

BACWBAC

Definition at line 195 of file CbcGenCtlBlk.hpp.

7.36.3 Constructor & Destructor Documentation

7.36.3.1 CbcGenCtlBlk::CbcGenCtlBlk ()

Default constructor.

```
7.36.3.2 CbcGenCtlBlk::~CbcGenCtlBlk()
Destructor.
7.36.4 Member Function Documentation
7.36.4.1 int CbcGenCtlBlk::getCutDepth() [inline]
Get cut depth setting.
The name is a bit of a misnomer. Essentially, this overrides the 'every so many nodes' control with 'execute when (depth
in tree) mod (cut depth) == 0'.
Definition at line 236 of file CbcGenCtlBlk.hpp.
7.36.4.2 void CbcGenCtlBlk::setCutDepth (int cutDepth ) [inline]
Set cut depth setting.
See comments for getCutDepth().
Definition at line 245 of file CbcGenCtlBlk.hpp.
7.36.4.3 IPPControl CbcGenCtlBlk::getlPPAction() [inline]
Definition at line 251 of file CbcGenCtlBlk.hpp.
7.36.4.4 void CbcGenCtlBlk::setIPPAction ( IPPControl action ) [inline]
Set action state for use of integer preprocessing.
Definition at line 257 of file CbcGenCtlBlk.hpp.
7.36.4.5 CGControl CbcGenCtlBlk::getProbing ( CglCutGenerator *& gen )
Obtain a prototype for a probing cut generator.
7.36.4.6 void CbcGenCtlBlk::setProbingAction ( CGControl action ) [inline]
Set action state for use of probing cut generator.
Definition at line 267 of file CbcGenCtlBlk.hpp.
7.36.4.7 CGControl CbcGenCtlBlk::getClique ( CglCutGenerator *& gen )
Obtain a prototype for a clique cut generator.
7.36.4.8 void CbcGenCtlBlk::setCliqueAction ( CGControl action ) [inline]
Set action state for use of clique cut generator.
Definition at line 277 of file CbcGenCtlBlk.hpp.
7.36.4.9 CGControl CbcGenCtlBlk::getFlow ( CglCutGenerator *& gen )
Obtain a prototype for a flow cover cut generator.
7.36.4.10 void CbcGenCtlBlk::setFlowAction ( CGControl action ) [inline]
```

Set action state for use of flow cover cut generator.

Definition at line 287 of file CbcGenCtlBlk.hpp.

7.36.4.11 CGControl CbcGenCtlBlk::getGomory (CglCutGenerator *& gen)

Obtain a prototype for a Gomory cut generator.

7.36.4.12 void CbcGenCtlBlk::setGomoryAction (CGControl action) [inline]

Set action state for use of Gomory cut generator.

Definition at line 297 of file CbcGenCtlBlk.hpp.

7.36.4.13 CGControl CbcGenCtlBlk::getKnapsack (CglCutGenerator *& gen)

Obtain a prototype for a knapsack cover cut generator.

7.36.4.14 void CbcGenCtlBlk::setKnapsackAction (CGControl action) [inline]

Set action state for use of knapsack cut generator.

Definition at line 307 of file CbcGenCtlBlk.hpp.

7.36.4.15 CGControl CbcGenCtlBlk::getMir (CglCutGenerator *& gen)

Obtain a prototype for a mixed integer rounding (MIR) cut generator.

7.36.4.16 void CbcGenCtlBlk::setMirAction (CGControl action) [inline]

Set action state for use of MIR cut generator.

Definition at line 329 of file CbcGenCtlBlk.hpp.

7.36.4.17 CGControl CbcGenCtlBlk::getRedSplit (CglCutGenerator *& gen)

Obtain a prototype for a reduce and split cut generator.

7.36.4.18 void CbcGenCtlBlk::setRedSplitAction (CGControl action) [inline]

Set action state for use of reduce and split cut generator.

Definition at line 339 of file CbcGenCtlBlk.hpp.

7.36.4.19 CGControl CbcGenCtlBlk::getTwomir (CglCutGenerator *& gen)

Obtain a prototype for a 2-MIR cut generator.

7.36.4.20 void CbcGenCtlBlk::setTwomirAction (CGControl action) [inline]

Set action state for use of 2-MIR cut generator.

Definition at line 349 of file CbcGenCtlBlk.hpp.

7.36.4.21 CGControl CbcGenCtlBlk::getFPump (CbcHeuristic *& gen, CbcModel * model, bool alwaysCreate = true)

Obtain a feasibility pump heuristic.

By default, any existing object is deleted and a new object is created and loaded with model. Set alwaysCreate = false to return an existing object if one exists.

7.36.4.22 void CbcGenCtlBlk::setFPumpAction (CGControl action) [inline]

Set action state for use of feasibility pump heuristic.

Definition at line 366 of file CbcGenCtlBlk.hpp.

7.36.4.23 CGControl CbcGenCtlBlk::getCombine (CbcHeuristic *& gen, CbcModel * model, bool alwaysCreate = true)

Obtain a local search/combine heuristic.

By default, any existing object is deleted and a new object is created and loaded with model. Set alwaysCreate = false to return an existing object if one exists.

7.36.4.24 void CbcGenCtlBlk::setCombineAction (CGControl action) [inline]

Set action state for use of local search/combine heuristic.

Definition at line 382 of file CbcGenCtlBlk.hpp.

7.36.4.25 CGControl CbcGenCtlBlk::getGreedyCover (CbcHeuristic *& gen, CbcModel * model, bool alwaysCreate = true)

Obtain a greedy cover heuristic.

By default, any existing object is deleted and a new object is created and loaded with model. Set alwaysCreate = false to return an existing object if one exists.

7.36.4.26 void CbcGenCtlBlk::setGreedyCoverAction (CGControl action) [inline]

Set action state for use of greedy cover heuristic.

Definition at line 398 of file CbcGenCtlBlk.hpp.

7.36.4.27 CGControl CbcGenCtlBlk::getGreedyEquality (CbcHeuristic *& gen, CbcModel * model, bool alwaysCreate = true)

Obtain a greedy equality heuristic.

By default, any existing object is deleted and a new object is created and loaded with model. Set alwaysCreate = false to return an existing object if one exists.

 $\textbf{7.36.4.28} \quad \textbf{void CbcGenCtlBlk::setGreedyEqualityAction (\textbf{CGControl} \textit{ action} \textbf{)} \quad [\texttt{inline}]$

Set action state for use of greedy equality heuristic.

Definition at line 414 of file CbcGenCtlBlk.hpp.

7.36.4.29 CGControl CbcGenCtlBlk::getRounding (CbcHeuristic *& gen, CbcModel * model, bool alwaysCreate = true)

Obtain a simple rounding heuristic.

By default, any existing object is deleted and a new object is created and loaded with model. Set alwaysCreate = false to return an existing object if one exists.

7.36.4.30 void CbcGenCtlBlk::setRoundingAction (CGControl action) [inline]

Set action state for use of simple rounding heuristic.

Definition at line 430 of file CbcGenCtlBlk.hpp.

7.36.4.31 CGControl CbcGenCtiBik::getTreeLocal (CbcTreeLocal *& localTree, CbcModel * model, bool alwaysCreate = true)

Obtain a local search tree object.

By default, any existing object is deleted and a new object is created and loaded with model. Set alwaysCreate = false to return an existing object if one exists.

7.36.4.32 void CbcGenCtlBlk::setTreeLocalAction (CGControl action) [inline]

Set action state for use of local tree.

Definition at line 446 of file CbcGenCtlBlk.hpp.

7.36.4.33 void CbcGenCtlBlk::setBaBStatus (BACMajor majorStatus, BACMinor minorStatus, BACWhere where, bool haveAnswer, OsiSolverInterface * answerSolver) [inline]

Set the result of branch-and-cut search.

Definition at line 459 of file CbcGenCtlBlk.hpp.

7.36.4.34 void CbcGenCtlBlk::setBaBStatus (const CbcModel * model, BACWhere where, bool haveAnswer = false, OsiSolverInterface * answerSolver = 0)

Set the result of branch-and-cut search.

This version will extract the necessary information from the CbcModel object and set appropriate status based on the value passed for where.

7.36.4.35 BACMajor CbcGenCtlBlk::translateMajor (int status)

Translate CbcModel major status to BACMajor.

See the BACMajor enum for details.

7.36.4.36 BACMinor CbcGenCtlBlk::translateMinor (int status)

Translate CbcModel minor status to BACMinor.

See the BACMinor enum for details.

7.36.4.37 BACMinor CbcGenCtlBlk::translateMinor (const OsiSolverInterface * osi)

Translate OsiSolverInterface status to BACMinor.

See the BACMinor enum for details. Optimal, infeasible, and unbounded get their own codes; everything else maps to BACmOther.

7.36.4.38 void CbcGenCtlBlk::printBaBStatus ()

Print the status block.

7.36.4.39 CoinMessageHandler& CbcGenCtlBlk::message (CbcGenMsgCode inID)

Print a message.

Uses the current message handler and messages.

7.36.4.40 void CbcGenCtlBlk::passInMessageHandler (CoinMessageHandler * handler)

Supply a new message handler.

Replaces the current message handler. The current handler is destroyed if ourMsgHandler_ is true, and the call will set ourMsgHandler_ = true.

7.36.4.41 CoinMessageHandler* CbcGenCtlBlk::messageHandler() const [inline]

Return a pointer to the message handler.

Definition at line 520 of file CbcGenCtlBlk.hpp.

7.36.4.42 void CbcGenCtlBlk::setMessages (CoinMessages::Language lang = CoinMessages::us_en)

Set up messages in the specified language.

Building a set of messages in a given language implies rebuilding the whole set of messages, for reasons explained in the body of the code. Hence there's no separate setLanguage routine. Use this routine for the initial setup of messages and any subsequent change in language. Note that the constructor gives you a message handler by default, but *not* messages. You need to call setMessages explicitly.

The default value specified here for lang effectively sets the default language.

7.36.4.43 void CbcGenCtlBlk::setLogLevel(int /v/) [inline]

Set log level.

Definition at line 539 of file CbcGenCtlBlk.hpp.

7.36.4.44 int CbcGenCtlBlk::logLevel() const [inline]

Get log level.

Definition at line 545 of file CbcGenCtlBlk.hpp.

7.36.5 Friends And Related Function Documentation

7.36.5.1 void CbcGenParamUtils::addCbcGenParams (int & numParams, CoinParamVec & paramVec, CbcGenCtlBlk * ctlBlk) [friend]

7.36.6 Member Data Documentation

7.36.6.1 int CbcGenCtlBlk::printOpt_

When greater than 0, integer presolve gives more information and branch-and-cut provides statistics.

Definition at line 552 of file CbcGenCtlBlk.hpp.

7.36.6.2 std::string CbcGenCtlBlk::version_

cbc-generic version

Definition at line 560 of file CbcGenCtlBlk.hpp.

7.36.6.3 std::string CbcGenCtlBlk::dfltDirectory_

Default directory prefix.

Definition at line 564 of file CbcGenCtlBlk.hpp.

7.36.6.4 std::string CbcGenCtlBlk::lastMpsIn_

Last MPS input file.

Definition at line 568 of file CbcGenCtlBlk.hpp.

7.36.6.5 bool CbcGenCtlBlk::allowImportErrors_

Allow/disallow errors when importing a model.

Definition at line 571 of file CbcGenCtlBlk.hpp.

7.36.6.6 std::string CbcGenCtlBlk::lastSolnOut_

Last solution output file.

Definition at line 575 of file CbcGenCtlBlk.hpp.

7.36.6.7 int CbcGenCtlBlk::printMode_

Solution printing mode.

Controls the amount of information printed when printing a solution. Coding is set by the keyword declarations for the printingOptions command.

Definition at line 583 of file CbcGenCtlBlk.hpp.

7.36.6.8 std::string CbcGenCtlBlk::printMask

Print mask.

Used to specify row/column names to be printed. Not implemented as of 060920.

Definition at line 590 of file CbcGenCtlBlk.hpp.

7.36.6.9 CoinParamVec* CbcGenCtlBlk::paramVec_

The parameter vector.

Definition at line 594 of file CbcGenCtlBlk.hpp.

7.36.6.10 struct CbcGenCtlBlk::genParamsInfo_struct CbcGenCtlBlk::genParams_

7.36.6.11 struct CbcGenCtlBlk::cbcParamsInfo struct CbcGenCtlBlk::cbcParams

7.36.6.12 struct CbcGenCtIBIk::osiParamsInfo_struct CbcGenCtIBIk::osiParams_

7.36.6.13 int CbcGenCtlBlk::verbose_

Verbosity level for help messages.

Interpretation is bitwise:

- (0): short help
- (1): long help
- (2): unused (for compatibility with cbc; indicates AMPL)
- (3): show parameters with display = false.

Definition at line 628 of file CbcGenCtlBlk.hpp.

7.36.6.14 int CbcGenCtlBlk::paramsProcessed_

Number of parameters processed.

Definition at line 632 of file CbcGenCtlBlk.hpp.

7.36.6.15 std::vector<bool> CbcGenCtlBlk::setByUser_

Record of parameters changed by user command.

Definition at line 636 of file CbcGenCtlBlk.hpp.

7.36.6.16 bool CbcGenCtlBlk::defaultSettings_

False if the user has made nontrivial modifications to the default control settings.

Initially true. Specifying DJFIX, TIGHTENFACTOR, or any cut or heuristic parameter will set this to false.

Definition at line 644 of file CbcGenCtlBlk.hpp.

7.36.6.17 std::string CbcGenCtlBlk::debugCreate_

Control debug file creation.

At the conclusion of branch-and-cut, dump the full solution in a binary format to debug.file in the current directory. When set to "createAfterPre", the solution is dumped before integer presolve transforms are removed. When set to "create", the solution is dumped after integer presolve transforms are backed out.

Definition at line 654 of file CbcGenCtlBlk.hpp.

7.36.6.18 std::string CbcGenCtlBlk::debugFile_

Last debug input file.

The file is expected to be in a binary format understood by activateRowCutDebugger.

Definition at line 662 of file CbcGenCtlBlk.hpp.

7.36.6.19 struct CbcGenCtlBlk::debugSolInfo_struct CbcGenCtlBlk::debugSol_

7.36.6.20 double CbcGenCtlBlk::totalTime_

Total elapsed time for this run.

Definition at line 680 of file CbcGenCtlBlk.hpp.

7.36.6.21 CbcModel* CbcGenCtlBlk::model_

The reference CbcModel object.

This is the CbcModel created when cbc-generic boots up. It holds the default solver with the current constraint system. CbcCbcParam parameters are applied here, and CbcOsiParam parameters are applied to the solver. Major modifications for branch-and-cut (integer preprocessing, installation of heuristics and cut generators) are performed on a clone. The solution is transferred back into this object.

Definition at line 697 of file CbcGenCtlBlk.hpp.

7.36.6.22 OsiSolverInterface* CbcGenCtlBlk::dfltSolver

The current default LP solver.

This is a pointer to a reference copy. If you want the solver associated with model_, ask for it directly.

Definition at line 705 of file CbcGenCtlBlk.hpp.

7.36.6.23 bool CbcGenCtlBlk::goodModel_

True if we have a valid model loaded, false otherwise.

Definition at line 709 of file CbcGenCtlBlk.hpp.

7.36.6.24 struct CbcGenCtlBlk::babState_struct CbcGenCtlBlk::bab_

7.36.6.25 struct CbcGenCtlBlk::djFixCtl_struct CbcGenCtlBlk::djFix_

7.36.6.26 BPControl CbcGenCtlBlk::priorityAction_

Control the assignment of branching priorities to integer variables.

Definition at line 747 of file CbcGenCtlBlk.hpp.

7.36.6.27 struct CbcGenCtlBlk::chooseStrongCtl_struct CbcGenCtlBlk::chooseStrong_

The documentation for this class was generated from the following file:


• /home/ted/COIN/trunk/Cbc/src/CbcGenCtlBlk.hpp

7.37 CbcGeneral Class Reference

Define a catch all class.

#include <CbcGeneral.hpp>

Inheritance diagram for CbcGeneral:



Public Member Functions

- CbcGeneral ()
- CbcGeneral (CbcModel *model)

Useful constructor Just needs to point to model.

- CbcGeneral (const CbcGeneral &)
- virtual CbcObject * clone () const =0

Clone.

- CbcGeneral & operator= (const CbcGeneral &rhs)
- ∼CbcGeneral ()
- virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const Infeasibility - large is 0.5.
- virtual void feasibleRegion ()=0

This looks at solution and sets bounds to contain solution.

virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Creates a branching object.

virtual void redoSequenceEtc (CbcModel *model, int numberColumns, const int *originalColumns)=0
 Redoes data when sequence numbers change.

```
Additional Inherited Members
```

```
7.37.1 Detailed Description
```

Define a catch all class.

This will create a list of subproblems

Definition at line 17 of file CbcGeneral.hpp.

```
7.37.2 Constructor & Destructor Documentation
```

```
7.37.2.1 CbcGeneral::CbcGeneral ( )
```

```
7.37.2.2 CbcGeneral::CbcGeneral ( CbcModel * model )
```

Useful constructor Just needs to point to model.

```
7.37.2.3 CbcGeneral::CbcGeneral ( const CbcGeneral & )
```

```
7.37.2.4 CbcGeneral:: ∼CbcGeneral ( )
```

7.37.3 Member Function Documentation

```
7.37.3.1 virtual CbcObject* CbcGeneral::clone( ) const [pure virtual]
```

Clone.

Implements CbcObject.

```
7.37.3.2 CbcGeneral& CbcGeneral::operator= ( const CbcGeneral & rhs )
```

```
7.37.3.3 virtual double CbcGeneral::infeasibility ( const OsiBranchingInformation * info, int & preferredWay ) const [virtual]
```

Infeasibility - large is 0.5.

Reimplemented from CbcObject.

```
7.37.3.4 virtual void CbcGeneral::feasibleRegion() [pure virtual]
```

This looks at solution and sets bounds to contain solution.

Implements CbcObject.

```
7.37.3.5 virtual CbcBranchingObject* CbcGeneral::createCbcBranch ( OsiSolverInterface * solver, const OsiBranchingInformation * info, int way ) [virtual]
```

Creates a branching object.

Reimplemented from CbcObject.

7.37.3.6 virtual void CbcGeneral::redoSequenceEtc (CbcModel * model, int numberColumns, const int * originalColumns)

[pure virtual]

Redoes data when sequence numbers change.

Reimplemented from CbcObject.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcGeneral.hpp

7.38 CbcGenParam Class Reference

Class for cbc-generic control parameters.

#include <CbcGenParam.hpp>

Inheritance diagram for CbcGenParam:



Public Types

Subtypes

enum CbcGenParamCode { CBCGEN FIRSTPARAM = 0, GENERALQUERY, FULLGENERALQUERY, HELP, BAB, CLEARCUTS, CLIQUECUTS, COMBINE, COSTSTRATEGY, CPP, CUTDEPTH, CUTSTRATEGY, DEBUG, DIRECTORY, DJFIX, DUMMY, ERRORSALLOWED, EXIT, EXPORT, FLOWCUTS, FPUMP, FPUMPITS, GOMORYCUTS, GREEDY, HEURISTICSTRATEGY, IMPORT, INTPRINT, KNAPSACKCUTS, LOCALTREE, LOGLEVEL, MESSAGES, MIPLIB, MIXEDCUTS, ODDHOLECUTS, OUTDUPROWS, OUTPUTFORMAT, PREPROCESS, PRINTMASK, PRINTOPTIONS, PRINTVERSION, PRIORITYIN, PROBINGCUTS, REDSPLITCUTS, ROUNDING, SOLUTION, SOLVECONTINUOUS, SOLVER, SOS, STDIN, STRENGTHEN, TIGHTENFACTOR, TWOMIRCUTS, UNITTEST, USERCBC, USESOLUTION, VERBOSE, SHOWUNIMP, CBCGEN_LASTPARAM } Enumeration for cbc-generic parameters.

Constructors and Destructors

Public Member Functions

Be careful how you specify parameters for the constructors! There's great potential for confusion.

CbcGenParam ()

Default constructor.

CbcGenParam (CbcGenParamCode code, std::string name, std::string help, double lower, double upper, double dflt=0.0, bool display=true)

Constructor for a parameter with a double value.

CbcGenParam (CbcGenParamCode code, std::string name, std::string help, int lower, int upper, int dflt=0, bool display=true)

Constructor for a parameter with an integer value.

CbcGenParam (CbcGenParamCode code, std::string name, std::string help, std::string firstValue, int dflt, bool display=true)

Constructor for a parameter with keyword values.

- CbcGenParam (CbcGenParamCode code, std::string name, std::string help, std::string dflt, bool display=true)

 Constructor for a string parameter.
- CbcGenParam (CbcGenParamCode code, std::string name, std::string help, bool display=true)

Constructor for an action parameter.

CbcGenParam (const CbcGenParam &orig)

Copy constructor.

CbcGenParam * clone ()

Clone.

CbcGenParam & operator= (const CbcGenParam &rhs)

Assignment.

∼CbcGenParam ()

Destructor.

Methods to guery and manipulate a parameter object

• CbcGenParamCode paramCode () const

Get the parameter code.

void setParamCode (CbcGenParamCode code)

Set the parameter code.

• CbcGenCtlBlk * obj () const

Get the underlying cbc-generic control object.

void setObj (CbcGenCtlBlk *obj)

Set the underlying cbc-generic control object.

7.38.1 Detailed Description

Class for cbc-generic control parameters.

Adds parameter type codes and push/pull functions to the generic parameter object.

Definition at line 34 of file CbcGenParam.hpp.

7.38.2 Member Enumeration Documentation

7.38.2.1 enum CbcGenParam::CbcGenParamCode

Enumeration for cbc-generic parameters.

These are parameters that control the operation of the cbc-generic main program by operating on a CbcGenCtlBlk object. CBCGEN_FIRSTPARAM and CBCGEN_LASTPARM are markers to allow convenient separation of parameter groups.

Enumerator

CBCGEN_FIRSTPARAM

GENERALQUERY

FULLGENERALQUERY

HELP

BAB

CLEARCUTS

CLIQUECUTS

COMBINE

COSTSTRATEGY

CPP

CUTDEPTH

CUTSTRATEGY

DEBUG

DIRECTORY

DJFIX

DUMMY

ERRORSALLOWED

EXIT

EXPORT

FLOWCUTS

FPUMP

FPUMPITS

GOMORYCUTS

GREEDY

HEURISTICSTRATEGY

IMPORT

INTPRINT

KNAPSACKCUTS

LOCALTREE

LOGLEVEL

MESSAGES

MIPLIB

MIXEDCUTS

ODDHOLECUTS

OUTDUPROWS

OUTPUTFORMAT

PREPROCESS

PRINTMASK

PRINTOPTIONS

PRINTVERSION

PRIORITYIN

PROBINGCUTS

REDSPLITCUTS

ROUNDING

SOLUTION

SOLVECONTINUOUS

SOLVER

SOS

STDIN

STRENGTHEN

TIGHTENFACTOR

TWOMIRCUTS

UNITTEST

USERCBC

USESOLUTION

VERBOSE

SHOWUNIMP

CBCGEN_LASTPARAM

Definition at line 49 of file CbcGenParam.hpp.

7.38.3 Constructor & Destructor Documentation

7.38.3.1 CbcGenParam::CbcGenParam()

Default constructor.

7.38.3.2 CbcGenParam::CbcGenParam (CbcGenParamCode code, std::string name, std::string help, double lower, double upper, double dflt = 0.0, bool display = true)

Constructor for a parameter with a double value.

The default value is 0.0. Be careful to clearly indicate that lower and upper are real (double) values to distinguish this constructor from the constructor for an integer parameter.

7.38.3.3 CbcGenParam::CbcGenParam (CbcGenParamCode code, std::string name, std::string help, int lower, int upper, int dflt = 0, bool display = true)

Constructor for a parameter with an integer value.

The default value is 0.

7.38.3.4 CbcGenParam: CbcGenParam (CbcGenParamCode code, std::string name, std::string help, std::string firstValue, int dflt, bool display = true)

Constructor for a parameter with keyword values.

The string supplied as firstValue becomes the first keyword. Additional keywords can be added using append-Kwd(). Keywords are numbered from zero. It's necessary to specify both the first keyword (firstValue) and the default keyword index (dflt) in order to distinguish this constructor from the string and action parameter constructors.

7.38.3.5 CbcGenParam::CbcGenParam (CbcGenParamCode code, std::string name, std::string help, std::string dflt, bool display = true)

Constructor for a string parameter.

The default string value must be specified explicitly to distinguish a string constructor from an action parameter constructor.

7.38.3.6 CbcGenParam::CbcGenParam (CbcGenParamCode code, std::string name, std::string help, bool display = true)

Constructor for an action parameter.

7.38.3.7 CbcGenParam::CbcGenParam (const CbcGenParam & orig)

Copy constructor.

7.38.3.8 CbcGenParam:: ~CbcGenParam ()

Destructor.

7.38.4 Member Function Documentation

7.38.4.1 CbcGenParam * CbcGenParam::clone ()

Clone.

7.38.4.2 CbcGenParam& CbcGenParam::operator= (const CbcGenParam & rhs)

Assignment.

7.38.4.3 CbcGenParamCode CbcGenParam::paramCode()const [inline]

Get the parameter code.

Definition at line 148 of file CbcGenParam.hpp.

7.38.4.4 void CbcGenParam::setParamCode (CbcGenParamCode code) [inline]

Set the parameter code.

Definition at line 154 of file CbcGenParam.hpp.

7.38.4.5 CbcGenCtlBlk* CbcGenParam::obj() const [inline]

Get the underlying cbc-generic control object.

Definition at line 160 of file CbcGenParam.hpp.

7.38.4.6 void CbcGenParam::setObj (CbcGenCtlBlk * obj) [inline]

Set the underlying cbc-generic control object.

Definition at line 166 of file CbcGenParam.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcGenParam.hpp

7.39 CbcHeuristic Class Reference

Heuristic base class.

#include <CbcHeuristic.hpp>

Inheritance diagram for CbcHeuristic:



Public Member Functions

- CbcHeuristic ()
- CbcHeuristic (CbcModel &model)
- CbcHeuristic (const CbcHeuristic &)
- virtual ∼CbcHeuristic ()
- virtual CbcHeuristic * clone () const =0

Clone.

• CbcHeuristic & operator= (const CbcHeuristic &rhs)

Assignment operator.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

virtual void resetModel (CbcModel *model)=0

Resets stuff if model changes.

virtual int solution (double &objectiveValue, double *newSolution)=0

returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value This is called after cuts have been added - so can not add cuts

virtual int solution2 (double &, double *, OsiCuts &)

returns 0 if no solution, 1 if valid solution, -1 if just returning an estimate of best possible solution with better objective value than one passed in Sets solution values if good, sets objective value (only if nonzero code) This is called at same time as cut generators - so can add cuts Default is do nothing

virtual void validate ()

Validate model i.e. sets when to 0 if necessary (may be NULL)

void setWhen (int value)

Sets "when" flag - 0 off, 1 at root, 2 other than root, 3 always.

int when () const

Gets "when" flag - 0 off, 1 at root, 2 other than root, 3 always.

void setNumberNodes (int value)

Sets number of nodes in subtree (default 200)

• int numberNodes () const

Gets number of nodes in a subtree (default 200)

void setSwitches (int value)

Switches (does not apply equally to all heuristics) 1 bit - stop once allowable gap on objective reached 2 bit - always do given number of passes 4 bit - weaken cutoff by 5% every 50 passes? 8 bit - if has cutoff and suminf bobbling for 20 passes then first try halving distance to best possible then try keep halving distance to known cutoff 16 bit - needs new solution to run 1024 bit - stop all heuristics on max time.

· int switches () const

Switches (does not apply equally to all heuristics) 1 bit - stop once allowable gap on objective reached 2 bit - always do given number of passes 4 bit - weaken cutoff by 5% every 50 passes? 8 bit - if has cutoff and suminf bobbling for 20 passes then first try halving distance to best possible then try keep halving distance to known cutoff 16 bit - needs new solution to run 1024 bit - stop all heuristics on max time.

bool exitNow (double bestObjective) const

Whether to exit at once on gap.

· void setFeasibilityPumpOptions (int value)

Sets feasibility pump options (-1 is off)

int feasibilityPumpOptions () const

Gets feasibility pump options (-1 is off)

void setModelOnly (CbcModel *model)

Just set model - do not do anything else.

void setFractionSmall (double value)

Sets fraction of new(rows+columns)/old(rows+columns) before doing small branch and bound (default 1.0)

· double fractionSmall () const

Gets fraction of new(rows+columns)/old(rows+columns) before doing small branch and bound (default 1.0)

• int numberSolutionsFound () const

Get how many solutions the heuristic thought it got.

void incrementNumberSolutionsFound ()

Increment how many solutions the heuristic thought it got.

• int smallBranchAndBound (OsiSolverInterface *solver, int numberNodes, double *newSolution, double &new-SolutionValue, double cutoff, std::string name) const

Do mini branch and bound - return 0 not finished - no solution 1 not finished - solution 2 finished - no solution 3 finished - solution (could add global cut if finished) -1 returned on size -2 time or user event.

virtual void generateCpp (FILE *)

Create C++ lines to get to current state.

void generateCpp (FILE *fp, const char *heuristic)

Create C++ lines to get to current state - does work for base class.

virtual bool canDealWithOdd () const

Returns true if can deal with "odd" problems e.g. sos type 2.

• const char * heuristicName () const

return name of heuristic

void setHeuristicName (const char *name)

set name of heuristic

void setSeed (int value)

Set random number generator seed.

int getSeed () const

Get random number generator seed.

void setDecayFactor (double value)

Sets decay factor (for howOften) on failure.

void setInputSolution (const double *solution, double objValue)

Set input solution.

- void setWhereFrom (int value)
- · int whereFrom () const
- void setShallowDepth (int value)

Upto this depth we call the tree shallow and the heuristic can be called multiple times.

void setHowOftenShallow (int value)

How often to invoke the heuristics in the shallow part of the tree.

void setMinDistanceToRun (int value)

How "far" should this node be from every other where the heuristic was run in order to allow the heuristic to run in this node, too.

virtual bool shouldHeurRun (int whereFrom)

Check whether the heuristic should run at all 0 - before cuts at root node (or from doHeuristics) 1 - during cuts at root 2 - after root node cuts 3 - after cuts at other nodes 4 - during cuts at other nodes 8 added if previous heuristic in loop found solution.

• bool shouldHeurRun_randomChoice ()

Check whether the heuristic should run this time.

- void debugNodes ()
- void printDistanceToNodes ()
- int numRuns () const

how many times the heuristic has actually run

• int numCouldRun () const

How many times the heuristic could run.

OsiSolverInterface * cloneBut (int type)

Clone, but ...

Protected Attributes

• CbcModel * model

Model.

int when

When flag - 0 off, 1 at root, 2 other than root, 3 always.

int numberNodes

Number of nodes in any sub tree.

int feasibilityPumpOptions_

Feasibility pump options, -1 is off >=0 for feasibility pump itself -2 quick proximity search -3 longer proximity search.

double fractionSmall_

Fraction of new(rows+columns)/old(rows+columns) before doing small branch and bound.

CoinThreadRandom randomNumberGenerator_

Thread specific random number generator.

• std::string heuristicName_

Name for printing.

int howOften

How often to do (code can change)

double decayFactor_

How much to increase how often.

int switches

Switches (does not apply equally to all heuristics) 1 bit - stop once allowable gap on objective reached 2 bit - always do given number of passes 4 bit - weaken cutoff by 5% every 50 passes? 8 bit - if has cutoff and suminf bobbling for 20 passes then first try halving distance to best possible then try keep halving distance to known cutoff 16 bit - needs new solution to run 1024 bit - stop all heuristics on max time.

- int whereFrom
- int shallowDepth

Upto this depth we call the tree shallow and the heuristic can be called multiple times.

int howOftenShallow_

How often to invoke the heuristics in the shallow part of the tree.

int numInvocationsInShallow

How many invocations happened within the same node when in a shallow part of the tree.

int numInvocationsInDeep

How many invocations happened when in the deep part of the tree.

int lastRunDeep_

After how many deep invocations was the heuristic run last time.

int numRuns

how many times the heuristic has actually run

int minDistanceToRun

How "far" should this node be from every other where the heuristic was run in order to allow the heuristic to run in this node, too.

CbcHeuristicNodeList runNodes_

The description of the nodes where this heuristic has been applied.

int numCouldRun_

How many times the heuristic could run.

int numberSolutionsFound

How many solutions the heuristic thought it got.

int numberNodesDone

How many nodes the heuristic did this go.

double * inputSolution_

7.39.1 Detailed Description

Heuristic base class.

Definition at line 77 of file CbcHeuristic.hpp.

7.39.2 Constructor & Destructor Documentation

```
7.39.2.1 CbcHeuristic::CbcHeuristic ( )
```

7.39.2.2 CbcHeuristic::CbcHeuristic (CbcModel & model)

7.39.2.3 CbcHeuristic::CbcHeuristic (const CbcHeuristic &)

7.39.2.4 virtual CbcHeuristic::~CbcHeuristic() [virtual]

7.39.3 Member Function Documentation

7.39.3.1 virtual CbcHeuristic* CbcHeuristic::clone () const [pure virtual]

Clone.

Implemented in CbcHeuristicJustOne, CbcSerendipity, CbcHeuristicPartial, CbcRounding, CbcHeuristicDynamic3, CbcHeuristicCrossover, CbcHeuristicGreedySOS, CbcHeuristicNaive, CbcHeuristicGreedyEquality, CbcHeuristicProximity, CbcHeuristicDW, CbcHeuristicDive, CbcHeuristicRINS, CbcHeuristicVND, CbcHeuristicFPump, CbcHeuristicRENS, CbcHeuristicDINS, CbcHeuristicGreedyCover, CbcHeuristicLocal, CbcHeuristicPivotAndFix, CbcHeuristicRandRound, CbcHeuristicDiveCoefficient, CbcHeuristicDiveFractional, CbcHeuristicDiveGuided, CbcHeuristicDiveLineSearch, CbcHeuristicDivePseudoCost, and CbcHeuristicDiveVectorLength.

7.39.3.2 CbcHeuristic& CbcHeuristic::operator= (const CbcHeuristic & rhs)

Assignment operator.

```
7.39.3.3 virtual void CbcHeuristic::setModel ( CbcModel * model ) [virtual]
```

update model (This is needed if cliques update matrix etc)

Reimplemented in CbcHeuristicJustOne, CbcSerendipity, CbcHeuristicPartial, CbcRounding, CbcHeuristicDynamic3, CbcHeuristicCrossover, CbcHeuristicGreedySOS, CbcHeuristicNaive, CbcHeuristicGreedyEquality, CbcHeuristic-Proximity, CbcHeuristicDW, CbcHeuristicDive, CbcHeuristicRINS, CbcHeuristicVND, CbcHeuristicDINS, CbcHeuristic-RENS, CbcHeuristicLocal, CbcHeuristicPivotAndFix, CbcHeuristicRandRound, CbcHeuristicFPump, and CbcHeuristic-GreedyCover.

```
7.39.3.4 virtual void CbcHeuristic::resetModel ( CbcModel * model ) [pure virtual]
```

Resets stuff if model changes.

Implemented in CbcHeuristicJustOne, CbcSerendipity, CbcHeuristicPartial, CbcRounding, CbcHeuristicDynamic3, CbcHeuristicCrossover, CbcHeuristicGreedySOS, CbcHeuristicNaive, CbcHeuristicGreedyEquality, CbcHeuristicProximity, CbcHeuristicGreedyCover, CbcHeuristicDW, CbcHeuristicDive, CbcHeuristicRINS, CbcHeuristicVND, CbcHeuristicDINS, CbcHeuristicRENS, CbcHeuristicLocal, CbcHeuristicPivotAndFix, CbcHeuristicRandRound, and CbcHeuristicFPump.

```
7.39.3.5 virtual int CbcHeuristic::solution ( double & objective Value, double * new Solution ) [pure virtual]
```

returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value This is called after cuts have been added - so can not add cuts

Implemented in CbcHeuristicJustOne, CbcSerendipity, CbcHeuristicPartial, CbcRounding, CbcHeuristicDynamic3, CbcHeuristicCrossover, CbcHeuristicGreedySOS, CbcHeuristicNaive, CbcHeuristicGreedyEquality, CbcHeuristicProximity, CbcHeuristicFpump, CbcHeuristicDive, CbcHeuristicDW, CbcHeuristicLocal, CbcHeuristicRINS, CbcHeuristicVND, CbcHeuristicDINS, CbcHeuristicRENS, CbcHeuristicGreedyCover, CbcHeuristicPivotAndFix, and CbcHeuristicRandRound.

```
7.39.3.6 virtual int CbcHeuristic::solution2 (double &, double *, OsiCuts & ) [inline], [virtual]
```

returns 0 if no solution, 1 if valid solution, -1 if just returning an estimate of best possible solution with better objective value than one passed in Sets solution values if good, sets objective value (only if nonzero code) This is called at same time as cut generators - so can add cuts Default is do nothing

Definition at line 121 of file CbcHeuristic.hpp.

```
7.39.3.7 virtual void CbcHeuristic::validate() [inline], [virtual]
```

Validate model i.e. sets when to 0 if necessary (may be NULL)

Reimplemented in CbcHeuristicJustOne, CbcHeuristicPartial, CbcRounding, CbcHeuristicGreedySOS, CbcHeuristicGreedySos, CbcHeuristicGreedyCover.

Definition at line 128 of file CbcHeuristic.hpp.

```
7.39.3.8 void CbcHeuristic::setWhen (int value) [inline]
```

Sets "when" flag - 0 off, 1 at root, 2 other than root, 3 always.

If 10 added then don't worry if validate says there are funny objects as user knows it will be fine

Definition at line 134 of file CbcHeuristic.hpp.

```
7.39.3.9 int CbcHeuristic::when ( ) const [inline]
```

Gets "when" flag - 0 off, 1 at root, 2 other than root, 3 always.

Definition at line 138 of file CbcHeuristic.hpp.

```
7.39.3.10 void CbcHeuristic::setNumberNodes (int value) [inline]
```

Sets number of nodes in subtree (default 200)

Definition at line 143 of file CbcHeuristic.hpp.

```
7.39.3.11 int CbcHeuristic::numberNodes ( ) const [inline]
```

Gets number of nodes in a subtree (default 200)

Definition at line 147 of file CbcHeuristic.hpp.

```
7.39.3.12 void CbcHeuristic::setSwitches (int value) [inline]
```

Switches (does not apply equally to all heuristics) 1 bit - stop once allowable gap on objective reached 2 bit - always do given number of passes 4 bit - weaken cutoff by 5% every 50 passes? 8 bit - if has cutoff and suminf bobbling for 20 passes then first try halving distance to best possible then try keep halving distance to known cutoff 16 bit - needs new solution to run 1024 bit - stop all heuristics on max time.

Definition at line 160 of file CbcHeuristic.hpp.

```
7.39.3.13 int CbcHeuristic::switches ( ) const [inline]
```

Switches (does not apply equally to all heuristics) 1 bit - stop once allowable gap on objective reached 2 bit - always do given number of passes 4 bit - weaken cutoff by 5% every 50 passes? 8 bit - if has cutoff and suminf bobbling for 20 passes then first try halving distance to best possible then try keep halving distance to known cutoff 16 bit - needs new solution to run 1024 bit - stop all heuristics on max time.

Definition at line 173 of file CbcHeuristic.hpp.

7.39.3.14 bool CbcHeuristic::exitNow (double bestObjective) const

Whether to exit at once on gap.

7.39.3.15 void CbcHeuristic::setFeasibilityPumpOptions (int value) [inline]

Sets feasibility pump options (-1 is off)

Definition at line 179 of file CbcHeuristic.hpp.

7.39.3.16 int CbcHeuristic::feasibilityPumpOptions () const [inline]

Gets feasibility pump options (-1 is off)

Definition at line 183 of file CbcHeuristic.hpp.

7.39.3.17 void CbcHeuristic::setModelOnly (CbcModel * model) [inline]

Just set model - do not do anything else.

Definition at line 187 of file CbcHeuristic.hpp.

7.39.3.18 void CbcHeuristic::setFractionSmall (double value) [inline]

Sets fraction of new(rows+columns)/old(rows+columns) before doing small branch and bound (default 1.0)

Definition at line 193 of file CbcHeuristic.hpp.

7.39.3.19 double CbcHeuristic::fractionSmall () const [inline]

Gets fraction of new(rows+columns)/old(rows+columns) before doing small branch and bound (default 1.0)

Definition at line 197 of file CbcHeuristic.hpp.

7.39.3.20 int CbcHeuristic::numberSolutionsFound() const [inline]

Get how many solutions the heuristic thought it got.

Definition at line 201 of file CbcHeuristic.hpp.

7.39.3.21 void CbcHeuristic::incrementNumberSolutionsFound() [inline]

Increment how many solutions the heuristic thought it got.

Definition at line 205 of file CbcHeuristic.hpp.

7.39.3.22 int CbcHeuristic::smallBranchAndBound (OsiSolverInterface * solver, int numberNodes, double * newSolution, double & newSolutionValue, double cutoff, std::string name) const

Do mini branch and bound - return 0 not finished - no solution 1 not finished - solution 2 finished - no solution 3 finished - solution (could add global cut if finished) -1 returned on size -2 time or user event.

7.39.3.23 virtual void CbcHeuristic::generateCpp (FILE *) [inline], [virtual]

Create C++ lines to get to current state.

Reimplemented in CbcHeuristicJustOne, CbcSerendipity, CbcHeuristicPartial, CbcRounding, CbcHeuristicCrossover, CbcHeuristicGreedySOS, CbcHeuristicNaive, CbcHeuristicGreedyEquality, CbcHeuristicProximity, CbcHeuristicDW, CbcHeuristicDive, CbcHeuristicRINS, CbcHeuristicVND, CbcHeuristicDINS, CbcHeuristicLocal, CbcHeuristicPivot-AndFix, CbcHeuristicRandRound, CbcHeuristicDiveCoefficient, CbcHeuristicDiveFractional, CbcHeuristicDiveGuided, CbcHeuristicDiveLineSearch, CbcHeuristicDivePseudoCost, CbcHeuristicDiveVectorLength, CbcHeuristicFPump, and

CbcHeuristicGreedyCover.

```
Definition at line 222 of file CbcHeuristic.hpp.
```

7.39.3.24 void CbcHeuristic::generateCpp (FILE * fp, const char * heuristic)

Create C++ lines to get to current state - does work for base class.

7.39.3.25 virtual bool CbcHeuristic::canDealWithOdd() const [inline], [virtual]

Returns true if can deal with "odd" problems e.g. sos type 2.

Reimplemented in CbcHeuristicDynamic3.

Definition at line 226 of file CbcHeuristic.hpp.

7.39.3.26 const char* CbcHeuristic::heuristicName () const [inline]

return name of heuristic

Definition at line 230 of file CbcHeuristic.hpp.

7.39.3.27 void CbcHeuristic::setHeuristicName (const char * name) [inline]

set name of heuristic

Definition at line 234 of file CbcHeuristic.hpp.

7.39.3.28 void CbcHeuristic::setSeed (int value)

Set random number generator seed.

7.39.3.29 int CbcHeuristic::getSeed () const

Get random number generator seed.

7.39.3.30 void CbcHeuristic::setDecayFactor (double value) [inline]

Sets decay factor (for howOften) on failure.

Definition at line 242 of file CbcHeuristic.hpp.

7.39.3.31 void CbcHeuristic::setInputSolution (const double * solution, double objValue)

Set input solution.

7.39.3.32 void CbcHeuristic::setWhereFrom (int value) [inline]

Definition at line 255 of file CbcHeuristic.hpp.

7.39.3.33 int CbcHeuristic::whereFrom () const [inline]

Definition at line 258 of file CbcHeuristic.hpp.

7.39.3.34 void CbcHeuristic::setShallowDepth (int value) [inline]

Upto this depth we call the tree shallow and the heuristic can be called multiple times.

That is, the test whether the current node is far from the others where the jeuristic was invoked will not be done, only the frequency will be tested. After that depth the heuristic will can be invoked only once per node, right before branching. That's when it'll be tested whether the heur should run at all.

Definition at line 267 of file CbcHeuristic.hpp.

```
7.39.3.35 void CbcHeuristic::setHowOftenShallow (int value ) [inline]
```

How often to invoke the heuristics in the shallow part of the tree.

Definition at line 271 of file CbcHeuristic.hpp.

```
7.39.3.36 void CbcHeuristic::setMinDistanceToRun (int value) [inline]
```

How "far" should this node be from every other where the heuristic was run in order to allow the heuristic to run in this node, too.

Currently this is tested, but we may switch to avgDistanceToRun in the future.

Definition at line 277 of file CbcHeuristic.hpp.

```
7.39.3.37 virtual bool CbcHeuristic::shouldHeurRun ( int whereFrom ) [virtual]
```

Check whether the heuristic should run at all 0 - before cuts at root node (or from doHeuristics) 1 - during cuts at root 2 - after root node cuts 3 - after cuts at other nodes 4 - during cuts at other nodes 8 added if previous heuristic in loop found solution.

Reimplemented in CbcHeuristicPartial.

```
7.39.3.38 bool CbcHeuristic::shouldHeurRun_randomChoice ( )
```

Check whether the heuristic should run this time.

```
7.39.3.39 void CbcHeuristic::debugNodes ( )
```

7.39.3.40 void CbcHeuristic::printDistanceToNodes ()

```
7.39.3.41 int CbcHeuristic::numRuns ( ) const [inline]
```

how many times the heuristic has actually run

Definition at line 295 of file CbcHeuristic.hpp.

```
7.39.3.42 int CbcHeuristic::numCouldRun ( ) const [inline]
```

How many times the heuristic could run.

Definition at line 300 of file CbcHeuristic.hpp.

```
7.39.3.43 OsiSolverInterface* CbcHeuristic::cloneBut ( int type )
```

Clone, but ...

If type is

- 0 clone the solver for the model,
- 1 clone the continuous solver for the model
- · Add 2 to say without integer variables which are at low priority
- · Add 4 to say quite likely infeasible so give up easily (clp only).

7.39.4 Member Data Documentation

7.39.4.1 CbcModel* CbcHeuristic::model_ [protected]

Model.

Definition at line 315 of file CbcHeuristic.hpp.

7.39.4.2 int CbcHeuristic::when_ [protected]

When flag - 0 off, 1 at root, 2 other than root, 3 always.

Definition at line 317 of file CbcHeuristic.hpp.

7.39.4.3 int CbcHeuristic::numberNodes_ [protected]

Number of nodes in any sub tree.

Definition at line 319 of file CbcHeuristic.hpp.

7.39.4.4 int CbcHeuristic::feasibilityPumpOptions_ [protected]

Feasibility pump options, -1 is off >=0 for feasibility pump itself -2 quick proximity search -3 longer proximity search.

Definition at line 325 of file CbcHeuristic.hpp.

7.39.4.5 double CbcHeuristic::fractionSmall_ [mutable], [protected]

Fraction of new(rows+columns)/old(rows+columns) before doing small branch and bound.

Definition at line 327 of file CbcHeuristic.hpp.

7.39.4.6 CoinThreadRandom CbcHeuristic::randomNumberGenerator [protected]

Thread specific random number generator.

Definition at line 329 of file CbcHeuristic.hpp.

7.39.4.7 std::string CbcHeuristic::heuristicName [protected]

Name for printing.

Definition at line 331 of file CbcHeuristic.hpp.

7.39.4.8 int CbcHeuristic::howOften_ [mutable], [protected]

How often to do (code can change)

Definition at line 334 of file CbcHeuristic.hpp.

7.39.4.9 double CbcHeuristic::decayFactor [protected]

How much to increase how often.

Definition at line 336 of file CbcHeuristic.hpp.

7.39.4.10 int CbcHeuristic::switches_ [mutable], [protected]

Switches (does not apply equally to all heuristics) 1 bit - stop once allowable gap on objective reached 2 bit - always do given number of passes 4 bit - weaken cutoff by 5% every 50 passes? 8 bit - if has cutoff and suminf bobbling for 20 passes then first try halving distance to best possible then try keep halving distance to known cutoff 16 bit - needs new solution to run 1024 bit - stop all heuristics on max time.

Definition at line 347 of file CbcHeuristic.hpp.

```
7.39.4.11 int CbcHeuristic::whereFrom_ [protected]
```

Definition at line 356 of file CbcHeuristic.hpp.

```
7.39.4.12 int CbcHeuristic::shallowDepth_ [protected]
```

Upto this depth we call the tree shallow and the heuristic can be called multiple times.

That is, the test whether the current node is far from the others where the jeuristic was invoked will not be done, only the frequency will be tested. After that depth the heuristic will can be invoked only once per node, right before branching. That's when it'll be tested whether the heur should run at all.

Definition at line 363 of file CbcHeuristic.hpp.

```
7.39.4.13 int CbcHeuristic::howOftenShallow_ [protected]
```

How often to invoke the heuristics in the shallow part of the tree.

Definition at line 365 of file CbcHeuristic.hpp.

```
7.39.4.14 int CbcHeuristic::numInvocationsInShallow_ [protected]
```

How many invocations happened within the same node when in a shallow part of the tree.

Definition at line 368 of file CbcHeuristic.hpp.

```
7.39.4.15 int CbcHeuristic::numInvocationsInDeep_ [protected]
```

How many invocations happened when in the deep part of the tree.

For every node we count only one invocation.

Definition at line 371 of file CbcHeuristic.hpp.

```
7.39.4.16 int CbcHeuristic::lastRunDeep_ [protected]
```

After how many deep invocations was the heuristic run last time.

Definition at line 373 of file CbcHeuristic.hpp.

```
7.39.4.17 int CbcHeuristic::numRuns_ [protected]
```

how many times the heuristic has actually run

Definition at line 375 of file CbcHeuristic.hpp.

```
7.39.4.18 int CbcHeuristic::minDistanceToRun_ [protected]
```

How "far" should this node be from every other where the heuristic was run in order to allow the heuristic to run in this node, too.

Currently this is tested, but we may switch to avgDistanceToRun in the future.

Definition at line 379 of file CbcHeuristic.hpp.

```
7.39.4.19 CbcHeuristicNodeList CbcHeuristic::runNodes_ [protected]
```

The description of the nodes where this heuristic has been applied.

Definition at line 382 of file CbcHeuristic.hpp.

7.39.4.20 int CbcHeuristic::numCouldRun_ [protected]

How many times the heuristic could run.

Definition at line 385 of file CbcHeuristic.hpp.

7.39.4.21 int CbcHeuristic::numberSolutionsFound_ [protected]

How many solutions the heuristic thought it got.

Definition at line 388 of file CbcHeuristic.hpp.

7.39.4.22 int CbcHeuristic::numberNodesDone_ [mutable], [protected]

How many nodes the heuristic did this go.

Definition at line 391 of file CbcHeuristic.hpp.

7.39.4.23 double* CbcHeuristic::inputSolution_ [protected]

Definition at line 394 of file CbcHeuristic.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristic.hpp

7.40 CbcHeuristicCrossover Class Reference

Crossover Search class.

#include <CbcHeuristicLocal.hpp>

Inheritance diagram for CbcHeuristicCrossover:



Public Member Functions

- CbcHeuristicCrossover ()
- CbcHeuristicCrossover (CbcModel &model)
- CbcHeuristicCrossover (const CbcHeuristicCrossover &)
- ∼CbcHeuristicCrossover ()
- virtual CbcHeuristic * clone () const

Clone

• CbcHeuristicCrossover & operator= (const CbcHeuristicCrossover &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

```
    virtual void setModel (CbcModel *model)

          update model (This is needed if cliques update matrix etc)

    virtual int solution (double &objectiveValue, double *newSolution)

          returns 0 if no solution, 1 if valid solution.

    void setNumberSolutions (int value)

          Sets number of solutions to use.
Protected Attributes

    std::vector< double > attempts_

          Attempts.
    • double random_[10]
          Random numbers to stop same search happening.

    int numberSolutions_

          Number of solutions so we only do after new solution.
    int useNumber_
          Number of solutions to use.
7.40.1 Detailed Description
Crossover Search class.
Definition at line 211 of file CbcHeuristicLocal.hpp.
7.40.2 Constructor & Destructor Documentation
7.40.2.1 CbcHeuristicCrossover::CbcHeuristicCrossover()
7.40.2.2 CbcHeuristicCrossover::CbcHeuristicCrossover ( CbcModel & model )
7.40.2.3 CbcHeuristicCrossover::CbcHeuristicCrossover ( const CbcHeuristicCrossover & )
7.40.2.4 CbcHeuristicCrossover::~CbcHeuristicCrossover( )
7.40.3 Member Function Documentation
7.40.3.1 virtual CbcHeuristic* CbcHeuristicCrossover::clone( )const [virtual]
Clone.
Implements CbcHeuristic.
7.40.3.2 CbcHeuristicCrossover & CbcHeuristicCrossover & rhs )
Assignment operator.
7.40.3.3 virtual void CbcHeuristicCrossover::generateCpp (FILE * fp ) [virtual]
Create C++ lines to get to current state.
```

Reimplemented from CbcHeuristic.

 $\textbf{7.40.3.4} \quad \textbf{virtual void CbcHeuristicCrossover::} \textbf{resetModel (CbcModel} * \textit{model } \textbf{)} \quad [\texttt{virtual}]$

Resets stuff if model changes.

Implements CbcHeuristic.

7.40.3.5 virtual void CbcHeuristicCrossover::setModel (CbcModel * model) [virtual]

update model (This is needed if cliques update matrix etc)

Reimplemented from CbcHeuristic.

7.40.3.6 virtual int CbcHeuristicCrossover::solution (double & objectiveValue, double * newSolution) [virtual]

returns 0 if no solution, 1 if valid solution.

Fix variables if agree in useNumber_ solutions when_ 0 off, 1 only at new solutions, 2 also every now and then add 10 to make only if agree at lower bound

Implements CbcHeuristic.

7.40.3.7 void CbcHeuristicCrossover::setNumberSolutions (int value) [inline]

Sets number of solutions to use.

Definition at line 253 of file CbcHeuristicLocal.hpp.

7.40.4 Member Data Documentation

7.40.4.1 std::vector<double> CbcHeuristicCrossover::attempts_ [protected]

Attempts.

Definition at line 261 of file CbcHeuristicLocal.hpp.

7.40.4.2 double CbcHeuristicCrossover::random_[10] [protected]

Random numbers to stop same search happening.

Definition at line 263 of file CbcHeuristicLocal.hpp.

7.40.4.3 int CbcHeuristicCrossover::numberSolutions_ [protected]

Number of solutions so we only do after new solution.

Definition at line 265 of file CbcHeuristicLocal.hpp.

7.40.4.4 int CbcHeuristicCrossover::useNumber_ [protected]

Number of solutions to use.

Definition at line 267 of file CbcHeuristicLocal.hpp.


The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcHeuristicLocal.hpp

7.41 CbcHeuristicDINS Class Reference

#include <CbcHeuristicDINS.hpp>

Inheritance diagram for CbcHeuristicDINS:



Public Member Functions

- CbcHeuristicDINS ()
- · CbcHeuristicDINS (CbcModel &model)
- CbcHeuristicDINS (const CbcHeuristicDINS &)
- ∼CbcHeuristicDINS ()
- virtual CbcHeuristic * clone () const

Clone.

CbcHeuristicDINS & operator= (const CbcHeuristicDINS &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

• virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

• int solutionFix (double &objectiveValue, double *newSolution, const int *keep)

This version fixes stuff and does IP.

• void setHowOften (int value)

Sets how often to do it.

void setMaximumKeep (int value)

Sets maximum number of solutions kept.

void setConstraint (int value)

Sets tightness of extra constraint.

Protected Attributes

• int numberSolutions_

Number of solutions so we can do something at solution.

int howOften_

How often to do (code can change)

• int numberSuccesses_

Number of successes.

· int numberTries_

Number of tries.

int maximumKeepSolutions_

Maximum number of solutions to keep.

```
· int numberKeptSolutions_
          Number of solutions kept.
    · int numberIntegers_
          Number of integer variables.
    · int localSpace_
          Local parameter.
    int ** values_
          Values of integer variables.
7.41.1 Detailed Description
Definition at line 14 of file CbcHeuristicDINS.hpp.
7.41.2 Constructor & Destructor Documentation
7.41.2.1 CbcHeuristicDINS::CbcHeuristicDINS()
7.41.2.2 CbcHeuristicDINS::CbcHeuristicDINS ( CbcModel & model )
7.41.2.3 CbcHeuristicDINS::CbcHeuristicDINS ( const CbcHeuristicDINS & )
7.41.2.4 CbcHeuristicDINS::~CbcHeuristicDINS()
7.41.3 Member Function Documentation
7.41.3.1 virtual CbcHeuristic* CbcHeuristicDINS::clone( ) const [virtual]
Clone.
Implements CbcHeuristic.
7.41.3.2 CbcHeuristicDINS& CbcHeuristicDINS::operator= ( const CbcHeuristicDINS & rhs )
Assignment operator.
7.41.3.3 virtual void CbcHeuristicDINS::generateCpp (FILE * fp ) [virtual]
Create C++ lines to get to current state.
Reimplemented from CbcHeuristic.
7.41.3.4 virtual void CbcHeuristicDINS::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.41.3.5 virtual void CbcHeuristicDINS::setModel ( CbcModel * model ) [virtual]
update model (This is needed if cliques update matrix etc)
Reimplemented from CbcHeuristic.
7.41.3.6 virtual int CbcHeuristicDINS::solution ( double & objectiveValue, double * newSolution ) [virtual]
returns 0 if no solution, 1 if valid solution.
```

Sets solution values if good, sets objective value (only if good) This does Relaxation Induced Neighborhood Search Implements CbcHeuristic.

7.41.3.7 int CbcHeuristicDINS::solutionFix (double & objectiveValue, double * newSolution, const int * keep)

This version fixes stuff and does IP.

7.41.3.8 void CbcHeuristicDINS::setHowOften (int value) [inline]

Sets how often to do it.

Definition at line 60 of file CbcHeuristicDINS.hpp.

7.41.3.9 void CbcHeuristicDINS::setMaximumKeep (int value) [inline]

Sets maximum number of solutions kept.

Definition at line 64 of file CbcHeuristicDINS.hpp.

7.41.3.10 void CbcHeuristicDINS::setConstraint (int value) [inline]

Sets tightness of extra constraint.

Definition at line 68 of file CbcHeuristicDINS.hpp.

7.41.4 Member Data Documentation

7.41.4.1 int CbcHeuristicDINS::numberSolutions_ [protected]

Number of solutions so we can do something at solution.

Definition at line 76 of file CbcHeuristicDINS.hpp.

7.41.4.2 int CbcHeuristicDINS::howOften_ [protected]

How often to do (code can change)

Definition at line 78 of file CbcHeuristicDINS.hpp.

7.41.4.3 int CbcHeuristicDINS::numberSuccesses_ [protected]

Number of successes.

Definition at line 80 of file CbcHeuristicDINS.hpp.

7.41.4.4 int CbcHeuristicDINS::numberTries_ [protected]

Number of tries.

Definition at line 82 of file CbcHeuristicDINS.hpp.

7.41.4.5 int CbcHeuristicDINS::maximumKeepSolutions_ [protected]

Maximum number of solutions to keep.

Definition at line 84 of file CbcHeuristicDINS.hpp.

7.41.4.6 int CbcHeuristicDINS::numberKeptSolutions_ [protected]

Number of solutions kept.

Definition at line 86 of file CbcHeuristicDINS.hpp.

7.41.4.7 int CbcHeuristicDINS::numberIntegers_ [protected]

Number of integer variables.

Definition at line 88 of file CbcHeuristicDINS.hpp.

7.41.4.8 int CbcHeuristicDINS::localSpace_ [protected]

Local parameter.

Definition at line 90 of file CbcHeuristicDINS.hpp.

7.41.4.9 int** CbcHeuristicDINS::values_ [protected]

Values of integer variables.

Definition at line 92 of file CbcHeuristicDINS.hpp.

The documentation for this class was generated from the following file:

• /home/ted/COIN/trunk/Cbc/src/CbcHeuristicDINS.hpp

7.42 CbcHeuristicDive Class Reference

Dive class.

#include <CbcHeuristicDive.hpp>

Inheritance diagram for CbcHeuristicDive:



Public Member Functions

- CbcHeuristicDive ()
- CbcHeuristicDive (CbcModel &model)
- CbcHeuristicDive (const CbcHeuristicDive &)
- ∼CbcHeuristicDive ()
- virtual CbcHeuristicDive * clone () const =0

Clone.

CbcHeuristicDive & operator= (const CbcHeuristicDive &rhs)

Assignment operator.

virtual void generateCpp (FILE *)

Create C++ lines to get to current state.

void generateCpp (FILE *fp, const char *heuristic)

Create C++ lines to get to current state - does work for base class.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value (only if good) This is called after cuts have been added - so can not add cuts This does Fractional Diving

 int solution (double &objectiveValue, int &numberNodes, int &numberCuts, OsiRowCut **cuts, CbcSubProblem **&nodes, double *newSolution)

inner part of dive

int fathom (CbcModel *model, int &numberNodes, CbcSubProblem **&nodes)

returns 0 if no solution, 1 if valid solution with better objective value than one passed in also returns list of nodes This does Fractional Diving

virtual void validate ()

Validate model i.e. sets when to 0 if necessary (may be NULL)

· void selectBinaryVariables ()

Select candidate binary variables for fixing.

void setPercentageToFix (double value)

Set percentage of integer variables to fix at bounds.

void setMaxIterations (int value)

Set maximum number of iterations.

void setMaxSimplexIterations (int value)

Set maximum number of simplex iterations.

int maxSimplexIterations () const

Get maximum number of simplex iterations.

void setMaxSimplexIterationsAtRoot (int value)

Set maximum number of simplex iterations at root node.

void setMaxTime (double value)

Set maximum time allowed.

• virtual bool canHeuristicRun ()

Tests if the heuristic can run.

virtual bool selectVariableToBranch (OsiSolverInterface *solver, const double *newSolution, int &bestColumn, int &bestRound)=0

Selects the next variable to branch on Returns true if all the fractional variables can be trivially rounded.

virtual void initializeData ()

Initializes any data which is going to be used repeatedly in selectVariableToBranch.

int reducedCostFix (OsiSolverInterface *solver)

Perform reduced cost fixing on integer variables.

virtual int fixOtherVariables (OsiSolverInterface *solver, const double *solution, PseudoReducedCost *candidate, const double *random)

Fix other variables at bounds.

Protected Attributes

- CoinPackedMatrix matrix_
- CoinPackedMatrix matrixByRow
- unsigned short * downLocks_
- unsigned short * upLocks_
- double * downArray

Extra down array (number Integers long)

double * upArray

Extra up array (number Integers long)

- std::vector< int > binVarIndex_
- std::vector< int > vbRowIndex_
- double percentageToFix_
- int maxIterations
- int maxSimplexIterations
- int maxSimplexIterationsAtRoot
- double maxTime

7.42.1 Detailed Description

Dive class.

Definition at line 21 of file CbcHeuristicDive.hpp.

- 7.42.2 Constructor & Destructor Documentation
- 7.42.2.1 CbcHeuristicDive::CbcHeuristicDive ()
- 7.42.2.2 CbcHeuristicDive::CbcHeuristicDive (CbcModel & model)
- 7.42.2.3 CbcHeuristicDive::CbcHeuristicDive (const CbcHeuristicDive &)
- 7.42.2.4 CbcHeuristicDive::~CbcHeuristicDive()
- 7.42.3 Member Function Documentation
- 7.42.3.1 virtual CbcHeuristicDive* CbcHeuristicDive::clone() const [pure virtual]

Clone.

Implements CbcHeuristic.

Implemented in CbcHeuristicDiveCoefficient, CbcHeuristicDiveFractional, CbcHeuristicDiveGuided, CbcHeuristicDiveLineSearch, CbcHeuristicDivePseudoCost, and CbcHeuristicDiveVectorLength.

7.42.3.2 CbcHeuristicDive& CbcHeuristicDive::operator= (const CbcHeuristicDive & rhs)

Assignment operator.

```
7.42.3.3 virtual void CbcHeuristicDive::generateCpp ( FILE * ) [inline], [virtual]
```

Create C++ lines to get to current state.

Reimplemented from CbcHeuristic.

Reimplemented in CbcHeuristicDiveCoefficient, CbcHeuristicDiveFractional, CbcHeuristicDiveGuided, CbcHeuristicDiveLineSearch, CbcHeuristicDivePseudoCost, and CbcHeuristicDiveVectorLength.

Definition at line 43 of file CbcHeuristicDive.hpp.

7.42.3.4 void CbcHeuristicDive::generateCpp (FILE * fp, const char * heuristic)

Create C++ lines to get to current state - does work for base class.

```
7.42.3.5 virtual void CbcHeuristicDive::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.42.3.6 virtual void CbcHeuristicDive::setModel ( CbcModel * model ) [virtual]
update model (This is needed if cliques update matrix etc)
Reimplemented from CbcHeuristic.
7.42.3.7 virtual int CbcHeuristicDive::solution ( double & objectiveValue, double * newSolution ) [virtual]
returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets
objective value (only if good) This is called after cuts have been added - so can not add cuts This does Fractional Diving
Implements CbcHeuristic.
7.42.3.8 int CbcHeuristicDive::solution ( double & objectiveValue, int & numberNodes, int & numberCuts, OsiRowCut ** cuts,
         CbcSubProblem **& nodes, double * newSolution )
inner part of dive
7.42.3.9 int CbcHeuristicDive::fathom ( CbcModel * model, int & numberNodes, CbcSubProblem **& nodes )
returns 0 if no solution, 1 if valid solution with better objective value than one passed in also returns list of nodes This
does Fractional Diving
7.42.3.10 virtual void CbcHeuristicDive::validate() [virtual]
Validate model i.e. sets when to 0 if necessary (may be NULL)
Reimplemented from CbcHeuristic.
7.42.3.11 void CbcHeuristicDive::selectBinaryVariables ( )
Select candidate binary variables for fixing.
7.42.3.12 void CbcHeuristicDive::setPercentageToFix ( double value ) [inline]
Set percentage of integer variables to fix at bounds.
Definition at line 82 of file CbcHeuristicDive.hpp.
7.42.3.13 void CbcHeuristicDive::setMaxIterations (int value) [inline]
Set maximum number of iterations.
Definition at line 87 of file CbcHeuristicDive.hpp.
7.42.3.14 void CbcHeuristicDive::setMaxSimplexIterations (int value) [inline]
Set maximum number of simplex iterations.
Definition at line 92 of file CbcHeuristicDive.hpp.
7.42.3.15 int CbcHeuristicDive::maxSimplexIterations ( ) const [inline]
Get maximum number of simplex iterations.
```

Definition at line 96 of file CbcHeuristicDive.hpp.

7.42.3.16 void CbcHeuristicDive::setMaxSimplexIterationsAtRoot (int value) [inline]

Set maximum number of simplex iterations at root node.

Definition at line 101 of file CbcHeuristicDive.hpp.

7.42.3.17 void CbcHeuristicDive::setMaxTime (double value) [inline]

Set maximum time allowed.

Definition at line 106 of file CbcHeuristicDive.hpp.

7.42.3.18 virtual bool CbcHeuristicDive::canHeuristicRun() [virtual]

Tests if the heuristic can run.

Reimplemented in CbcHeuristicDiveGuided.

7.42.3.19 virtual bool CbcHeuristicDive::selectVariableToBranch (OsiSolverInterface * solver, const double * newSolution, int & bestColumn, int & bestRound) [pure virtual]

Selects the next variable to branch on Returns true if all the fractional variables can be trivially rounded.

Returns false, if there is at least one fractional variable that is not trivially roundable. In this case, the bestColumn returned will not be trivially roundable.

Implemented in CbcHeuristicDiveGuided, CbcHeuristicDiveCoefficient, CbcHeuristicDiveFractional, CbcHeuristicDiveLineSearch, CbcHeuristicDivePseudoCost, and CbcHeuristicDiveVectorLength.

7.42.3.20 virtual void CbcHeuristicDive::initializeData() [inline], [virtual]

Initializes any data which is going to be used repeatedly in selectVariableToBranch.

Reimplemented in CbcHeuristicDivePseudoCost.

Definition at line 125 of file CbcHeuristicDive.hpp.

7.42.3.21 int CbcHeuristicDive::reducedCostFix (OsiSolverInterface * solver)

Perform reduced cost fixing on integer variables.

7.42.3.22 virtual int CbcHeuristicDive::fixOtherVariables (OsiSolverInterface * solver, const double * solution, PseudoReducedCost * candidate, const double * random) [virtual]

Fix other variables at bounds.

Reimplemented in CbcHeuristicDivePseudoCost.

7.42.4 Member Data Documentation

7.42.4.1 CoinPackedMatrix CbcHeuristicDive::matrix [protected]

Definition at line 139 of file CbcHeuristicDive.hpp.

7.42.4.2 CoinPackedMatrix CbcHeuristicDive::matrixByRow_ [protected]

Definition at line 142 of file CbcHeuristicDive.hpp.

7.42.4.3 unsigned short* CbcHeuristicDive::downLocks_ [protected]

Definition at line 145 of file CbcHeuristicDive.hpp.

7.42.4.4 unsigned short* CbcHeuristicDive::upLocks_ [protected]

Definition at line 148 of file CbcHeuristicDive.hpp.

7.42.4.5 double* CbcHeuristicDive::downArray_ [protected]

Extra down array (number Integers long)

Definition at line 151 of file CbcHeuristicDive.hpp.

7.42.4.6 double* CbcHeuristicDive::upArray_ [protected]

Extra up array (number Integers long)

Definition at line 154 of file CbcHeuristicDive.hpp.

7.42.4.7 std::vector<int> CbcHeuristicDive::binVarIndex_ [protected]

Definition at line 158 of file CbcHeuristicDive.hpp.

7.42.4.8 std::vector<int> CbcHeuristicDive::vbRowIndex_ [protected]

Definition at line 161 of file CbcHeuristicDive.hpp.

7.42.4.9 double CbcHeuristicDive::percentageToFix [protected]

Definition at line 164 of file CbcHeuristicDive.hpp.

7.42.4.10 int CbcHeuristicDive::maxIterations_ [protected]

Definition at line 167 of file CbcHeuristicDive.hpp.

7.42.4.11 int CbcHeuristicDive::maxSimplexIterations_ [protected]

Definition at line 170 of file CbcHeuristicDive.hpp.

7.42.4.12 int CbcHeuristicDive::maxSimplexIterationsAtRoot_ [protected]

Definition at line 173 of file CbcHeuristicDive.hpp.

7.42.4.13 double CbcHeuristicDive::maxTime [protected]

Definition at line 176 of file CbcHeuristicDive.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDive.hpp

7.43 CbcHeuristicDiveCoefficient Class Reference

DiveCoefficient class.

#include <CbcHeuristicDiveCoefficient.hpp>

Inheritance diagram for CbcHeuristicDiveCoefficient:



Public Member Functions

- CbcHeuristicDiveCoefficient ()
- CbcHeuristicDiveCoefficient (CbcModel &model)
- CbcHeuristicDiveCoefficient (const CbcHeuristicDiveCoefficient &)
- ∼CbcHeuristicDiveCoefficient ()
- · virtual

CbcHeuristicDiveCoefficient * clone () const

Clone.

CbcHeuristicDiveCoefficient & operator= (const CbcHeuristicDiveCoefficient &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

 virtual bool selectVariableToBranch (OsiSolverInterface *solver, const double *newSolution, int &bestColumn, int &bestRound)

Selects the next variable to branch on.

Additional Inherited Members

7.43.1 Detailed Description

DiveCoefficient class.

Definition at line 14 of file CbcHeuristicDiveCoefficient.hpp.

- 7.43.2 Constructor & Destructor Documentation
- 7.43.2.1 CbcHeuristicDiveCoefficient::CbcHeuristicDiveCoefficient ()
- 7.43.2.2 CbcHeuristicDiveCoefficient::CbcHeuristicDiveCoefficient (CbcModel & model)
- 7.43.2.3 CbcHeuristicDiveCoefficient::CbcHeuristicDiveCoefficient (const CbcHeuristicDiveCoefficient &)
- 7.43.2.4 CbcHeuristicDiveCoefficient::~CbcHeuristicDiveCoefficient()
- 7.43.3 Member Function Documentation
- 7.43.3.1 virtual CbcHeuristicDiveCoefficient* CbcHeuristicDiveCoefficient::clone() const [virtual]

Clone.

Implements CbcHeuristicDive.

7.43.3.2 CbcHeuristicDiveCoefficient& CbcHeuristicDiveCoefficient::operator= (const CbcHeuristicDiveCoefficient & rhs)

Assignment operator.

7.43.3.3 virtual void CbcHeuristicDiveCoefficient::generateCpp (FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristicDive.

7.43.3.4 virtual bool CbcHeuristicDiveCoefficient::selectVariableToBranch (OsiSolverInterface * solver, const double * newSolution, int & bestColumn, int & bestRound) [virtual]

Selects the next variable to branch on.

Returns true if all the fractional variables can be trivially rounded. Returns false, if there is at least one fractional variable that is not trivially roundable. In this case, the bestColumn returned will not be trivially roundable.

Implements CbcHeuristicDive.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveCoefficient.hpp

7.44 CbcHeuristicDiveFractional Class Reference

DiveFractional class.

#include <CbcHeuristicDiveFractional.hpp>

Inheritance diagram for CbcHeuristicDiveFractional:



Public Member Functions

- CbcHeuristicDiveFractional ()
- CbcHeuristicDiveFractional (CbcModel &model)
- CbcHeuristicDiveFractional (const CbcHeuristicDiveFractional &)
- ∼CbcHeuristicDiveFractional ()
- virtual

CbcHeuristicDiveFractional * clone () const

Clone.

• CbcHeuristicDiveFractional & operator= (const CbcHeuristicDiveFractional &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual bool selectVariableToBranch (OsiSolverInterface *solver, const double *newSolution, int &bestColumn, int &bestRound)

Selects the next variable to branch on.

Additional Inherited Members

7.44.1 Detailed Description

DiveFractional class.

Definition at line 14 of file CbcHeuristicDiveFractional.hpp.

- 7.44.2 Constructor & Destructor Documentation
- 7.44.2.1 CbcHeuristicDiveFractional::CbcHeuristicDiveFractional ()
- 7.44.2.2 CbcHeuristicDiveFractional::CbcHeuristicDiveFractional (CbcModel & model)
- 7.44.2.3 CbcHeuristicDiveFractional::CbcHeuristicDiveFractional (const CbcHeuristicDiveFractional &)
- 7.44.2.4 CbcHeuristicDiveFractional:: ~ CbcHeuristicDiveFractional ()
- 7.44.3 Member Function Documentation
- 7.44.3.1 virtual CbcHeuristicDiveFractional* CbcHeuristicDiveFractional::clone() const [virtual]

Clone.

Implements CbcHeuristicDive.

7.44.3.2 CbcHeuristicDiveFractional& CbcHeuristicDiveFractional::operator=(const CbcHeuristicDiveFractional& rhs)

Assignment operator.

7.44.3.3 virtual void CbcHeuristicDiveFractional::generateCpp(FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristicDive.

7.44.3.4 virtual bool CbcHeuristicDiveFractional::selectVariableToBranch (OsiSolverInterface * solver, const double * newSolution, int & bestColumn, int & bestRound) [virtual]

Selects the next variable to branch on.

Returns true if all the fractional variables can be trivially rounded. Returns false, if there is at least one fractional variable that is not trivially roundable. In this case, the bestColumn returned will not be trivially roundable.

Implements CbcHeuristicDive.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveFractional.hpp

7.45 CbcHeuristicDiveGuided Class Reference

DiveGuided class.

#include <CbcHeuristicDiveGuided.hpp>

Inheritance diagram for CbcHeuristicDiveGuided:



Public Member Functions

- CbcHeuristicDiveGuided ()
- CbcHeuristicDiveGuided (CbcModel &model)
- CbcHeuristicDiveGuided (const CbcHeuristicDiveGuided &)
- ∼CbcHeuristicDiveGuided ()
- virtual CbcHeuristicDiveGuided * clone () const

Clone

• CbcHeuristicDiveGuided & operator= (const CbcHeuristicDiveGuided &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual bool canHeuristicRun ()

Tests if the heuristic can run.

virtual bool selectVariableToBranch (OsiSolverInterface *solver, const double *newSolution, int &bestColumn, int &bestRound)

Selects the next variable to branch on.

Additional Inherited Members

7.45.1 Detailed Description

DiveGuided class.

Definition at line 14 of file CbcHeuristicDiveGuided.hpp.

- 7.45.2 Constructor & Destructor Documentation
- 7.45.2.1 CbcHeuristicDiveGuided::CbcHeuristicDiveGuided ()
- 7.45.2.2 CbcHeuristicDiveGuided::CbcHeuristicDiveGuided (CbcModel & model)
- 7.45.2.3 CbcHeuristicDiveGuided::CbcHeuristicDiveGuided (const CbcHeuristicDiveGuided &)

7.45.2.4 CbcHeuristicDiveGuided::~CbcHeuristicDiveGuided ()

7.45.3 Member Function Documentation

7.45.3.1 virtual CbcHeuristicDiveGuided* CbcHeuristicDiveGuided::clone() const [virtual]

Clone.

Implements CbcHeuristicDive.

7.45.3.2 CbcHeuristicDiveGuided& CbcHeuristicDiveGuided::operator=(const CbcHeuristicDiveGuided & rhs)

Assignment operator.

7.45.3.3 virtual void CbcHeuristicDiveGuided::generateCpp (FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristicDive.

7.45.3.4 virtual bool CbcHeuristicDiveGuided::canHeuristicRun() [virtual]

Tests if the heuristic can run.

Reimplemented from CbcHeuristicDive.

7.45.3.5 virtual bool CbcHeuristicDiveGuided::selectVariableToBranch (OsiSolverInterface * solver, const double * newSolution, int & bestColumn, int & bestRound) [virtual]

Selects the next variable to branch on.

Returns true if all the fractional variables can be trivially rounded. Returns false, if there is at least one fractional variable that is not trivially roundable. In this case, the bestColumn returned will not be trivially roundable.

Implements CbcHeuristicDive.

The documentation for this class was generated from the following file:


• /home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveGuided.hpp

7.46 CbcHeuristicDiveLineSearch Class Reference

DiveLineSearch class.

#include <CbcHeuristicDiveLineSearch.hpp>

Inheritance diagram for CbcHeuristicDiveLineSearch:



Public Member Functions

- CbcHeuristicDiveLineSearch ()
- CbcHeuristicDiveLineSearch (CbcModel &model)
- CbcHeuristicDiveLineSearch (const CbcHeuristicDiveLineSearch &)
- ∼CbcHeuristicDiveLineSearch ()
- virtual

CbcHeuristicDiveLineSearch * clone () const

Clone

CbcHeuristicDiveLineSearch & operator= (const CbcHeuristicDiveLineSearch &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

 virtual bool selectVariableToBranch (OsiSolverInterface *solver, const double *newSolution, int &bestColumn, int &bestRound)

Selects the next variable to branch on.

Additional Inherited Members

7.46.1 Detailed Description

DiveLineSearch class.

Definition at line 14 of file CbcHeuristicDiveLineSearch.hpp.

- 7.46.2 Constructor & Destructor Documentation
- 7.46.2.1 CbcHeuristicDiveLineSearch::CbcHeuristicDiveLineSearch ()
- 7.46.2.2 CbcHeuristicDiveLineSearch::CbcHeuristicDiveLineSearch (CbcModel & model)
- 7.46.2.3 CbcHeuristicDiveLineSearch::CbcHeuristicDiveLineSearch (const CbcHeuristicDiveLineSearch &)
- 7.46.2.4 CbcHeuristicDiveLineSearch:: ~ CbcHeuristicDiveLineSearch ()
- 7.46.3 Member Function Documentation
- 7.46.3.1 virtual CbcHeuristicDiveLineSearch* CbcHeuristicDiveLineSearch::clone() const [virtual]

Clone.

Implements CbcHeuristicDive.

7.46.3.2 CbcHeuristicDiveLineSearch& CbcHeuristicDiveLineSearch::operator= (const CbcHeuristicDiveLineSearch & rhs)

Assignment operator.

7.46.3.3 virtual void CbcHeuristicDiveLineSearch::generateCpp(FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristicDive.

7.46.3.4 virtual bool CbcHeuristicDiveLineSearch::selectVariableToBranch (OsiSolverInterface * solver, const double * newSolution, int & bestColumn, int & bestRound) [virtual]

Selects the next variable to branch on.

Returns true if all the fractional variables can be trivially rounded. Returns false, if there is at least one fractional variable that is not trivially roundable. In this case, the bestColumn returned will not be trivially roundable.

Implements CbcHeuristicDive.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveLineSearch.hpp

7.47 CbcHeuristicDivePseudoCost Class Reference

DivePseudoCost class.

#include <CbcHeuristicDivePseudoCost.hpp>

Inheritance diagram for CbcHeuristicDivePseudoCost:



Public Member Functions

- CbcHeuristicDivePseudoCost ()
- CbcHeuristicDivePseudoCost (CbcModel &model)
- CbcHeuristicDivePseudoCost (const CbcHeuristicDivePseudoCost &)
- CbcHeuristicDivePseudoCost ()
- virtual

CbcHeuristicDivePseudoCost * clone () const

Clone.

CbcHeuristicDivePseudoCost & operator= (const CbcHeuristicDivePseudoCost &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual bool selectVariableToBranch (OsiSolverInterface *solver, const double *newSolution, int &bestColumn, int &bestRound)

Selects the next variable to branch on.

• virtual void initializeData ()

Initializes any data which is going to be used repeatedly in selectVariableToBranch.

virtual int fixOtherVariables (OsiSolverInterface *solver, const double *solution, PseudoReducedCost *candidate, const double *random)

Fix other variables at bounds.

Additional Inherited Members

7.47.1 Detailed Description

DivePseudoCost class.

Definition at line 14 of file CbcHeuristicDivePseudoCost.hpp.

- 7.47.2 Constructor & Destructor Documentation
- 7.47.2.1 CbcHeuristicDivePseudoCost::CbcHeuristicDivePseudoCost()
- 7.47.2.2 CbcHeuristicDivePseudoCost::CbcHeuristicDivePseudoCost (CbcModel & model)
- 7.47.2.3 CbcHeuristicDivePseudoCost::CbcHeuristicDivePseudoCost (const CbcHeuristicDivePseudoCost &)
- 7.47.2.4 CbcHeuristicDivePseudoCost::~CbcHeuristicDivePseudoCost()
- 7.47.3 Member Function Documentation
- 7.47.3.1 virtual CbcHeuristicDivePseudoCost* CbcHeuristicDivePseudoCost::clone() const [virtual]

Clone.

Implements CbcHeuristicDive.

7.47.3.2 CbcHeuristicDivePseudoCost& CbcHeuristicDivePseudoCost::operator=(const CbcHeuristicDivePseudoCost & rhs)

Assignment operator.

7.47.3.3 virtual void CbcHeuristicDivePseudoCost::generateCpp (FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristicDive.

7.47.3.4 virtual bool CbcHeuristicDivePseudoCost::selectVariableToBranch (OsiSolverInterface * solver, const double * newSolution, int & bestColumn, int & bestRound) [virtual]

Selects the next variable to branch on.

Returns true if all the fractional variables can be trivially rounded. Returns false, if there is at least one fractional variable that is not trivially roundable. In this case, the bestColumn returned will not be trivially roundable.

Implements CbcHeuristicDive.

```
7.47.3.5 virtual void CbcHeuristicDivePseudoCost::initializeData() [virtual]
```

Initializes any data which is going to be used repeatedly in selectVariableToBranch.

Reimplemented from CbcHeuristicDive.

7.47.3.6 virtual int CbcHeuristicDivePseudoCost::fixOtherVariables (OsiSolverInterface * solver, const double * solution, PseudoReducedCost * candidate, const double * random) [virtual]

Fix other variables at bounds.

Reimplemented from CbcHeuristicDive.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDivePseudoCost.hpp

7.48 CbcHeuristicDiveVectorLength Class Reference

DiveVectorLength class.

#include <CbcHeuristicDiveVectorLength.hpp>

Inheritance diagram for CbcHeuristicDiveVectorLength:



Public Member Functions

- CbcHeuristicDiveVectorLength ()
- CbcHeuristicDiveVectorLength (CbcModel &model)
- CbcHeuristicDiveVectorLength (const CbcHeuristicDiveVectorLength &)
- ∼CbcHeuristicDiveVectorLength ()
- virtua

CbcHeuristicDiveVectorLength * clone () const

Clone

CbcHeuristicDiveVectorLength & operator= (const CbcHeuristicDiveVectorLength &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

 virtual bool selectVariableToBranch (OsiSolverInterface *solver, const double *newSolution, int &bestColumn, int &bestRound)

Selects the next variable to branch on.

Additional Inherited Members

7.48.1 Detailed Description

DiveVectorLength class.

Definition at line 14 of file CbcHeuristicDiveVectorLength.hpp.

- 7.48.2 Constructor & Destructor Documentation
- 7.48.2.1 CbcHeuristicDiveVectorLength::CbcHeuristicDiveVectorLength ()
- 7.48.2.2 CbcHeuristicDiveVectorLength::CbcHeuristicDiveVectorLength (CbcModel & model)

7.48.2.3 CbcHeuristicDiveVectorLength::CbcHeuristicDiveVectorLength (const CbcHeuristicDiveVectorLength &)

7.48.2.4 CbcHeuristicDiveVectorLength:: ~ CbcHeuristicDiveVectorLength ()

7.48.3 Member Function Documentation

7.48.3.1 virtual CbcHeuristicDiveVectorLength* CbcHeuristicDiveVectorLength::clone() const [virtual]

Clone.

Implements CbcHeuristicDive.

7.48.3.2 CbcHeuristicDiveVectorLength& CbcHeuristicDiveVectorLength::operator= (const CbcHeuristicDiveVectorLength & rhs)

Assignment operator.

7.48.3.3 virtual void CbcHeuristicDiveVectorLength::generateCpp(FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristicDive.

7.48.3.4 virtual bool CbcHeuristicDiveVectorLength::selectVariableToBranch (OsiSolverInterface * solver, const double * newSolution, int & bestColumn, int & bestRound) [virtual]

Selects the next variable to branch on.

Returns true if all the fractional variables can be trivially rounded. Returns false, if there is at least one fractional variable that is not trivially roundable. In this case, the bestColumn returned will not be trivially roundable.

Implements CbcHeuristicDive.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveVectorLength.hpp

7.49 CbcHeuristicDW Class Reference

This is unlike the other heuristics in that it is very very compute intensive.

```
#include <CbcHeuristicDW.hpp>
```

Inheritance diagram for CbcHeuristicDW:



Public Member Functions

- CbcHeuristicDW ()
- CbcHeuristicDW (CbcModel &model, int keepContinuous=0)
- CbcHeuristicDW (CbcModel &model, int callBack(CbcHeuristicDW *currentHeuristic, CbcModel *thisModel, int whereFrom), int keepContinuous=0)

- CbcHeuristicDW (const CbcHeuristicDW &)
- ∼CbcHeuristicDW ()
- virtual CbcHeuristic * clone () const

Clone

CbcHeuristicDW & operator= (const CbcHeuristicDW &rhs)

Assignment operator.

• virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

• int numberBlocks () const

Return number of blocks <=0 - no usable structure.

void passInSolution (const double *solution)

Pass in a solution.

void passInContinuousSolution (const double *solution)

Pass in continuous solution.

void setProposalActions (int fullDWEverySoOften)

DW Proposal actions fullDWEverySoOften - 0 - off k - every k times solution gets better.

double objectiveValueWhen (int whichDW) const

Objective value when whichDw created.

· int numberColumnsDW (int whichDW) const

Number of columns in DW.

• OsiSolverInterface * solver () const

Solver.

OsiSolverInterface * DWModel (int whichDW) const

DW model (user must delete)

• double bestObjective () const

Best objective value.

• const double * bestSolution () const

Best solution found so far.

const double * continuousSolution () const

Continuous solution.

const double * fixedDj () const

Reduced costs of fixed solution.

const double * objectiveDW () const

Objective at which DW updated.

• int numberDWTimes () const

Number of times we have added to DW model.

const int * numberColumnsDW () const

Number of columns in DW.

void setNumberPasses (int value)

Set number of passes.

void setNumberBadPasses (int value)

Set number of passes without better solution.

void setNumberNeeded (int value)

Set number free integers needed (Base value)

• int getNumberNeeded () const

Get number free integers needed (Base value)

void setCurrentNumberNeeded (int value)

Set number free integers needed (Current value)

int getCurrentNumberNeeded () const

Get number free integers needed (Current value)

void setNumberNodes (int value)

Set number nodes (could be done in callback) (Base value)

• int getNumberNodes () const

Get number nodes (could be done in callback) (Base value)

void setCurrentNumberNodes (int value)

Set number nodes (could be done in callback) (Current value)

int getCurrentNumberNodes () const

Get number nodes (could be done in callback) (Current value)

void setTargetObjective (double value)

Set target objective.

void setHowOften (int value)

Sets how often to do it.

const int * whichRowBlock () const

Block for every row.

const int * whichColumnBlock () const

Block for every column.

• double * initialLower () const

Initial Lower bounds.

double * initialUpper () const

Initial Upper bounds.

int * intArrays () const

Local integer arrays (each numberBlocks_ long)

• double * doubleArrays () const

Local double arrays (each numberBlocks_ long)

• int phase () const

Phase of solution.

· int pass () const

Pass number.

const int * columnsInBlock () const

Which columns are in block.

• const int * startColumnBlock () const

Starts for columnsInBlock.

• const int * intsInBlock () const

Number of integer variables in each block.

• double objective Value (const double *solution)

Objective value (could also check validity)

Protected Types

typedef int(* heuristicCallBack)(CbcHeuristicDW *, CbcModel *, int)

Protected Attributes

double targetObjective_

Target objective.

double bestObjective_

Best objective value.

· double lastObjective_

Objective value last time.

heuristicCallBack functionPointer

Call back whereFrom - 0 - after blocks found but before data setup 1 - after blocks sorted but before used 2 - just before normal branch and bound 3 - after DW has been updated 4 - if better solution found 5 - every time a block might be used next few for adjustment of nNeeded etc 6 - complete search done - no solution 7 - stopped on nodes - no improvement 8 - improving (same as 4 but after nNeeded changed Pointers to local data given by following pointers.

int * intArray

Local integer arrays (each numberBlocks_ long)

double * doubleArray_

Local double arrays (each numberBlocks_ long)

OsiSolverInterface * solver_

Base solver.

OsiSolverInterface * dwSolver_

DW solver.

double * bestSolution

Best solution found so far.

double * continuousSolution_

Continuous solution.

double * fixedDj_

Reduced costs of fixed solution.

double * saveLower_

Original lower bounds.

double * saveUpper_

Original Upper bounds.

double * random

random numbers for master rows

double * weights

Weights for each proposal.

double * objectiveDW_

Objective at which DW updated.

int * numberColumnsDW_

Number of columns in each DW.

int * whichRowBlock

Block for every row.

int * whichColumnBlock

Block for every column.

int * dwBlock

Block number for each proposal.

int * backwardRow_

Points back to master rows.

int * rowsInBlock

Which rows are in blocke.

int * columnsInBlock

Which columns are in block.

int * startRowBlock

Starts for rowsInBlock.

int * startColumnBlock

Starts for columnsInBlock.

int * intsInBlock

Number of integer variables in each block.

unsigned int * fingerPrint_

Bits set for 1 integers in each block.

unsigned short * affinity_

Affinity each block has for other (will be triangular?)

int fullDWEverySoOften_

DW Proposal actions fullDWEverySoOften - 0 - off k - every k times solution gets better.

· int numberPasses_

Number of passes.

int howOften_

How often to do (code can change)

int maximumDW

Current maximum number of DW proposals.

int numberDW

Number of DW proposals.

int numberDWTimes

Number of times we have added to DW model.

int sizeFingerPrint

Number of unsigned ints needed for each block of fingerPrint.

int numberMasterColumns

Number of columns in master.

int numberMasterRows

Number of rows in master.

int numberBlocks_

Number of blocks.

int keepContinuous_

Action on decomposition - 1 keep continuous, 0 don't.

· int phase_

Phase of solution.

int pass_

Pass number.

int nNeededBase

Base number of integers needed.

• int nNodesBase_

Base number of nodes needed.

int nNeeded_

Base number of integers needed.

int nNodes_

Base number of nodes needed.

int numberBadPasses

Number of passes without better solution.

int solveState

7.49.1 Detailed Description

This is unlike the other heuristics in that it is very very compute intensive.

It tries to find a DW structure and use that

Definition at line 17 of file CbcHeuristicDW.hpp.

- 7.49.2 Member Typedef Documentation
- 7.49.2.1 typedef int(* CbcHeuristicDW::heuristicCallBack)(CbcHeuristicDW *,CbcModel *, int) [protected]

Definition at line 194 of file CbcHeuristicDW.hpp.

- 7.49.3 Constructor & Destructor Documentation
- 7.49.3.1 CbcHeuristicDW::CbcHeuristicDW()
- 7.49.3.2 CbcHeuristicDW::CbcHeuristicDW (CbcModel & model, int keepContinuous = 0)
- 7.49.3.3 CbcHeuristicDW::CbcHeuristicDW (CbcModel & model, int callBackCbcHeuristicDW *currentHeuristic, CbcModel *thisModel, int whereFrom, int keepContinuous = 0)
- 7.49.3.4 CbcHeuristicDW::CbcHeuristicDW (const CbcHeuristicDW &)
- 7.49.3.5 CbcHeuristicDW::~CbcHeuristicDW ()
- 7.49.4 Member Function Documentation
- 7.49.4.1 virtual CbcHeuristic* CbcHeuristicDW::clone()const [virtual]

Clone.

Implements CbcHeuristic.

7.49.4.2 CbcHeuristicDW& CbcHeuristicDW::operator= (const CbcHeuristicDW & rhs)

Assignment operator.

7.49.4.3 virtual void CbcHeuristicDW::generateCpp (FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristic.

```
7.49.4.4 virtual void CbcHeuristicDW::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.49.4.5 virtual void CbcHeuristicDW::setModel ( CbcModel * model ) [virtual]
update model (This is needed if cliques update matrix etc)
Reimplemented from CbcHeuristic.
7.49.4.6 virtual int CbcHeuristicDW::solution ( double & objectiveValue, double * newSolution ) [virtual]
returns 0 if no solution, 1 if valid solution.
Sets solution values if good, sets objective value (only if good) This does Relaxation Induced Neighborhood Search
Implements CbcHeuristic.
7.49.4.7 int CbcHeuristicDW::numberBlocks ( ) const [inline]
Return number of blocks <=0 - no usable structure.
Definition at line 65 of file CbcHeuristicDW.hpp.
7.49.4.8 void CbcHeuristicDW::passInSolution ( const double * solution )
Pass in a solution.
7.49.4.9 void CbcHeuristicDW::passInContinuousSolution ( const double * solution )
Pass in continuous solution.
7.49.4.10 void CbcHeuristicDW::setProposalActions (int fullDWEverySoOften)
DW Proposal actions fullDWEverySoOften - 0 - off k - every k times solution gets better.
7.49.4.11 double CbcHeuristicDW::objectiveValueWhen (int whichDW) const
Objective value when whichDw created.
7.49.4.12 int CbcHeuristicDW::numberColumnsDW (int whichDW) const
Number of columns in DW.
7.49.4.13 OsiSolverInterface* CbcHeuristicDW::solver( ) const [inline]
Solver.
Definition at line 82 of file CbcHeuristicDW.hpp.
7.49.4.14 OsiSolverInterface* CbcHeuristicDW::DWModel ( int whichDW ) const
DW model (user must delete)
7.49.4.15 double CbcHeuristicDW::bestObjective ( ) const [inline]
Best objective value.
```

Definition at line 87 of file CbcHeuristicDW.hpp.

```
7.49.4.16 const double* CbcHeuristicDW::bestSolution ( ) const [inline]
Best solution found so far.
Definition at line 90 of file CbcHeuristicDW.hpp.
7.49.4.17 const double* CbcHeuristicDW::continuousSolution ( ) const [inline]
Continuous solution.
Definition at line 93 of file CbcHeuristicDW.hpp.
7.49.4.18 const double* CbcHeuristicDW::fixedDj( ) const [inline]
Reduced costs of fixed solution.
Definition at line 96 of file CbcHeuristicDW.hpp.
7.49.4.19 const double* CbcHeuristicDW::objectiveDW ( ) const [inline]
Objective at which DW updated.
Definition at line 99 of file CbcHeuristicDW.hpp.
7.49.4.20 int CbcHeuristicDW::numberDWTimes ( ) const [inline]
Number of times we have added to DW model.
Definition at line 102 of file CbcHeuristicDW.hpp.
7.49.4.21 const int* CbcHeuristicDW::numberColumnsDW ( ) const [inline]
Number of columns in DW.
Definition at line 105 of file CbcHeuristicDW.hpp.
7.49.4.22 void CbcHeuristicDW::setNumberPasses (int value ) [inline]
Set number of passes.
Definition at line 108 of file CbcHeuristicDW.hpp.
7.49.4.23 void CbcHeuristicDW::setNumberBadPasses (int value) [inline]
Set number of passes without better solution.
Definition at line 111 of file CbcHeuristicDW.hpp.
7.49.4.24 void CbcHeuristicDW::setNumberNeeded (int value) [inline]
Set number free integers needed (Base value)
Definition at line 114 of file CbcHeuristicDW.hpp.
7.49.4.25 int CbcHeuristicDW::getNumberNeeded ( ) const [inline]
Get number free integers needed (Base value)
Definition at line 117 of file CbcHeuristicDW.hpp.
```

```
7.49.4.26 void CbcHeuristicDW::setCurrentNumberNeeded (int value) [inline]
Set number free integers needed (Current value)
Definition at line 120 of file CbcHeuristicDW.hpp.
7.49.4.27 int CbcHeuristicDW::getCurrentNumberNeeded() const [inline]
Get number free integers needed (Current value)
Definition at line 123 of file CbcHeuristicDW.hpp.
7.49.4.28 void CbcHeuristicDW::setNumberNodes (int value) [inline]
Set number nodes (could be done in callback) (Base value)
Definition at line 126 of file CbcHeuristicDW.hpp.
7.49.4.29 int CbcHeuristicDW::getNumberNodes() const [inline]
Get number nodes (could be done in callback) (Base value)
Definition at line 129 of file CbcHeuristicDW.hpp.
7.49.4.30 void CbcHeuristicDW::setCurrentNumberNodes (int value) [inline]
Set number nodes (could be done in callback) (Current value)
Definition at line 132 of file CbcHeuristicDW.hpp.
7.49.4.31 int CbcHeuristicDW::getCurrentNumberNodes() const [inline]
Get number nodes (could be done in callback) (Current value)
Definition at line 135 of file CbcHeuristicDW.hpp.
7.49.4.32 void CbcHeuristicDW::setTargetObjective ( double value ) [inline]
Set target objective.
Definition at line 138 of file CbcHeuristicDW.hpp.
7.49.4.33 void CbcHeuristicDW::setHowOften (int value ) [inline]
Sets how often to do it.
Definition at line 141 of file CbcHeuristicDW.hpp.
7.49.4.34 const int* CbcHeuristicDW::whichRowBlock( ) const [inline]
Block for every row.
Definition at line 145 of file CbcHeuristicDW.hpp.
7.49.4.35 const int* CbcHeuristicDW::whichColumnBlock( ) const [inline]
Block for every column.
Definition at line 148 of file CbcHeuristicDW.hpp.
```

```
7.49.4.36 double* CbcHeuristicDW::initialLower( ) const [inline]
Initial Lower bounds.
Definition at line 151 of file CbcHeuristicDW.hpp.
7.49.4.37 double* CbcHeuristicDW::initialUpper( ) const [inline]
Initial Upper bounds.
Definition at line 154 of file CbcHeuristicDW.hpp.
7.49.4.38 int* CbcHeuristicDW::intArrays() const [inline]
Local integer arrays (each numberBlocks long)
Definition at line 157 of file CbcHeuristicDW.hpp.
7.49.4.39 double* CbcHeuristicDW::doubleArrays ( ) const [inline]
Local double arrays (each numberBlocks long)
Definition at line 160 of file CbcHeuristicDW.hpp.
7.49.4.40 int CbcHeuristicDW::phase ( ) const [inline]
Phase of solution.
Definition at line 163 of file CbcHeuristicDW.hpp.
7.49.4.41 int CbcHeuristicDW::pass ( ) const [inline]
Pass number.
Definition at line 166 of file CbcHeuristicDW.hpp.
7.49.4.42 const int* CbcHeuristicDW::columnsInBlock( ) const [inline]
Which columns are in block.
Definition at line 169 of file CbcHeuristicDW.hpp.
7.49.4.43 const int* CbcHeuristicDW::startColumnBlock( ) const [inline]
Starts for columnsInBlock.
Definition at line 172 of file CbcHeuristicDW.hpp.
7.49.4.44 const int* CbcHeuristicDW::intsInBlock( ) const [inline]
Number of integer variables in each block.
Definition at line 175 of file CbcHeuristicDW.hpp.
7.49.4.45 double CbcHeuristicDW::objectiveValue ( const double * solution )
Objective value (could also check validity)
```

7.49.5 Member Data Documentation

7.49.5.1 double CbcHeuristicDW::targetObjective_ [protected]

Target objective.

Definition at line 197 of file CbcHeuristicDW.hpp.

7.49.5.2 double CbcHeuristicDW::bestObjective [protected]

Best objective value.

Definition at line 199 of file CbcHeuristicDW.hpp.

7.49.5.3 double CbcHeuristicDW::lastObjective_ [protected]

Objective value last time.

Definition at line 201 of file CbcHeuristicDW.hpp.

7.49.5.4 heuristicCallBack CbcHeuristicDW::functionPointer_ [protected]

Call back whereFrom - 0 - after blocks found but before data setup 1 - after blocks sorted but before used 2 - just before normal branch and bound 3 - after DW has been updated 4 - if better solution found 5 - every time a block might be used next few for adjustment of nNeeded etc 6 - complete search done - no solution 7 - stopped on nodes - no improvement 8 - improving (same as 4 but after nNeeded changed Pointers to local data given by following pointers.

Definition at line 216 of file CbcHeuristicDW.hpp.

7.49.5.5 int* CbcHeuristicDW::intArray_ [protected]

Local integer arrays (each numberBlocks long)

Definition at line 218 of file CbcHeuristicDW.hpp.

7.49.5.6 double* CbcHeuristicDW::doubleArray_ [protected]

Local double arrays (each numberBlocks_long)

Definition at line 220 of file CbcHeuristicDW.hpp.

7.49.5.7 OsiSolverInterface* **CbcHeuristicDW::solver_** [protected]

Base solver.

Definition at line 222 of file CbcHeuristicDW.hpp.

7.49.5.8 OsiSolverInterface* CbcHeuristicDW::dwSolver_ [protected]

DW solver.

Definition at line 224 of file CbcHeuristicDW.hpp.

7.49.5.9 double* CbcHeuristicDW::bestSolution_ [protected]

Best solution found so far.

Definition at line 226 of file CbcHeuristicDW.hpp.

7.49.5.10 double* CbcHeuristicDW::continuousSolution_ [protected]

Continuous solution.

Definition at line 228 of file CbcHeuristicDW.hpp.

7.49.5.11 double* CbcHeuristicDW::fixedDj_ [protected] Reduced costs of fixed solution. Definition at line 230 of file CbcHeuristicDW.hpp. **7.49.5.12** double* CbcHeuristicDW::saveLower_ [protected] Original lower bounds. Definition at line 232 of file CbcHeuristicDW.hpp. **7.49.5.13** double* CbcHeuristicDW::saveUpper_ [protected] Original Upper bounds. Definition at line 234 of file CbcHeuristicDW.hpp. **7.49.5.14** double* CbcHeuristicDW::random_ [protected] random numbers for master rows Definition at line 236 of file CbcHeuristicDW.hpp. **7.49.5.15** double* CbcHeuristicDW::weights_ [protected] Weights for each proposal. Definition at line 238 of file CbcHeuristicDW.hpp. **7.49.5.16** double* CbcHeuristicDW::objectiveDW_ [protected] Objective at which DW updated. Definition at line 240 of file CbcHeuristicDW.hpp. 7.49.5.17 int* CbcHeuristicDW::numberColumnsDW_ [protected] Number of columns in each DW. Definition at line 242 of file CbcHeuristicDW.hpp. **7.49.5.18** int* CbcHeuristicDW::whichRowBlock_ [protected] Block for every row. Definition at line 244 of file CbcHeuristicDW.hpp. **7.49.5.19** int* CbcHeuristicDW::whichColumnBlock_ [protected] Block for every column. Definition at line 246 of file CbcHeuristicDW.hpp.

Block number for each proposal.

Definition at line 248 of file CbcHeuristicDW.hpp.

7.49.5.20 int* CbcHeuristicDW::dwBlock_ [protected]

```
7.49.5.21 int* CbcHeuristicDW::backwardRow_ [protected]
```

Points back to master rows.

Definition at line 250 of file CbcHeuristicDW.hpp.

7.49.5.22 int* CbcHeuristicDW::rowslnBlock [protected]

Which rows are in blocke.

Definition at line 252 of file CbcHeuristicDW.hpp.

7.49.5.23 int* CbcHeuristicDW::columnslnBlock_ [protected]

Which columns are in block.

Definition at line 254 of file CbcHeuristicDW.hpp.

7.49.5.24 int* CbcHeuristicDW::startRowBlock_ [protected]

Starts for rowsInBlock.

Definition at line 256 of file CbcHeuristicDW.hpp.

7.49.5.25 int* CbcHeuristicDW::startColumnBlock [protected]

Starts for columnsInBlock.

Definition at line 258 of file CbcHeuristicDW.hpp.

7.49.5.26 int* CbcHeuristicDW::intslnBlock_ [protected]

Number of integer variables in each block.

Definition at line 260 of file CbcHeuristicDW.hpp.

7.49.5.27 unsigned int* CbcHeuristicDW::fingerPrint_ [protected]

Bits set for 1 integers in each block.

Definition at line 262 of file CbcHeuristicDW.hpp.

7.49.5.28 unsigned short* CbcHeuristicDW::affinity_ [protected]

Affinity each block has for other (will be triangular?)

Definition at line 264 of file CbcHeuristicDW.hpp.

7.49.5.29 int CbcHeuristicDW::fullDWEverySoOften_ [protected]

DW Proposal actions fullDWEverySoOften - 0 - off k - every k times solution gets better.

Definition at line 270 of file CbcHeuristicDW.hpp.

7.49.5.30 int CbcHeuristicDW::numberPasses_ [protected]

Number of passes.

Definition at line 272 of file CbcHeuristicDW.hpp.

7.49.5.31 int CbcHeuristicDW::howOften_ [protected] How often to do (code can change) Definition at line 274 of file CbcHeuristicDW.hpp. **7.49.5.32** int CbcHeuristicDW::maximumDW_ [protected] Current maximum number of DW proposals. Definition at line 276 of file CbcHeuristicDW.hpp. **7.49.5.33** int CbcHeuristicDW::numberDW_ [protected] Number of DW proposals. Definition at line 278 of file CbcHeuristicDW.hpp. **7.49.5.34** int CbcHeuristicDW::numberDWTimes_ [protected] Number of times we have added to DW model. Definition at line 280 of file CbcHeuristicDW.hpp. **7.49.5.35** int CbcHeuristicDW::sizeFingerPrint_ [protected] Number of unsigned ints needed for each block of fingerPrint. Definition at line 282 of file CbcHeuristicDW.hpp. **7.49.5.36** int CbcHeuristicDW::numberMasterColumns_ [protected] Number of columns in master. Definition at line 284 of file CbcHeuristicDW.hpp. **7.49.5.37** int CbcHeuristicDW::numberMasterRows_ [protected] Number of rows in master. Definition at line 286 of file CbcHeuristicDW.hpp. **7.49.5.38** int CbcHeuristicDW::numberBlocks_ [protected] Number of blocks. Definition at line 288 of file CbcHeuristicDW.hpp. 7.49.5.39 int CbcHeuristicDW::keepContinuous_ [protected] Action on decomposition - 1 keep continuous, 0 don't. Definition at line 290 of file CbcHeuristicDW.hpp.

7.49.5.40 int CbcHeuristicDW::phase_ [protected]

Phase of solution.

Definition at line 292 of file CbcHeuristicDW.hpp.

7.49.5.41 int CbcHeuristicDW::pass_ [protected]

Pass number.

Definition at line 294 of file CbcHeuristicDW.hpp.

7.49.5.42 int CbcHeuristicDW::nNeededBase_ [protected]

Base number of integers needed.

Definition at line 296 of file CbcHeuristicDW.hpp.

7.49.5.43 int CbcHeuristicDW::nNodesBase_ [protected]

Base number of nodes needed.

Definition at line 298 of file CbcHeuristicDW.hpp.

7.49.5.44 int CbcHeuristicDW::nNeeded_ [protected]

Base number of integers needed.

Definition at line 300 of file CbcHeuristicDW.hpp.

7.49.5.45 int CbcHeuristicDW::nNodes_ [protected]

Base number of nodes needed.

Definition at line 302 of file CbcHeuristicDW.hpp.

7.49.5.46 int CbcHeuristicDW::numberBadPasses_ [protected]

Number of passes without better solution.

Definition at line 304 of file CbcHeuristicDW.hpp.

7.49.5.47 int CbcHeuristicDW::solveState_ [protected]

Definition at line 306 of file CbcHeuristicDW.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDW.hpp

7.50 CbcHeuristicDynamic3 Class Reference

heuristic - just picks up any good solution

#include <CbcLinked.hpp>

Inheritance diagram for CbcHeuristicDynamic3:



Public Member Functions

- CbcHeuristicDynamic3 ()
- CbcHeuristicDynamic3 (CbcModel &model)
- CbcHeuristicDynamic3 (const CbcHeuristicDynamic3 &)
- CbcHeuristicDynamic3 ()
- virtual CbcHeuristic * clone () const

Clone

virtual void setModel (CbcModel *model)

update model

• virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

· virtual bool canDealWithOdd () const

Returns true if can deal with "odd" problems e.g. sos type 2.

Additional Inherited Members

7.50.1 Detailed Description

heuristic - just picks up any good solution

Definition at line 379 of file CbcLinked.hpp.

- 7.50.2 Constructor & Destructor Documentation
- 7.50.2.1 CbcHeuristicDynamic3::CbcHeuristicDynamic3 ()
- 7.50.2.2 CbcHeuristicDynamic3::CbcHeuristicDynamic3 (CbcModel & model)
- 7.50.2.3 CbcHeuristicDynamic3::CbcHeuristicDynamic3 (const CbcHeuristicDynamic3 &)
- 7.50.2.4 CbcHeuristicDynamic3::~CbcHeuristicDynamic3 ()
- 7.50.3 Member Function Documentation
- 7.50.3.1 virtual CbcHeuristic* CbcHeuristicDynamic3::clone()const [virtual]

Clone.

Implements CbcHeuristic.

7.50.3.2 virtual void CbcHeuristicDynamic3::setModel (CbcModel * model) [virtual]

update model

Reimplemented from CbcHeuristic.

7.50.3.3 virtual int CbcHeuristicDynamic3::solution (double & objectiveValue, double * newSolution) [virtual]

returns 0 if no solution, 1 if valid solution.

Sets solution values if good, sets objective value (only if good) We leave all variables which are at one at this node of the tree to that value and will initially set all others to zero. We then sort all variables in order of their cost divided by the number of entries in rows which are not yet covered. We randomize that value a bit so that ties will be broken in different ways on different runs of the heuristic. We then choose the best one and set it to one and repeat the exercise.

Implements CbcHeuristic.

7.50.3.4 virtual void CbcHeuristicDynamic3::resetModel (CbcModel * model) [virtual]

Resets stuff if model changes.

Implements CbcHeuristic.

7.50.3.5 virtual bool CbcHeuristicDynamic3::canDealWithOdd() const [inline], [virtual]

Returns true if can deal with "odd" problems e.g. sos type 2.

Reimplemented from CbcHeuristic.

Definition at line 417 of file CbcLinked.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.51 CbcHeuristicFPump Class Reference

Feasibility Pump class.

#include <CbcHeuristicFPump.hpp>

Inheritance diagram for CbcHeuristicFPump:



Public Member Functions

- CbcHeuristicFPump ()
- CbcHeuristicFPump (CbcModel &model, double downValue=0.5, bool roundExpensive=false)
- CbcHeuristicFPump (const CbcHeuristicFPump &)
- ∼CbcHeuristicFPump ()
- CbcHeuristicFPump & operator= (const CbcHeuristicFPump &rhs)

Assignment operator.

• virtual CbcHeuristic * clone () const

Clone.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value (only if good) This is called after cuts have been added - so can not add cuts.

void setMaximumTime (double value)

Set maximum Time (default off) - also sets starttime to current.

double maximumTime () const

Get maximum Time (default 0.0 == time limit off)

void setFakeCutoff (double value)

Set fake cutoff (default COIN DBL MAX == off)

double fakeCutoff () const

Get fake cutoff (default 0.0 == off)

void setAbsoluteIncrement (double value)

Set absolute increment (default 0.0 == off)

• double absoluteIncrement () const

Get absolute increment (default 0.0 == off)

void setRelativeIncrement (double value)

Set relative increment (default 0.0 == off)

· double relativeIncrement () const

Get relative increment (default 0.0 == off)

void setDefaultRounding (double value)

Set default rounding (default 0.5)

double defaultRounding () const

Get default rounding (default 0.5)

void setInitialWeight (double value)

Set initial weight (default 0.0 == off)

double initialWeight () const

Get initial weight (default 0.0 == off)

void setWeightFactor (double value)

Set weight factor (default 0.1)

double weightFactor () const

Get weight factor (default 0.1)

void setArtificialCost (double value)

Set threshold cost for using original cost - even on continuous (default infinity)

• double artificialCost () const

Get threshold cost for using original cost - even on continuous (default infinity)

• double iterationRatio () const

Get iteration to size ratio.

· void setIterationRatio (double value)

Set iteration to size ratio.

void setMaximumPasses (int value)

Set maximum passes (default 100)

int maximumPasses () const

Get maximum passes (default 100)

void setMaximumRetries (int value)

Set maximum retries (default 1)

· int maximumRetries () const

Get maximum retries (default 1)

void setAccumulate (int value)

Set use of multiple solutions and solves 0 - do not reuse solves, do not accumulate integer solutions for local search 1 - do not reuse solves, accumulate integer solutions for local search 2 - reuse solves, do not accumulate integer solutions for local search 3 - reuse solves, accumulate integer solutions for local search If we add 4 then use second form of problem (with extra rows and variables for general integers) At some point (date?), I added.

· int accumulate () const

Get accumulation option.

void setFixOnReducedCosts (int value)

Set whether to fix variables on known solution 0 - do not fix 1 - fix integers on reduced costs 2 - fix integers on reduced costs but only on entry.

• int fixOnReducedCosts () const

Get reduced cost option.

void setReducedCostMultiplier (double value)

Set reduced cost multiplier 1.0 as normal < 1.0 (x) - pretend gap is x* actual gap - just for fixing.

double reducedCostMultiplier () const

Get reduced cost multiplier.

Protected Attributes

double startTime

Start time.

double maximumTime

Maximum Cpu seconds.

· double fakeCutoff_

Fake cutoff value.

· double absoluteIncrement_

If positive carry on after solution expecting gain of at least this.

double relativeIncrement_

If positive carry on after solution expecting gain of at least this times objective.

double defaultRounding_

Default is round up if > this.

double initialWeight_

Initial weight for true objective.

double weightFactor_

Factor for decreasing weight.

double artificialCost

Threshold cost for using original cost - even on continuous.

double iterationRatio

If iterationRatio > 0 use instead of maximumPasses_ test is iterations > ratio*(2*nrow+ncol)

double reducedCostMultiplier_

Reduced cost multiplier 1.0 as normal < 1.0 (x) - pretend gap is x* actual gap - just for fixing.

int maximumPasses_

Maximum number of passes.

int maximumRetries_

Maximum number of retries if we find a solution.

int accumulate

Set use of multiple solutions and solves 0 - do not reuse solves, do not accumulate integer solutions for local search 1 - do not reuse solves, accumulate integer solutions for local search 2 - reuse solves, do not accumulate integer solutions for local search 3 - reuse solves, accumulate integer solutions for local search If we add 4 then use second form of problem (with extra rows and variables for general integers) If we do not accumulate solutions then no mini branch and bounds will be done reuse - refers to initial solve after adding in new "cut" If we add 8 then can run after initial cuts (if no solution)

int fixOnReducedCosts

Set whether to fix variables on known solution 0 - do not fix 1 - fix integers on reduced costs 2 - fix integers on reduced costs but only on entry.

bool roundExpensive_

If true round to expensive.

7.51.1 Detailed Description

Feasibility Pump class.

Definition at line 15 of file CbcHeuristicFPump.hpp.

```
7.51.2 Constructor & Destructor Documentation
```

```
7.51.2.1 CbcHeuristicFPump::CbcHeuristicFPump()
```

- 7.51.2.2 CbcHeuristicFPump::CbcHeuristicFPump (CbcModel & model, double downValue = 0.5, bool roundExpensive = false)
- 7.51.2.3 CbcHeuristicFPump::CbcHeuristicFPump (const CbcHeuristicFPump &)
- 7.51.2.4 CbcHeuristicFPump::~CbcHeuristicFPump()
- 7.51.3 Member Function Documentation
- 7.51.3.1 CbcHeuristicFPump& CbcHeuristicFPump::operator= (const CbcHeuristicFPump & rhs)

Assignment operator.

```
7.51.3.2 virtual CbcHeuristic* CbcHeuristicFPump::clone() const [virtual]
```

Clone.

Implements CbcHeuristic.

```
7.51.3.3 virtual void CbcHeuristicFPump::generateCpp (FILE * fp ) [virtual]
```

Create C++ lines to get to current state.

Reimplemented from CbcHeuristic.

```
7.51.3.4 virtual void CbcHeuristicFPump::resetModel ( CbcModel * model ) [virtual]
```

Resets stuff if model changes.

Implements CbcHeuristic.

```
7.51.3.5 virtual void CbcHeuristicFPump::setModel ( CbcModel * model ) [virtual]
```

update model (This is needed if cliques update matrix etc)

Reimplemented from CbcHeuristic.

```
7.51.3.6 virtual int CbcHeuristicFPump::solution ( double & objectiveValue, double * newSolution ) [virtual]
```

returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value (only if good) This is called after cuts have been added - so can not add cuts.

It may make sense for user to call this outside Branch and Cut to get solution. Or normally is just at root node.

new meanings for when_ - on first try then set back to 1 11 - at end fix all integers at same bound throughout 12 - also fix all integers staying at same internal integral value throughout 13 - also fix all continuous variables staying at same bound throughout 14 - also fix all continuous variables staying at same internal value throughout 15 - as 13 but no internal integers And beyond that, it's apparently possible for the range to be between 21 and 25, in which case it's reduced on entry to solution() to be between 11 and 15 and allSlack is set to true. Then, if we're not processing general integers, we'll use an all-slack basis to solve ... what? Don't see that yet.

Implements CbcHeuristic.

```
7.51.3.7 void CbcHeuristicFPump::setMaximumTime ( double value )
```

Set maximum Time (default off) - also sets starttime to current.

```
7.51.3.8 double CbcHeuristicFPump::maximumTime() const [inline]
```

Get maximum Time (default 0.0 == time limit off)

Definition at line 71 of file CbcHeuristicFPump.hpp.

7.51.3.9 void CbcHeuristicFPump::setFakeCutoff (double value) [inline]

Set fake cutoff (default COIN DBL MAX == off)

Definition at line 75 of file CbcHeuristicFPump.hpp.

7.51.3.10 double CbcHeuristicFPump::fakeCutoff() const [inline]

Get fake cutoff (default 0.0 == off)

Definition at line 79 of file CbcHeuristicFPump.hpp.

7.51.3.11 void CbcHeuristicFPump::setAbsoluteIncrement (double value) [inline]

Set absolute increment (default 0.0 == off)

Definition at line 83 of file CbcHeuristicFPump.hpp.

7.51.3.12 double CbcHeuristicFPump::absoluteIncrement () const [inline]

Get absolute increment (default 0.0 == off)

Definition at line 87 of file CbcHeuristicFPump.hpp.

7.51.3.13 void CbcHeuristicFPump::setRelativeIncrement (double value) [inline]

Set relative increment (default 0.0 == off)

Definition at line 91 of file CbcHeuristicFPump.hpp.

7.51.3.14 double CbcHeuristicFPump::relativeIncrement () const [inline]

Get relative increment (default 0.0 == off)

Definition at line 95 of file CbcHeuristicFPump.hpp.

```
7.51.3.15 void CbcHeuristicFPump::setDefaultRounding ( double value ) [inline]
Set default rounding (default 0.5)
Definition at line 99 of file CbcHeuristicFPump.hpp.
7.51.3.16 double CbcHeuristicFPump::defaultRounding() const [inline]
Get default rounding (default 0.5)
Definition at line 103 of file CbcHeuristicFPump.hpp.
7.51.3.17 void CbcHeuristicFPump::setInitialWeight ( double value ) [inline]
Set initial weight (default 0.0 == off)
Definition at line 107 of file CbcHeuristicFPump.hpp.
7.51.3.18 double CbcHeuristicFPump::initialWeight() const [inline]
Get initial weight (default 0.0 == off)
Definition at line 111 of file CbcHeuristicFPump.hpp.
7.51.3.19 void CbcHeuristicFPump::setWeightFactor ( double value ) [inline]
Set weight factor (default 0.1)
Definition at line 115 of file CbcHeuristicFPump.hpp.
7.51.3.20 double CbcHeuristicFPump::weightFactor() const [inline]
Get weight factor (default 0.1)
Definition at line 119 of file CbcHeuristicFPump.hpp.
7.51.3.21 void CbcHeuristicFPump::setArtificialCost ( double value ) [inline]
Set threshold cost for using original cost - even on continuous (default infinity)
Definition at line 123 of file CbcHeuristicFPump.hpp.
7.51.3.22 double CbcHeuristicFPump::artificialCost ( ) const [inline]
Get threshold cost for using original cost - even on continuous (default infinity)
Definition at line 127 of file CbcHeuristicFPump.hpp.
7.51.3.23 double CbcHeuristicFPump::iterationRatio() const [inline]
Get iteration to size ratio.
Definition at line 131 of file CbcHeuristicFPump.hpp.
7.51.3.24 void CbcHeuristicFPump::setIterationRatio ( double value ) [inline]
Set iteration to size ratio.
Definition at line 135 of file CbcHeuristicFPump.hpp.
```

7.51.3.25 void CbcHeuristicFPump::setMaximumPasses (int value) [inline]

Set maximum passes (default 100)

Definition at line 139 of file CbcHeuristicFPump.hpp.

7.51.3.26 int CbcHeuristicFPump::maximumPasses () const [inline]

Get maximum passes (default 100)

Definition at line 143 of file CbcHeuristicFPump.hpp.

7.51.3.27 void CbcHeuristicFPump::setMaximumRetries (int value) [inline]

Set maximum retries (default 1)

Definition at line 147 of file CbcHeuristicFPump.hpp.

7.51.3.28 int CbcHeuristicFPump::maximumRetries () const [inline]

Get maximum retries (default 1)

Definition at line 151 of file CbcHeuristicFPump.hpp.

7.51.3.29 void CbcHeuristicFPump::setAccumulate (int value) [inline]

Set use of multiple solutions and solves 0 - do not reuse solves, do not accumulate integer solutions for local search 1 - do not reuse solves, accumulate integer solutions for local search 2 - reuse solves, do not accumulate integer solutions for local search 3 - reuse solves, accumulate integer solutions for local search If we add 4 then use second form of problem (with extra rows and variables for general integers) At some point (date?), I added.

And then there are a few bit fields: 4 - something about general integers So my (Ih) guess for 4 was at least in the ballpark, but I'll have to rethink 8 entirely (and it may well not mean the same thing as it did when I added that comment. 8 - determines whether we process general integers

And on 090831, John added

If we add 4 then use second form of problem (with extra rows and variables for general integers) If we add 8 then can run after initial cuts (if no solution)

Definition at line 175 of file CbcHeuristicFPump.hpp.

7.51.3.30 int CbcHeuristicFPump::accumulate() const [inline]

Get accumulation option.

Definition at line 179 of file CbcHeuristicFPump.hpp.

7.51.3.31 void CbcHeuristicFPump::setFixOnReducedCosts (int value) [inline]

Set whether to fix variables on known solution 0 - do not fix 1 - fix integers on reduced costs 2 - fix integers on reduced costs but only on entry.

Definition at line 187 of file CbcHeuristicFPump.hpp.

7.51.3.32 int CbcHeuristicFPump::fixOnReducedCosts () const [inline]

Get reduced cost option.

Definition at line 191 of file CbcHeuristicFPump.hpp.

7.51.3.33 void CbcHeuristicFPump::setReducedCostMultiplier (double value) [inline]

Set reduced cost multiplier 1.0 as normal <1.0 (x) - pretend gap is x* actual gap - just for fixing.

Definition at line 198 of file CbcHeuristicFPump.hpp. 7.51.3.34 double CbcHeuristicFPump::reducedCostMultiplier() const [inline] Get reduced cost multiplier. Definition at line 202 of file CbcHeuristicFPump.hpp. 7.51.4 Member Data Documentation **7.51.4.1 double CbcHeuristicFPump::startTime** [protected] Start time. Definition at line 209 of file CbcHeuristicFPump.hpp. **7.51.4.2 double CbcHeuristicFPump::maximumTime** [protected] Maximum Cpu seconds. Definition at line 211 of file CbcHeuristicFPump.hpp. **7.51.4.3 double CbcHeuristicFPump::fakeCutoff** [protected] Fake cutoff value. If set then better of real cutoff and this used to add a constraint Definition at line 215 of file CbcHeuristicFPump.hpp. **7.51.4.4 double CbcHeuristicFPump::absoluteIncrement** [protected] If positive carry on after solution expecting gain of at least this. Definition at line 217 of file CbcHeuristicFPump.hpp. **7.51.4.5 double CbcHeuristicFPump::relativeIncrement** [protected] If positive carry on after solution expecting gain of at least this times objective. Definition at line 219 of file CbcHeuristicFPump.hpp. **7.51.4.6 double CbcHeuristicFPump::defaultRounding_** [protected] Default is round up if > this. Definition at line 221 of file CbcHeuristicFPump.hpp. **7.51.4.7 double CbcHeuristicFPump::initialWeight** [protected] Initial weight for true objective. Definition at line 223 of file CbcHeuristicFPump.hpp. **7.51.4.8 double CbcHeuristicFPump::weightFactor** [protected] Factor for decreasing weight.

Definition at line 225 of file CbcHeuristicFPump.hpp.

7.51.4.9 double CbcHeuristicFPump::artificialCost_ [protected]

Threshold cost for using original cost - even on continuous.

Definition at line 227 of file CbcHeuristicFPump.hpp.

7.51.4.10 double CbcHeuristicFPump::iterationRatio_ [protected]

If iterationRatio >0 use instead of maximumPasses test is iterations > ratio*(2*nrow+ncol)

Definition at line 230 of file CbcHeuristicFPump.hpp.

7.51.4.11 double CbcHeuristicFPump::reducedCostMultiplier_ [protected]

Reduced cost multiplier 1.0 as normal < 1.0 (x) - pretend gap is x* actual gap - just for fixing.

Definition at line 235 of file CbcHeuristicFPump.hpp.

7.51.4.12 int CbcHeuristicFPump::maximumPasses_ [protected]

Maximum number of passes.

Definition at line 237 of file CbcHeuristicFPump.hpp.

7.51.4.13 int CbcHeuristicFPump::maximumRetries_ [protected]

Maximum number of retries if we find a solution.

If negative we clean out used array

Definition at line 241 of file CbcHeuristicFPump.hpp.

7.51.4.14 int CbcHeuristicFPump::accumulate_ [protected]

Set use of multiple solutions and solves 0 - do not reuse solves, do not accumulate integer solutions for local search 1 - do not reuse solves, accumulate integer solutions for local search 2 - reuse solves, do not accumulate integer solutions for local search 1 - reuse solves, accumulate integer solutions for local search If we add 4 then use second form of problem (with extra rows and variables for general integers) If we do not accumulate solutions then no mini branch and bounds will be done reuse - refers to initial solve after adding in new "cut" If we add 8 then can run after initial cuts (if no solution)

Definition at line 252 of file CbcHeuristicFPump.hpp.

7.51.4.15 int CbcHeuristicFPump::fixOnReducedCosts_ [protected]

Set whether to fix variables on known solution 0 - do not fix 1 - fix integers on reduced costs 2 - fix integers on reduced costs but only on entry.

Definition at line 258 of file CbcHeuristicFPump.hpp.

7.51.4.16 bool CbcHeuristicFPump::roundExpensive_ [protected]

If true round to expensive.

Definition at line 260 of file CbcHeuristicFPump.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicFPump.hpp

7.52 CbcHeuristicGreedyCover Class Reference

Greedy heuristic classes.

#include <CbcHeuristicGreedy.hpp>

Inheritance diagram for CbcHeuristicGreedyCover:



Public Member Functions

- CbcHeuristicGreedyCover ()
- CbcHeuristicGreedyCover (CbcModel &model)
- CbcHeuristicGreedyCover (const CbcHeuristicGreedyCover &)
- ∼CbcHeuristicGreedyCover ()
- virtual CbcHeuristic * clone () const

Clone

CbcHeuristicGreedyCover & operator= (const CbcHeuristicGreedyCover &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

• virtual void validate ()

Validate model i.e. sets when to 0 if necessary (may be NULL)

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

- int algorithm () const
- void setAlgorithm (int value)
- int numberTimes () const
- void setNumberTimes (int value)

Protected Member Functions

void gutsOfConstructor (CbcModel *model)

Guts of constructor from a CbcModel.

Protected Attributes

- CoinPackedMatrix matrix
- int originalNumberRows
- · int algorithm_
- int numberTimes_

Do this many times.

```
7.52.1 Detailed Description
```

Greedy heuristic classes.

Definition at line 13 of file CbcHeuristicGreedy.hpp.

```
7.52.2 Constructor & Destructor Documentation
```

```
7.52.2.1 CbcHeuristicGreedyCover::CbcHeuristicGreedyCover ( )
```

7.52.2.2 CbcHeuristicGreedyCover::CbcHeuristicGreedyCover (CbcModel & model)

7.52.2.3 CbcHeuristicGreedyCover::CbcHeuristicGreedyCover (const CbcHeuristicGreedyCover &)

7.52.2.4 CbcHeuristicGreedyCover::~CbcHeuristicGreedyCover()

7.52.3 Member Function Documentation

7.52.3.1 virtual CbcHeuristic* CbcHeuristicGreedyCover::clone() const [virtual]

Clone.

Implements CbcHeuristic.

7.52.3.2 CbcHeuristicGreedyCover& CbcHeuristicGreedyCover::operator= (const CbcHeuristicGreedyCover & rhs)

Assignment operator.

7.52.3.3 virtual void CbcHeuristicGreedyCover::generateCpp (FILE * *fp*) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristic.

 $\textbf{7.52.3.4} \quad \textbf{virtual void CbcHeuristicGreedyCover::setModel (\textbf{CbcModel}*\textit{model}) \quad [\texttt{virtual}]$

update model (This is needed if cliques update matrix etc)

Reimplemented from CbcHeuristic.

7.52.3.5 virtual int CbcHeuristicGreedyCover::solution (double & objectiveValue, double * newSolution) [virtual]

returns 0 if no solution, 1 if valid solution.

Sets solution values if good, sets objective value (only if good) We leave all variables which are at one at this node of the tree to that value and will initially set all others to zero. We then sort all variables in order of their cost divided by the number of entries in rows which are not yet covered. We randomize that value a bit so that ties will be broken in different ways on different runs of the heuristic. We then choose the best one and set it to one and repeat the exercise.

Implements CbcHeuristic.

```
7.52.3.6 virtual void CbcHeuristicGreedyCover::validate() [virtual]
```

Validate model i.e. sets when to 0 if necessary (may be NULL)

Reimplemented from CbcHeuristic.

```
7.52.3.7 virtual void CbcHeuristicGreedyCover::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.52.3.8 int CbcHeuristicGreedyCover::algorithm ( ) const [inline]
Definition at line 63 of file CbcHeuristicGreedy.hpp.
7.52.3.9 void CbcHeuristicGreedyCover::setAlgorithm (int value) [inline]
Definition at line 66 of file CbcHeuristicGreedy.hpp.
7.52.3.10 int CbcHeuristicGreedyCover::numberTimes ( ) const [inline]
Definition at line 70 of file CbcHeuristicGreedy.hpp.
7.52.3.11 void CbcHeuristicGreedyCover::setNumberTimes (int value) [inline]
Definition at line 73 of file CbcHeuristicGreedy.hpp.
7.52.3.12 void CbcHeuristicGreedyCover::gutsOfConstructor( CbcModel * model ) [protected]
Guts of constructor from a CbcModel.
7.52.4 Member Data Documentation
7.52.4.1 CoinPackedMatrix CbcHeuristicGreedyCover::matrix [protected]
Definition at line 83 of file CbcHeuristicGreedy.hpp.
7.52.4.2 int CbcHeuristicGreedyCover::originalNumberRows_ [protected]
Definition at line 85 of file CbcHeuristicGreedy.hpp.
7.52.4.3 int CbcHeuristicGreedyCover::algorithm_ [protected]
Definition at line 91 of file CbcHeuristicGreedy.hpp.
```

Definition at line 93 of file CbcHeuristicGreedy.hpp.

Do this many times.

The documentation for this class was generated from the following file:


7.52.4.4 int CbcHeuristicGreedyCover::numberTimes_ [protected]

/home/ted/COIN/trunk/Cbc/src/CbcHeuristicGreedy.hpp

7.53 CbcHeuristicGreedyEquality Class Reference

#include <CbcHeuristicGreedy.hpp>

Inheritance diagram for CbcHeuristicGreedyEquality:



Public Member Functions

- CbcHeuristicGreedyEquality ()
- · CbcHeuristicGreedyEquality (CbcModel &model)
- CbcHeuristicGreedyEquality (const CbcHeuristicGreedyEquality &)
- ~CbcHeuristicGreedyEquality ()
- virtual CbcHeuristic * clone () const

Clone.

• CbcHeuristicGreedyEquality & operator= (const CbcHeuristicGreedyEquality &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

• virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

• virtual void validate ()

Validate model i.e. sets when_ to 0 if necessary (may be NULL)

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

- int algorithm () const
- void setAlgorithm (int value)
- void setFraction (double value)
- double fraction () const
- int numberTimes () const
- void setNumberTimes (int value)

Protected Member Functions

void gutsOfConstructor (CbcModel *model)

Guts of constructor from a CbcModel.

Protected Attributes

- CoinPackedMatrix matrix
- double fraction
- · int originalNumberRows_
- · int algorithm_
- int numberTimes_

Do this many times.

```
7.53.1 Detailed Description
```

Definition at line 98 of file CbcHeuristicGreedy.hpp.

```
7.53.2 Constructor & Destructor Documentation
```

```
7.53.2.1 CbcHeuristicGreedyEquality::CbcHeuristicGreedyEquality ( )
```

7.53.2.2 CbcHeuristicGreedyEquality::CbcHeuristicGreedyEquality (CbcModel & model)

7.53.2.3 CbcHeuristicGreedyEquality::CbcHeuristicGreedyEquality (const CbcHeuristicGreedyEquality &)

7.53.2.4 CbcHeuristicGreedyEquality::~CbcHeuristicGreedyEquality ()

7.53.3 Member Function Documentation

7.53.3.1 virtual CbcHeuristic* CbcHeuristicGreedyEquality::clone() const [virtual]

Clone.

Implements CbcHeuristic.

7.53.3.2 CbcHeuristicGreedyEquality& CbcHeuristicGreedyEquality::operator= (const CbcHeuristicGreedyEquality & rhs)

Assignment operator.

7.53.3.3 virtual void CbcHeuristicGreedyEquality::generateCpp (FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristic.

7.53.3.4 virtual void CbcHeuristicGreedyEquality::setModel (CbcModel * model) [virtual]

update model (This is needed if cliques update matrix etc)

Reimplemented from CbcHeuristic.

7.53.3.5 virtual int CbcHeuristicGreedyEquality::solution (double & objectiveValue, double * newSolution) [virtual]

returns 0 if no solution, 1 if valid solution.

Sets solution values if good, sets objective value (only if good) We leave all variables which are at one at this node of the tree to that value and will initially set all others to zero. We then sort all variables in order of their cost divided by the number of entries in rows which are not yet covered. We randomize that value a bit so that ties will be broken in different ways on different runs of the heuristic. We then choose the best one and set it to one and repeat the exercise.

Implements CbcHeuristic.

```
7.53.3.6 virtual void CbcHeuristicGreedyEquality::validate() [virtual]
```

Validate model i.e. sets when to 0 if necessary (may be NULL)

Reimplemented from CbcHeuristic.

7.53.3.7 virtual void CbcHeuristicGreedyEquality::resetModel (CbcModel * model) [virtual]

Resets stuff if model changes.

```
Implements CbcHeuristic.
7.53.3.8 int CbcHeuristicGreedyEquality::algorithm ( ) const [inline]
Definition at line 148 of file CbcHeuristicGreedy.hpp.
7.53.3.9 void CbcHeuristicGreedyEquality::setAlgorithm (int value) [inline]
Definition at line 151 of file CbcHeuristicGreedy.hpp.
7.53.3.10 void CbcHeuristicGreedyEquality::setFraction ( double value ) [inline]
Definition at line 155 of file CbcHeuristicGreedy.hpp.
7.53.3.11 double CbcHeuristicGreedyEquality::fraction ( ) const [inline]
Definition at line 158 of file CbcHeuristicGreedy.hpp.
7.53.3.12 int CbcHeuristicGreedyEquality::numberTimes ( ) const [inline]
Definition at line 162 of file CbcHeuristicGreedy.hpp.
7.53.3.13 void CbcHeuristicGreedyEquality::setNumberTimes (int value) [inline]
Definition at line 165 of file CbcHeuristicGreedy.hpp.
7.53.3.14 void CbcHeuristicGreedyEquality::gutsOfConstructor ( CbcModel * model ) [protected]
Guts of constructor from a CbcModel.
7.53.4 Member Data Documentation
7.53.4.1 CoinPackedMatrix CbcHeuristicGreedyEquality::matrix [protected]
Definition at line 174 of file CbcHeuristicGreedy.hpp.
7.53.4.2 double CbcHeuristicGreedyEquality::fraction [protected]
Definition at line 176 of file CbcHeuristicGreedy.hpp.
7.53.4.3 int CbcHeuristicGreedyEquality::originalNumberRows_ [protected]
Definition at line 178 of file CbcHeuristicGreedy.hpp.
7.53.4.4 int CbcHeuristicGreedyEquality::algorithm_ [protected]
Definition at line 184 of file CbcHeuristicGreedy.hpp.
7.53.4.5 int CbcHeuristicGreedyEquality::numberTimes_ [protected]
Do this many times.
Definition at line 186 of file CbcHeuristicGreedy.hpp.
The documentation for this class was generated from the following file:
```


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicGreedy.hpp

7.54 CbcHeuristicGreedySOS Class Reference

Greedy heuristic for SOS and L rows (and positive elements)

#include <CbcHeuristicGreedy.hpp>

Inheritance diagram for CbcHeuristicGreedySOS:



Public Member Functions

- CbcHeuristicGreedySOS ()
- CbcHeuristicGreedySOS (CbcModel &model)
- CbcHeuristicGreedySOS (const CbcHeuristicGreedySOS &)
- ∼CbcHeuristicGreedySOS ()
- virtual CbcHeuristic * clone () const

Clone.

CbcHeuristicGreedySOS & operator= (const CbcHeuristicGreedySOS &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

• virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

• virtual void validate ()

Validate model i.e. sets when_ to 0 if necessary (may be NULL)

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

- int algorithm () const
- · void setAlgorithm (int value)
- int numberTimes () const
- · void setNumberTimes (int value)

Protected Member Functions

void gutsOfConstructor (CbcModel *model)

Guts of constructor from a CbcModel.

Protected Attributes

- double * originalRhs_
- CoinPackedMatrix matrix_
- int originalNumberRows

- · int algorithm_
- int numberTimes

Do this many times.

7.54.1 Detailed Description

Greedy heuristic for SOS and L rows (and positive elements)

Definition at line 193 of file CbcHeuristicGreedy.hpp.

- 7.54.2 Constructor & Destructor Documentation
- 7.54.2.1 CbcHeuristicGreedySOS::CbcHeuristicGreedySOS ()
- 7.54.2.2 CbcHeuristicGreedySOS::CbcHeuristicGreedySOS (CbcModel & model)
- 7.54.2.3 CbcHeuristicGreedySOS::CbcHeuristicGreedySOS (const CbcHeuristicGreedySOS &)
- 7.54.2.4 CbcHeuristicGreedySOS::~CbcHeuristicGreedySOS()
- 7.54.3 Member Function Documentation
- 7.54.3.1 virtual CbcHeuristic* CbcHeuristicGreedySOS::clone()const [virtual]

Clone.

Implements CbcHeuristic.

7.54.3.2 CbcHeuristicGreedySOS& CbcHeuristicGreedySOS::operator=(const CbcHeuristicGreedySOS & rhs)

Assignment operator.

7.54.3.3 virtual void CbcHeuristicGreedySOS::generateCpp (FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristic.

7.54.3.4 virtual void CbcHeuristicGreedySOS::setModel (CbcModel * model) [virtual]

update model (This is needed if cliques update matrix etc)

Reimplemented from CbcHeuristic.

7.54.3.5 virtual int CbcHeuristicGreedySOS::solution (double & objectiveValue, double * newSolution) [virtual]

returns 0 if no solution. 1 if valid solution.

Sets solution values if good, sets objective value (only if good) We leave all variables which are at one at this node of the tree to that value and will initially set all others to zero. We then sort all variables in order of their cost divided by the number of entries in rows which are not yet covered. We randomize that value a bit so that ties will be broken in different ways on different runs of the heuristic. We then choose the best one and set it to one and repeat the exercise.

Implements CbcHeuristic.

7.54.3.6 virtual void CbcHeuristicGreedySOS::validate() [virtual]

Validate model i.e. sets when to 0 if necessary (may be NULL)

```
Reimplemented from CbcHeuristic.
7.54.3.7 virtual void CbcHeuristicGreedySOS::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.54.3.8 int CbcHeuristicGreedySOS::algorithm ( ) const [inline]
Definition at line 245 of file CbcHeuristicGreedy.hpp.
7.54.3.9 void CbcHeuristicGreedySOS::setAlgorithm (int value) [inline]
Definition at line 248 of file CbcHeuristicGreedy.hpp.
7.54.3.10 int CbcHeuristicGreedySOS::numberTimes ( ) const [inline]
Definition at line 252 of file CbcHeuristicGreedy.hpp.
7.54.3.11 void CbcHeuristicGreedySOS::setNumberTimes ( int value ) [inline]
Definition at line 255 of file CbcHeuristicGreedy.hpp.
7.54.3.12 void CbcHeuristicGreedySOS::gutsOfConstructor ( CbcModel * model ) [protected]
Guts of constructor from a CbcModel.
7.54.4 Member Data Documentation
7.54.4.1 double* CbcHeuristicGreedySOS::originalRhs_ [protected]
Definition at line 265 of file CbcHeuristicGreedy.hpp.
7.54.4.2 CoinPackedMatrix CbcHeuristicGreedySOS::matrix [protected]
Definition at line 267 of file CbcHeuristicGreedy.hpp.
7.54.4.3 int CbcHeuristicGreedySOS::originalNumberRows_ [protected]
Definition at line 269 of file CbcHeuristicGreedy.hpp.
7.54.4.4 int CbcHeuristicGreedySOS::algorithm_ [protected]
Definition at line 272 of file CbcHeuristicGreedy.hpp.
7.54.4.5 int CbcHeuristicGreedySOS::numberTimes_ [protected]
Do this many times.
Definition at line 274 of file CbcHeuristicGreedy.hpp.
```

/home/ted/COIN/trunk/Cbc/src/CbcHeuristicGreedy.hpp


The documentation for this class was generated from the following file:

7.55 CbcHeuristicJustOne Class Reference

Just One class - this chooses one at random.

#include <CbcHeuristic.hpp>

Inheritance diagram for CbcHeuristicJustOne:



Public Member Functions

- CbcHeuristicJustOne ()
- CbcHeuristicJustOne (CbcModel &model)
- CbcHeuristicJustOne (const CbcHeuristicJustOne &)
- ∼CbcHeuristicJustOne ()
- virtual CbcHeuristicJustOne * clone () const

Clone

CbcHeuristicJustOne & operator= (const CbcHeuristicJustOne &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value (only if good) This is called after cuts have been added - so can not add cuts This does Fractional Diving

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

• virtual bool selectVariableToBranch (OsiSolverInterface *, const double *, int &, int &)

Selects the next variable to branch on.

• virtual void validate ()

Validate model i.e. sets when to 0 if necessary (may be NULL)

void addHeuristic (const CbcHeuristic *heuristic, double probability)

Adds an heuristic with probability.

void normalizeProbabilities ()

Normalize probabilities.

Protected Attributes

- double * probabilities_
- CbcHeuristic ** heuristic
- · int numberHeuristics_

```
7.55.1 Detailed Description
Just One class - this chooses one at random.
Definition at line 601 of file CbcHeuristic.hpp.
7.55.2 Constructor & Destructor Documentation
7.55.2.1 CbcHeuristicJustOne::CbcHeuristicJustOne ( )
7.55.2.2 CbcHeuristicJustOne::CbcHeuristicJustOne ( CbcModel & model )
7.55.2.3 CbcHeuristicJustOne::CbcHeuristicJustOne ( const CbcHeuristicJustOne & )
7.55.2.4 CbcHeuristicJustOne:: ~ CbcHeuristicJustOne ( )
7.55.3 Member Function Documentation
7.55.3.1 virtual CbcHeuristicJustOne* CbcHeuristicJustOne::clone( ) const [virtual]
Clone.
Implements CbcHeuristic.
7.55.3.2 CbcHeuristicJustOne& CbcHeuristicJustOne::operator=( const CbcHeuristicJustOne & rhs )
Assignment operator.
7.55.3.3 virtual void CbcHeuristicJustOne::generateCpp (FILE * fp ) [virtual]
Create C++ lines to get to current state.
Reimplemented from CbcHeuristic.
7.55.3.4 virtual int CbcHeuristicJustOne::solution ( double & objectiveValue, double * newSolution ) [virtual]
returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets
objective value (only if good) This is called after cuts have been added - so can not add cuts This does Fractional Diving
Implements CbcHeuristic.
7.55.3.5 virtual void CbcHeuristicJustOne::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.55.3.6 virtual void CbcHeuristicJustOne::setModel ( CbcModel * model ) [virtual]
update model (This is needed if cliques update matrix etc)
Reimplemented from CbcHeuristic.
7.55.3.7 virtual bool CbcHeuristicJustOne::selectVariableToBranch ( OsiSolverInterface * , const double * , int & , int & )
```

Selects the next variable to branch on.

Returns true if all the fractional variables can be trivially rounded. Returns false, if there is at least one fractional variable

[inline], [virtual]

that is not trivially roundable. In this case, the bestColumn returned will not be trivially roundable. This is dummy as never called

Definition at line 645 of file CbcHeuristic.hpp.

7.55.3.8 virtual void CbcHeuristicJustOne::validate() [virtual]

Validate model i.e. sets when to 0 if necessary (may be NULL)

Reimplemented from CbcHeuristic.

7.55.3.9 void CbcHeuristicJustOne::addHeuristic (const CbcHeuristic * heuristic, double probability)

Adds an heuristic with probability.

7.55.3.10 void CbcHeuristicJustOne::normalizeProbabilities ()

Normalize probabilities.

7.55.4 Member Data Documentation

7.55.4.1 double* CbcHeuristicJustOne::probabilities_ [protected]

Definition at line 661 of file CbcHeuristic.hpp.

7.55.4.2 CbcHeuristic** **CbcHeuristicJustOne**::heuristic_ [protected]

Definition at line 664 of file CbcHeuristic.hpp.

 $\textbf{7.55.4.3} \quad \textbf{int CbcHeuristicJustOne::numberHeuristics} \quad \texttt{[protected]}$

Definition at line 667 of file CbcHeuristic.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristic.hpp

7.56 CbcHeuristicLocal Class Reference

LocalSearch class.

#include <CbcHeuristicLocal.hpp>

Inheritance diagram for CbcHeuristicLocal:



Public Member Functions

- CbcHeuristicLocal ()
- CbcHeuristicLocal (CbcModel &model)

7.56 CbcHeuristicLocal Class Reference CbcHeuristicLocal (const CbcHeuristicLocal &) ∼CbcHeuristicLocal () virtual CbcHeuristic * clone () const Clone. CbcHeuristicLocal & operator= (const CbcHeuristicLocal &rhs) Assignment operator. virtual void generateCpp (FILE *fp) Create C++ lines to get to current state. virtual void resetModel (CbcModel *model) Resets stuff if model changes. virtual void setModel (CbcModel *model) update model (This is needed if cliques update matrix etc) virtual int solution (double &objectiveValue, double *newSolution) returns 0 if no solution, 1 if valid solution. int solutionFix (double &objectiveValue, double *newSolution, const int *keep) This version fixes stuff and does IP. void setSearchType (int value) Sets type of search. int * used () const Used array so we can set. **Protected Attributes** CoinPackedMatrix matrix int numberSolutions_ int swap int * used Whether a variable has been in a solution (also when)

7.56.1 Detailed Description

LocalSearch class.

Definition at line 13 of file CbcHeuristicLocal.hpp.

```
7.56.2 Constructor & Destructor Documentation
7.56.2.1 CbcHeuristicLocal::CbcHeuristicLocal ( )
7.56.2.2 CbcHeuristicLocal::CbcHeuristicLocal ( CbcModel & model )
7.56.2.3 CbcHeuristicLocal::CbcHeuristicLocal ( const CbcHeuristicLocal & )
7.56.2.4 CbcHeuristicLocal::~CbcHeuristicLocal()
7.56.3 Member Function Documentation
7.56.3.1 virtual CbcHeuristic* CbcHeuristicLocal::clone() const [virtual]
```

Clone.

Implements CbcHeuristic.

```
7.56.3.2 CbcHeuristicLocal & CbcHeuristicLocal & rhs )
Assignment operator.
7.56.3.3 virtual void CbcHeuristicLocal::generateCpp (FILE * fp ) [virtual]
Create C++ lines to get to current state.
Reimplemented from CbcHeuristic.
7.56.3.4 virtual void CbcHeuristicLocal::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.56.3.5 virtual void CbcHeuristicLocal::setModel ( CbcModel * model ) [virtual]
update model (This is needed if cliques update matrix etc)
Reimplemented from CbcHeuristic.
7.56.3.6 virtual int CbcHeuristicLocal::solution ( double & objectiveValue, double * newSolution ) [virtual]
returns 0 if no solution, 1 if valid solution.
Sets solution values if good, sets objective value (only if good) This is called after cuts have been added - so can not
add cuts First tries setting a variable to better value. If feasible then tries setting others. If not feasible then tries swaps
This first version does not do LP's and does swaps of two integer variables. Later versions could do Lps.
Implements CbcHeuristic.
7.56.3.7 int CbcHeuristicLocal::solutionFix ( double & objectiveValue, double * newSolution, const int * keep )
This version fixes stuff and does IP.
7.56.3.8 void CbcHeuristicLocal::setSearchType (int value) [inline]
Sets type of search.
Definition at line 65 of file CbcHeuristicLocal.hpp.
7.56.3.9 int* CbcHeuristicLocal::used() const [inline]
Used array so we can set.
Definition at line 69 of file CbcHeuristicLocal.hpp.
7.56.4 Member Data Documentation
7.56.4.1 CoinPackedMatrix CbcHeuristicLocal::matrix_ [protected]
Definition at line 77 of file CbcHeuristicLocal.hpp.
7.56.4.2 int CbcHeuristicLocal::numberSolutions_ [protected]
Definition at line 80 of file CbcHeuristicLocal.hpp.
```

7.56.4.3 int CbcHeuristicLocal::swap_ [protected]

Definition at line 82 of file CbcHeuristicLocal.hpp.

7.56.4.4 int* CbcHeuristicLocal::used_ [protected]

Whether a variable has been in a solution (also when)

Definition at line 84 of file CbcHeuristicLocal.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicLocal.hpp

7.57 CbcHeuristicNaive Class Reference

Naive class a) Fix all ints as close to zero as possible b) Fix all ints with nonzero costs and < large to zero c) Put bounds round continuous and UIs and maximize.

#include <CbcHeuristicLocal.hpp>

Inheritance diagram for CbcHeuristicNaive:



Public Member Functions

- CbcHeuristicNaive ()
- CbcHeuristicNaive (CbcModel &model)
- CbcHeuristicNaive (const CbcHeuristicNaive &)
- ∼CbcHeuristicNaive ()
- virtual CbcHeuristic * clone () const

Clone.

CbcHeuristicNaive & operator= (const CbcHeuristicNaive &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

• virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

void setLargeValue (double value)

Sets large cost value.

double largeValue () const

Gets large cost value.

Protected Attributes

double large

Data Large value.

7.57.1 Detailed Description

Naive class a) Fix all ints as close to zero as possible b) Fix all ints with nonzero costs and < large to zero c) Put bounds round continuous and UIs and maximize.

Definition at line 154 of file CbcHeuristicLocal.hpp.

Sets solution values if good, sets objective value (only if good)

```
7.57.2 Constructor & Destructor Documentation
7.57.2.1 CbcHeuristicNaive::CbcHeuristicNaive ( )
7.57.2.2 CbcHeuristicNaive::CbcHeuristicNaive ( CbcModel & model )
7.57.2.3 CbcHeuristicNaive::CbcHeuristicNaive ( const CbcHeuristicNaive & )
7.57.2.4 CbcHeuristicNaive:: ~ CbcHeuristicNaive ( )
7.57.3 Member Function Documentation
7.57.3.1 virtual CbcHeuristic* CbcHeuristicNaive::clone( )const [virtual]
Clone.
Implements CbcHeuristic.
7.57.3.2 CbcHeuristicNaive & CbcHeuristicNaive & rhs )
Assignment operator.
7.57.3.3 virtual void CbcHeuristicNaive::generateCpp ( FILE * fp ) [virtual]
Create C++ lines to get to current state.
Reimplemented from CbcHeuristic.
7.57.3.4 virtual void CbcHeuristicNaive::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.57.3.5 virtual void CbcHeuristicNaive::setModel ( CbcModel * model ) [virtual]
update model (This is needed if cliques update matrix etc)
Reimplemented from CbcHeuristic.
7.57.3.6 virtual int CbcHeuristicNaive::solution ( double & objectiveValue, double * newSolution ) [virtual]
returns 0 if no solution, 1 if valid solution.
```

Implements CbcHeuristic.

7.57.3.7 void CbcHeuristicNaive::setLargeValue (double value) [inline]

Sets large cost value.

Definition at line 194 of file CbcHeuristicLocal.hpp.

7.57.3.8 double CbcHeuristicNaive::largeValue() const [inline]

Gets large cost value.

Definition at line 198 of file CbcHeuristicLocal.hpp.

7.57.4 Member Data Documentation

7.57.4.1 double CbcHeuristicNaive::large [protected]

Data Large value.

Definition at line 205 of file CbcHeuristicLocal.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcHeuristicLocal.hpp

7.58 CbcHeuristicNode Class Reference

A class describing the branching decisions that were made to get to the node where a heuristic was invoked from.

```
#include <CbcHeuristic.hpp>
```

Public Member Functions

- CbcHeuristicNode (CbcModel &model)
- CbcHeuristicNode (const CbcHeuristicNode &rhs)
- ∼CbcHeuristicNode ()
- double distance (const CbcHeuristicNode *node) const
- double minDistance (const CbcHeuristicNodeList &nodeList) const
- · bool minDistanceIsSmall (const CbcHeuristicNodeList &nodeList, const double threshold) const
- double avgDistance (const CbcHeuristicNodeList &nodeList) const

7.58.1 Detailed Description

A class describing the branching decisions that were made to get to the node where a heuristic was invoked from. Definition at line 28 of file CbcHeuristic.hpp.

- 7.58.2 Constructor & Destructor Documentation
- 7.58.2.1 CbcHeuristicNode::CbcHeuristicNode (CbcModel & model)
- 7.58.2.2 CbcHeuristicNode::CbcHeuristicNode (const CbcHeuristicNode & rhs)

- 7.58.2.3 CbcHeuristicNode::~CbcHeuristicNode()
- 7.58.3 Member Function Documentation
- 7.58.3.1 double CbcHeuristicNode::distance (const CbcHeuristicNode * node) const
- 7.58.3.2 double CbcHeuristicNode::minDistance (const CbcHeuristicNodeList & nodeList) const
- 7.58.3.3 bool CbcHeuristicNode::minDistancelsSmall (const CbcHeuristicNodeList & nodeList, const double threshold) const
- 7.58.3.4 double CbcHeuristicNode::avgDistance (const CbcHeuristicNodeList & nodeList) const

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcHeuristic.hpp

7.59 CbcHeuristicNodeList Class Reference

```
#include <CbcHeuristic.hpp>
```

Public Member Functions

- CbcHeuristicNodeList ()
- CbcHeuristicNodeList (const CbcHeuristicNodeList &rhs)
- CbcHeuristicNodeList & operator= (const CbcHeuristicNodeList &rhs)
- ∼CbcHeuristicNodeList ()
- void append (CbcHeuristicNode *&node)
- void append (const CbcHeuristicNodeList &nodes)
- const CbcHeuristicNode * node (int i) const
- int size () const

7.59.1 Detailed Description

Definition at line 52 of file CbcHeuristic.hpp.

- 7.59.2 Constructor & Destructor Documentation
- 7.59.2.1 CbcHeuristicNodeList::CbcHeuristicNodeList() [inline]

Definition at line 59 of file CbcHeuristic.hpp.

- 7.59.2.2 CbcHeuristicNodeList::CbcHeuristicNodeList (const CbcHeuristicNodeList & rhs)
- 7.59.2.3 CbcHeuristicNodeList::~CbcHeuristicNodeList()
- 7.59.3 Member Function Documentation
- 7.59.3.1 CbcHeuristicNodeList & CbcHeuristicNodeList::operator=(const CbcHeuristicNodeList & rhs)
- 7.59.3.2 void CbcHeuristicNodeList::append (CbcHeuristicNode *& node)

7.59.3.3 void CbcHeuristicNodeList::append (const CbcHeuristicNodeList & nodes)

7.59.3.4 const CbcHeuristicNode* CbcHeuristicNodeList::node(inti)const [inline]

Definition at line 66 of file CbcHeuristic.hpp.

7.59.3.5 int CbcHeuristicNodeList::size () const [inline]

Definition at line 69 of file CbcHeuristic.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristic.hpp

7.60 CbcHeuristicPartial Class Reference

Partial solution class If user knows a partial solution this tries to get an integer solution it uses hotstart information.

#include <CbcHeuristic.hpp>

Inheritance diagram for CbcHeuristicPartial:



Public Member Functions

- CbcHeuristicPartial ()
- CbcHeuristicPartial (CbcModel &model, int fixPriority=10000, int numberNodes=200)

Constructor with model - assumed before cuts Fixes all variables with priority <= given and does given number of nodes.

- CbcHeuristicPartial (const CbcHeuristicPartial &)
- ∼CbcHeuristicPartial ()
- CbcHeuristicPartial & operator= (const CbcHeuristicPartial &rhs)

Assignment operator.

• virtual CbcHeuristic * clone () const

Clone.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

• virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value (only if good) This is called after cuts have been added - so can not add cuts

virtual void validate ()

Validate model i.e. sets when to 0 if necessary (may be NULL)

void setFixPriority (int value)

Set priority level.

virtual bool shouldHeurRun (int whereFrom)

Check whether the heuristic should run at all.

update model (This is needed if cliques update matrix etc)

Reimplemented from CbcHeuristic.

Protected Attributes

int fixPriority

7.60.1 Detailed Description

Partial solution class If user knows a partial solution this tries to get an integer solution it uses hotstart information. Definition at line 489 of file CbcHeuristic.hpp.

```
7.60.2 Constructor & Destructor Documentation
7.60.2.1 CbcHeuristicPartial::CbcHeuristicPartial()
7.60.2.2 CbcHeuristicPartial::CbcHeuristicPartial ( CbcModel & model, int fixPriority = 10000, int numberNodes = 200)
Constructor with model - assumed before cuts Fixes all variables with priority <= given and does given number of nodes.
7.60.2.3 CbcHeuristicPartial::CbcHeuristicPartial ( const CbcHeuristicPartial & )
7.60.2.4 CbcHeuristicPartial:: ~ CbcHeuristicPartial ( )
7.60.3 Member Function Documentation
7.60.3.1 CbcHeuristicPartial& CbcHeuristicPartial & rhs )
Assignment operator.
7.60.3.2 virtual CbcHeuristic* CbcHeuristicPartial::clone() const [virtual]
Clone.
Implements CbcHeuristic.
7.60.3.3 virtual void CbcHeuristicPartial::generateCpp (FILE * fp ) [virtual]
Create C++ lines to get to current state.
Reimplemented from CbcHeuristic.
7.60.3.4 virtual void CbcHeuristicPartial::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.60.3.5 virtual void CbcHeuristicPartial::setModel ( CbcModel * model ) [virtual]
```

7.60.3.6 virtual int CbcHeuristicPartial::solution (double & objectiveValue, double * newSolution) [virtual]

returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value (only if good) This is called after cuts have been added - so can not add cuts

Implements CbcHeuristic.

7.60.3.7 virtual void CbcHeuristicPartial::validate() [virtual]

Validate model i.e. sets when_ to 0 if necessary (may be NULL)

Reimplemented from CbcHeuristic.

7.60.3.8 void CbcHeuristicPartial::setFixPriority (int value) [inline]

Set priority level.

Definition at line 534 of file CbcHeuristic.hpp.

7.60.3.9 virtual bool CbcHeuristicPartial::shouldHeurRun (int whereFrom) [virtual]

Check whether the heuristic should run at all.

Reimplemented from CbcHeuristic.

7.60.4 Member Data Documentation

7.60.4.1 int CbcHeuristicPartial::fixPriority_ [protected]

Definition at line 545 of file CbcHeuristic.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristic.hpp

7.61 CbcHeuristicPivotAndFix Class Reference

LocalSearch class.

#include <CbcHeuristicPivotAndFix.hpp>

Inheritance diagram for CbcHeuristicPivotAndFix:



Public Member Functions

- CbcHeuristicPivotAndFix ()
- CbcHeuristicPivotAndFix (CbcModel &model)
- CbcHeuristicPivotAndFix (const CbcHeuristicPivotAndFix &)
- ∼CbcHeuristicPivotAndFix ()

• virtual CbcHeuristic * clone () const

```
Clone.

    CbcHeuristicPivotAndFix & operator= (const CbcHeuristicPivotAndFix &rhs)

          Assignment operator.

    virtual void generateCpp (FILE *fp)

          Create C++ lines to get to current state.

    virtual void resetModel (CbcModel *model)

          Resets stuff if model changes.

    virtual void setModel (CbcModel *model)

          update model (This is needed if cliques update matrix etc)

    virtual int solution (double &objectiveValue, double *newSolution)

          returns 0 if no solution, 1 if valid solution.
Additional Inherited Members
7.61.1 Detailed Description
LocalSearch class.
Definition at line 13 of file CbcHeuristicPivotAndFix.hpp.
7.61.2 Constructor & Destructor Documentation
7.61.2.1 CbcHeuristicPivotAndFix::CbcHeuristicPivotAndFix ( )
7.61.2.2 CbcHeuristicPivotAndFix::CbcHeuristicPivotAndFix ( CbcModel & model )
7.61.2.3 CbcHeuristicPivotAndFix::CbcHeuristicPivotAndFix ( const CbcHeuristicPivotAndFix & )
7.61.2.4 CbcHeuristicPivotAndFix::~CbcHeuristicPivotAndFix()
7.61.3 Member Function Documentation
7.61.3.1 virtual CbcHeuristic* CbcHeuristicPivotAndFix::clone() const [virtual]
Clone.
Implements CbcHeuristic.
7.61.3.2 CbcHeuristicPivotAndFix&CbcHeuristicPivotAndFix::operator=( const CbcHeuristicPivotAndFix & rhs )
Assignment operator.
7.61.3.3 virtual void CbcHeuristicPivotAndFix::generateCpp (FILE * fp ) [virtual]
Create C++ lines to get to current state.
Reimplemented from CbcHeuristic.
7.61.3.4 virtual void CbcHeuristicPivotAndFix::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
```

7.61.3.5 virtual void CbcHeuristicPivotAndFix::setModel (CbcModel * model) [virtual]

update model (This is needed if cliques update matrix etc)

Reimplemented from CbcHeuristic.

7.61.3.6 virtual int CbcHeuristicPivotAndFix::solution (double & objectiveValue, double * newSolution) [virtual]

returns 0 if no solution, 1 if valid solution.

Sets solution values if good, sets objective value (only if good) needs comments Implements CbcHeuristic.


The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcHeuristicPivotAndFix.hpp

7.62 CbcHeuristicProximity Class Reference

#include <CbcHeuristicLocal.hpp>

Inheritance diagram for CbcHeuristicProximity:



Public Member Functions

- CbcHeuristicProximity ()
- CbcHeuristicProximity (CbcModel &model)
- CbcHeuristicProximity (const CbcHeuristicProximity &)
- ∼CbcHeuristicProximity ()
- virtual CbcHeuristic * clone () const

Clone

• CbcHeuristicProximity & operator= (const CbcHeuristicProximity &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

· void setIncrement (double value)

Set extra increment.

int * used () const

Used array so we can set.

Protected Attributes

```
    double increment

          Increment to use if no change.

    CbcHeuristicFPump * feasibilityPump

          Copy of Feasibility pump.
    int numberSolutions_
          Number of solutions so we only do after new solution.
    int * used
          Whether a variable has been in a solution (also when)
7.62.1 Detailed Description
Definition at line 90 of file CbcHeuristicLocal.hpp.
7.62.2
       Constructor & Destructor Documentation
7.62.2.1 CbcHeuristicProximity::CbcHeuristicProximity ( )
7.62.2.2 CbcHeuristicProximity::CbcHeuristicProximity ( CbcModel & model )
7.62.2.3 CbcHeuristicProximity::CbcHeuristicProximity ( const CbcHeuristicProximity & )
7.62.2.4 CbcHeuristicProximity::~CbcHeuristicProximity()
7.62.3 Member Function Documentation
7.62.3.1 virtual CbcHeuristic* CbcHeuristicProximity::clone( ) const [virtual]
Clone.
Implements CbcHeuristic.
7.62.3.2 CbcHeuristicProximity& CbcHeuristicProximity::operator= ( const CbcHeuristicProximity & rhs )
Assignment operator.
7.62.3.3 virtual void CbcHeuristicProximity::generateCpp (FILE * fp ) [virtual]
Create C++ lines to get to current state.
Reimplemented from CbcHeuristic.
7.62.3.4 virtual void CbcHeuristicProximity::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.62.3.5 virtual void CbcHeuristicProximity::setModel ( CbcModel * model ) [virtual]
update model (This is needed if cliques update matrix etc)
Reimplemented from CbcHeuristic.
```

7.62.3.6 virtual int CbcHeuristicProximity::solution (double & objectiveValue, double * newSolution) [virtual]

returns 0 if no solution, 1 if valid solution.

Sets solution values if good, sets objective value (only if good)

Implements CbcHeuristic.

7.62.3.7 void CbcHeuristicProximity::setIncrement (double value) [inline]

Set extra increment.

Definition at line 128 of file CbcHeuristicLocal.hpp.

7.62.3.8 int* CbcHeuristicProximity::used() const [inline]

Used array so we can set.

Definition at line 131 of file CbcHeuristicLocal.hpp.

7.62.4 Member Data Documentation

7.62.4.1 double CbcHeuristicProximity::increment [protected]

Increment to use if no change.

Definition at line 138 of file CbcHeuristicLocal.hpp.

7.62.4.2 CbcHeuristicFPump* CbcHeuristicProximity::feasibilityPump_ [protected]

Copy of Feasibility pump.

Definition at line 140 of file CbcHeuristicLocal.hpp.

7.62.4.3 int CbcHeuristicProximity::numberSolutions_ [protected]

Number of solutions so we only do after new solution.

Definition at line 142 of file CbcHeuristicLocal.hpp.

7.62.4.4 int* CbcHeuristicProximity::used_ [protected]

Whether a variable has been in a solution (also when)

Definition at line 144 of file CbcHeuristicLocal.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicLocal.hpp

7.63 CbcHeuristicRandRound Class Reference

LocalSearch class.

#include <CbcHeuristicRandRound.hpp>

Inheritance diagram for CbcHeuristicRandRound:



Public Member Functions

- CbcHeuristicRandRound ()
- CbcHeuristicRandRound (CbcModel &model)
- CbcHeuristicRandRound (const CbcHeuristicRandRound &)
- ∼CbcHeuristicRandRound ()
- virtual CbcHeuristic * clone () const

Clone.

• CbcHeuristicRandRound & operator= (const CbcHeuristicRandRound &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

Additional Inherited Members

7.63.1 Detailed Description

LocalSearch class.

Definition at line 13 of file CbcHeuristicRandRound.hpp.

- 7.63.2 Constructor & Destructor Documentation
- 7.63.2.1 CbcHeuristicRandRound::CbcHeuristicRandRound()
- 7.63.2.2 CbcHeuristicRandRound::CbcHeuristicRandRound (CbcModel & model)
- 7.63.2.3 CbcHeuristicRandRound::CbcHeuristicRandRound (const CbcHeuristicRandRound &)
- 7.63.2.4 CbcHeuristicRandRound:: ~ CbcHeuristicRandRound ()
- 7.63.3 Member Function Documentation
- 7.63.3.1 virtual CbcHeuristic* CbcHeuristicRandRound::clone() const [virtual]

Clone.

Implements CbcHeuristic.

7.63.3.2 CbcHeuristicRandRound& CbcHeuristicRandRound::operator= (const CbcHeuristicRandRound & rhs)

Assignment operator.

7.63.3.3 virtual void CbcHeuristicRandRound::generateCpp(FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristic.

7.63.3.4 virtual void CbcHeuristicRandRound::resetModel (CbcModel * model) [virtual]

Resets stuff if model changes.

Implements CbcHeuristic.

7.63.3.5 virtual void CbcHeuristicRandRound::setModel (CbcModel * model) [virtual]

update model (This is needed if cliques update matrix etc)

Reimplemented from CbcHeuristic.

7.63.3.6 virtual int CbcHeuristicRandRound::solution (double & objectiveValue, double * newSolution) [virtual]

returns 0 if no solution, 1 if valid solution.

Sets solution values if good, sets objective value (only if good) needs comments

Implements CbcHeuristic.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicRandRound.hpp

7.64 CbcHeuristicRENS Class Reference

LocalSearch class.

#include <CbcHeuristicRENS.hpp>

Inheritance diagram for CbcHeuristicRENS:



Public Member Functions

- CbcHeuristicRENS ()
- CbcHeuristicRENS (CbcModel &model)
- CbcHeuristicRENS (const CbcHeuristicRENS &)
- ∼CbcHeuristicRENS ()
- virtual CbcHeuristic * clone () const

Clone

CbcHeuristicRENS & operator= (const CbcHeuristicRENS &rhs)

Assignment operator.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

void setRensType (int value)

Set type.

Protected Attributes

int numberTries

Number of tries.

int rensType_

Type 0 - fix at LB 1 - fix on dj 2 - fix at UB as well 3 - fix on 0.01*average dj add 16 to allow two tries.

7.64.1 Detailed Description

LocalSearch class.

Definition at line 16 of file CbcHeuristicRENS.hpp.

```
7.64.2 Constructor & Destructor Documentation
```

```
7.64.2.1 CbcHeuristicRENS::CbcHeuristicRENS ( )
```

7.64.2.2 CbcHeuristicRENS::CbcHeuristicRENS (CbcModel & model)

7.64.2.3 CbcHeuristicRENS::CbcHeuristicRENS (const CbcHeuristicRENS &)

7.64.2.4 CbcHeuristicRENS::~CbcHeuristicRENS()

7.64.3 Member Function Documentation

7.64.3.1 virtual CbcHeuristic* CbcHeuristicRENS::clone() const [virtual]

Clone.

Implements CbcHeuristic.

7.64.3.2 CbcHeuristicRENS& CbcHeuristicRENS::operator= (const CbcHeuristicRENS & rhs)

Assignment operator.

7.64.3.3 virtual void CbcHeuristicRENS::resetModel (CbcModel * model) [virtual]

Resets stuff if model changes.

Implements CbcHeuristic.

7.64.3.4 virtual void CbcHeuristicRENS::setModel (CbcModel * model) [virtual]

update model (This is needed if cliques update matrix etc)

Reimplemented from CbcHeuristic.

7.64.3.5 virtual int CbcHeuristicRENS::solution (double & objectiveValue, double * newSolution) [virtual]

returns 0 if no solution, 1 if valid solution.

Sets solution values if good, sets objective value (only if good) This does Relaxation Extension Neighborhood Search Does not run if when <2 and a solution exists

Implements CbcHeuristic.

7.64.3.6 void CbcHeuristicRENS::setRensType (int value) [inline]

Set type.

Definition at line 56 of file CbcHeuristicRENS.hpp.

7.64.4 Member Data Documentation

7.64.4.1 int CbcHeuristicRENS::numberTries_ [protected]

Number of tries.

Definition at line 62 of file CbcHeuristicRENS.hpp.

7.64.4.2 int CbcHeuristicRENS::rensType_ [protected]

Type 0 - fix at LB 1 - fix on dj 2 - fix at UB as well 3 - fix on 0.01*average dj add 16 to allow two tries.

Definition at line 70 of file CbcHeuristicRENS.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicRENS.hpp

7.65 CbcHeuristicRINS Class Reference

LocalSearch class.

#include <CbcHeuristicRINS.hpp>

Inheritance diagram for CbcHeuristicRINS:



Public Member Functions

- CbcHeuristicRINS ()
- CbcHeuristicRINS (CbcModel &model)

- CbcHeuristicRINS (const CbcHeuristicRINS &)
- ∼CbcHeuristicRINS ()
- virtual CbcHeuristic * clone () const

Clone

• CbcHeuristicRINS & operator= (const CbcHeuristicRINS &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

• int solutionFix (double &objectiveValue, double *newSolution, const int *keep)

This version fixes stuff and does IP.

· void setHowOften (int value)

Sets how often to do it.

• char * used () const

Used array so we can set.

void setLastNode (int value)

Resets lastNode.

void setSolutionCount (int value)

Resets number of solutions.

Protected Attributes

int numberSolutions

Number of solutions so we can do something at solution.

int howOften

How often to do (code can change)

int numberSuccesses_

Number of successes.

int numberTries_

Number of tries.

int stateOfFixing_

State of fixing continuous variables - 0 - not tried +n - this divisor makes small enough -n - this divisor still not small enough.

int lastNode_

Node when last done.

char * used_

Whether a variable has been in a solution.

7.65.1 Detailed Description

LocalSearch class.

Definition at line 17 of file CbcHeuristicRINS.hpp.

```
7.65.2 Constructor & Destructor Documentation
7.65.2.1 CbcHeuristicRINS::CbcHeuristicRINS ( )
7.65.2.2 CbcHeuristicRINS::CbcHeuristicRINS ( CbcModel & model )
7.65.2.3 CbcHeuristicRINS::CbcHeuristicRINS ( const CbcHeuristicRINS & )
7.65.2.4 CbcHeuristicRINS::~CbcHeuristicRINS()
7.65.3 Member Function Documentation
7.65.3.1 virtual CbcHeuristic* CbcHeuristicRINS::clone( ) const [virtual]
Clone.
Implements CbcHeuristic.
7.65.3.2 CbcHeuristicRINS& CbcHeuristicRINS::operator= ( const CbcHeuristicRINS & rhs )
Assignment operator.
7.65.3.3 virtual void CbcHeuristicRINS::generateCpp (FILE * fp ) [virtual]
Create C++ lines to get to current state.
Reimplemented from CbcHeuristic.
7.65.3.4 virtual void CbcHeuristicRINS::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.65.3.5 virtual void CbcHeuristicRINS::setModel ( CbcModel * model ) [virtual]
update model (This is needed if cliques update matrix etc)
Reimplemented from CbcHeuristic.
7.65.3.6 virtual int CbcHeuristicRINS::solution ( double & objectiveValue, double * newSolution ) [virtual]
returns 0 if no solution, 1 if valid solution.
Sets solution values if good, sets objective value (only if good) This does Relaxation Induced Neighborhood Search
Implements CbcHeuristic.
7.65.3.7 int CbcHeuristicRINS::solutionFix ( double & objectiveValue, double * newSolution, const int * keep )
This version fixes stuff and does IP.
7.65.3.8 void CbcHeuristicRINS::setHowOften (int value ) [inline]
Sets how often to do it.
Definition at line 63 of file CbcHeuristicRINS.hpp.
```

7.65.3.9 char* CbcHeuristicRINS::used() const [inline]

Used array so we can set.

Definition at line 67 of file CbcHeuristicRINS.hpp.

7.65.3.10 void CbcHeuristicRINS::setLastNode (int value) [inline]

Resets lastNode.

Definition at line 71 of file CbcHeuristicRINS.hpp.

7.65.3.11 void CbcHeuristicRINS::setSolutionCount (int value) [inline]

Resets number of solutions.

Definition at line 75 of file CbcHeuristicRINS.hpp.

7.65.4 Member Data Documentation

7.65.4.1 int CbcHeuristicRINS::numberSolutions_ [protected]

Number of solutions so we can do something at solution.

Definition at line 83 of file CbcHeuristicRINS.hpp.

7.65.4.2 int CbcHeuristicRINS::howOften_ [protected]

How often to do (code can change)

Definition at line 85 of file CbcHeuristicRINS.hpp.

7.65.4.3 int CbcHeuristicRINS::numberSuccesses_ [protected]

Number of successes.

Definition at line 87 of file CbcHeuristicRINS.hpp.

7.65.4.4 int CbcHeuristicRINS::numberTries_ [protected]

Number of tries.

Definition at line 89 of file CbcHeuristicRINS.hpp.

7.65.4.5 int CbcHeuristicRINS::stateOfFixing_ [protected]

State of fixing continuous variables - 0 - not tried +n - this divisor makes small enough -n - this divisor still not small enough.

Definition at line 95 of file CbcHeuristicRINS.hpp.

7.65.4.6 int CbcHeuristicRINS::lastNode_ [protected]

Node when last done.

Definition at line 97 of file CbcHeuristicRINS.hpp.

7.65.4.7 char* CbcHeuristicRINS::used_ [protected]

Whether a variable has been in a solution.

Definition at line 99 of file CbcHeuristicRINS.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristicRINS.hpp

7.66 CbcHeuristicVND Class Reference

LocalSearch class.

#include <CbcHeuristicVND.hpp>

Inheritance diagram for CbcHeuristicVND:



Public Member Functions

- CbcHeuristicVND ()
- CbcHeuristicVND (CbcModel &model)
- CbcHeuristicVND (const CbcHeuristicVND &)
- ∼CbcHeuristicVND ()
- virtual CbcHeuristic * clone () const

Clone.

• CbcHeuristicVND & operator= (const CbcHeuristicVND &rhs)

Assignment operator.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

• virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

int solutionFix (double &objectiveValue, double *newSolution, const int *keep)

This version fixes stuff and does IP.

void setHowOften (int value)

Sets how often to do it.

double * baseSolution () const

base solution array so we can set

Protected Attributes

• int numberSolutions_

Number of solutions so we can do something at solution.

int howOften

How often to do (code can change)

int numberSuccesses

Number of successes.

int numberTries

Number of tries.

int lastNode

Node when last done.

int stepSize_

Step size for decomposition.

- int k__
- int kmax
- int nDifferent
- double * baseSolution

Base solution.

7.66.1 Detailed Description

LocalSearch class.

Definition at line 17 of file CbcHeuristicVND.hpp.

- 7.66.2 Constructor & Destructor Documentation
- 7.66.2.1 CbcHeuristicVND::CbcHeuristicVND()
- 7.66.2.2 CbcHeuristicVND::CbcHeuristicVND (CbcModel & model)
- 7.66.2.3 CbcHeuristicVND::CbcHeuristicVND (const CbcHeuristicVND &)
- 7.66.2.4 CbcHeuristicVND:: \sim CbcHeuristicVND ()
- 7.66.3 Member Function Documentation
- 7.66.3.1 virtual CbcHeuristic* CbcHeuristicVND::clone()const [virtual]

Clone.

Implements CbcHeuristic.

7.66.3.2 CbcHeuristicVND& CbcHeuristicVND::operator= (const CbcHeuristicVND & rhs)

Assignment operator.

7.66.3.3 virtual void CbcHeuristicVND::generateCpp (FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristic.

```
7.66.3.4 virtual void CbcHeuristicVND::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.66.3.5 virtual void CbcHeuristicVND::setModel ( CbcModel * model ) [virtual]
update model (This is needed if cliques update matrix etc)
Reimplemented from CbcHeuristic.
7.66.3.6 virtual int CbcHeuristicVND::solution ( double & objectiveValue, double * newSolution ) [virtual]
returns 0 if no solution, 1 if valid solution.
Sets solution values if good, sets objective value (only if good) This does Relaxation Induced Neighborhood Search
Implements CbcHeuristic.
7.66.3.7 int CbcHeuristicVND::solutionFix ( double & objectiveValue, double * newSolution, const int * keep )
This version fixes stuff and does IP.
7.66.3.8 void CbcHeuristicVND::setHowOften (int value ) [inline]
Sets how often to do it.
Definition at line 63 of file CbcHeuristicVND.hpp.
7.66.3.9 double* CbcHeuristicVND::baseSolution ( ) const [inline]
base solution array so we can set
Definition at line 67 of file CbcHeuristicVND.hpp.
7.66.4 Member Data Documentation
7.66.4.1 int CbcHeuristicVND::numberSolutions_ [protected]
Number of solutions so we can do something at solution.
Definition at line 75 of file CbcHeuristicVND.hpp.
7.66.4.2 int CbcHeuristicVND::howOften_ [protected]
How often to do (code can change)
Definition at line 77 of file CbcHeuristicVND.hpp.
7.66.4.3 int CbcHeuristicVND::numberSuccesses_ [protected]
Number of successes.
Definition at line 79 of file CbcHeuristicVND.hpp.
7.66.4.4 int CbcHeuristicVND::numberTries_ [protected]
Number of tries.
Definition at line 81 of file CbcHeuristicVND.hpp.
```

7.66.4.5 int CbcHeuristicVND::lastNode_ [protected]

Node when last done.

Definition at line 83 of file CbcHeuristicVND.hpp.

7.66.4.6 int CbcHeuristicVND::stepSize_ [protected]

Step size for decomposition.

Definition at line 85 of file CbcHeuristicVND.hpp.

7.66.4.7 int CbcHeuristicVND::k_ [protected]

Definition at line 86 of file CbcHeuristicVND.hpp.

7.66.4.8 int CbcHeuristicVND::kmax_ [protected]

Definition at line 87 of file CbcHeuristicVND.hpp.

7.66.4.9 int CbcHeuristicVND::nDifferent_ [protected]

Definition at line 88 of file CbcHeuristicVND.hpp.

7.66.4.10 double* CbcHeuristicVND::baseSolution_ [protected]

Base solution.

Definition at line 90 of file CbcHeuristicVND.hpp.

The documentation for this class was generated from the following file:


• /home/ted/COIN/trunk/Cbc/src/CbcHeuristicVND.hpp

7.67 CbcldiotBranch Class Reference

Define an idiotic idea class.

#include <CbcFollowOn.hpp>

Inheritance diagram for CbcldiotBranch:



Public Member Functions

- CbcldiotBranch ()
- CbcldiotBranch (CbcModel *model)

Useful constructor.

CbcldiotBranch (const CbcldiotBranch &)

virtual CbcObject * clone () const

Clone.

- CbcldiotBranch & operator= (const CbcldiotBranch &rhs)
- ∼CbcldiotBranch ()
- virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const

Infeasibility - large is 0.5.

· virtual void feasibleRegion ()

This looks at solution and sets bounds to contain solution.

virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Creates a branching object.

virtual void initializeForBranching (CbcModel *)

Initialize for branching.

Protected Member Functions

OsiRowCut buildCut (const OsiBranchingInformation *info, int type, int &preferredWay) const
 Build "cut".

Protected Attributes

CoinThreadRandom randomNumberGenerator_

data Thread specific random number generator

CoinThreadRandom savedRandomNumberGenerator

Saved version of thread specific random number generator.

7.67.1 Detailed Description

Define an idiotic idea class.

The idea of this is that we take some integer variables away from integer and sum them with some randomness to get signed sum close to 0.5. We then can branch to exclude that gap.

This branching rule should be in addition to normal rules and have a high priority.

Definition at line 161 of file CbcFollowOn.hpp.

```
7.67.2 Constructor & Destructor Documentation
```

```
7.67.2.1 CbcldiotBranch::CbcldiotBranch ( )
```

7.67.2.2 CbcldiotBranch::CbcldiotBranch (CbcModel * model)

Useful constructor.

7.67.2.3 CbcldiotBranch::CbcldiotBranch (const CbcldiotBranch &)

7.67.2.4 CbcldiotBranch:: ~ CbcldiotBranch ()

7.67.3 Member Function Documentation

```
7.67.3.1 virtual CbcObject* CbcIdiotBranch::clone( ) const [virtual]
Clone.
Implements CbcObject.
7.67.3.2 CbcldiotBranch& CbcldiotBranch::operator= ( const CbcldiotBranch & rhs )
7.67.3.3 virtual double CbcldiotBranch::infeasibility ( const OsiBranchingInformation * info, int & preferredWay ) const
         [virtual]
Infeasibility - large is 0.5.
Reimplemented from CbcObject.
7.67.3.4 virtual void CbcldiotBranch::feasibleRegion() [virtual]
This looks at solution and sets bounds to contain solution.
Implements CbcObject.
7.67.3.5 virtual CbcBranchingObject * CbcIdiotBranch::createCbcBranch ( OsiSolverInterface * solver, const
         OsiBranchingInformation * info, int way ) [virtual]
Creates a branching object.
Reimplemented from CbcObject.
7.67.3.6 virtual void CbcldiotBranch::initializeForBranching ( CbcModel * ) [virtual]
Initialize for branching.
Reimplemented from CbcObject.
7.67.3.7 OsiRowCut CbcIdiotBranch::buildCut ( const OsiBranchingInformation * info, int type, int & preferredWay ) const
         [protected]
Build "cut".
7.67.4 Member Data Documentation
7.67.4.1 CoinThreadRandom CbcldiotBranch::randomNumberGenerator_ [mutable], [protected]
data Thread specific random number generator
Definition at line 201 of file CbcFollowOn.hpp.
7.67.4.2 CoinThreadRandom CbcldiotBranch::savedRandomNumberGenerator [mutable], [protected]
Saved version of thread specific random number generator.
Definition at line 203 of file CbcFollowOn.hpp.
The documentation for this class was generated from the following file:
```

/home/ted/COIN/trunk/Cbc/src/CbcFollowOn.hpp


Generated on Mon Oct 21 2013 19:03:07 for Cbc by Doxygen

7.68 CbcIntegerBranchingObject Class Reference

Simple branching object for an integer variable.

#include <CbcSimpleInteger.hpp>

Inheritance diagram for CbcIntegerBranchingObject:



Public Member Functions

CbcIntegerBranchingObject ()

Default constructor.

CbcIntegerBranchingObject (CbcModel *model, int variable, int way, double value)

Create a standard floor/ceiling branch object.

CbcIntegerBranchingObject (CbcModel *model, int variable, int way, double lowerValue, double upperValue)

Create a degenerate branch object.

CbcIntegerBranchingObject (const CbcIntegerBranchingObject &)

Copy constructor.

CbcIntegerBranchingObject & operator= (const CbcIntegerBranchingObject &rhs)

Assignment operator.

virtual CbcBranchingObject * clone () const

Clone.

• virtual ~CbcIntegerBranchingObject ()

Destructor.

· void fillPart (int variable, int way, double value)

Does part of constructor.

virtual double branch ()

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

• virtual void fix (OsiSolverInterface *solver, double *lower, double *upper, int branchState) const

Update bounds in solver as in 'branch' and update given bounds.

virtual bool tighten (OsiSolverInterface *)

Change (tighten) bounds in object to reflect bounds in solver.

· virtual void print ()

Print something about branch - only if log level high.

const double * downBounds () const

Lower and upper bounds for down branch.

const double * upBounds () const

Lower and upper bounds for up branch.

void setDownBounds (const double bounds[2])

Set lower and upper bounds for down branch.

void setUpBounds (const double bounds[2])

Set lower and upper bounds for up branch.

virtual CbcBranchObjType type () const

Return the type (an integer identifier) of this.

 virtual CbcRangeCompare compareBranchingObject (const CbcBranchingObject *brObj, const bool replaceIf-Overlap=false)

Compare the this with brObj.

Protected Attributes

• double down_[2]

Lower [0] and upper [1] bounds for the down arm (way_ = -1)

double up_ [2]

Lower [0] and upper [1] bounds for the up arm (way_ = 1)

7.68.1 Detailed Description

Simple branching object for an integer variable.

This object can specify a two-way branch on an integer variable. For each arm of the branch, the upper and lower bounds on the variable can be independently specified.

Variable holds the index of the integer variable in the integerVariable array of the model.

Definition at line 23 of file CbcSimpleInteger.hpp.

7.68.2 Constructor & Destructor Documentation

7.68.2.1 CbcIntegerBranchingObject::CbcIntegerBranchingObject()

Default constructor.

7.68.2.2 CbcIntegerBranchingObject::CbcIntegerBranchingObject (CbcModel * model, int variable, int way, double value)

Create a standard floor/ceiling branch object.

Specifies a simple two-way branch. Let value = x*. One arm of the branch will be $lb \le x \le loor(x*)$, the other $ceil(x*) \le x \le loor(x*)$. Specify way = -1 to set the object state to perform the down arm first, way = 1 for the up arm.

7.68.2.3 CbcIntegerBranchingObject::CbcIntegerBranchingObject (CbcModel * model, int variable, int way, double lowerValue, double upperValue)

Create a degenerate branch object.

Specifies a 'one-way branch'. Calling branch() for this object will always result in lowerValue <= x <= upperValue. Used to fix a variable when lowerValue = upperValue.

7.68.2.4 CbcIntegerBranchingObject::CbcIntegerBranchingObject (const CbcIntegerBranchingObject &)

Copy constructor.

7.68.2.5 virtual CbcIntegerBranchingObject::~CbcIntegerBranchingObject() [virtual]

Destructor.

7.68.3 Member Function Documentation

7.68.3.1 CbcIntegerBranchingObject& CbcIntegerBranchingObject::operator= (const CbcIntegerBranchingObject & rhs)

Assignment operator.

7.68.3.2 virtual CbcBranchingObject* CbcIntegerBranchingObject::clone() const [virtual]

Clone.

Implements CbcBranchingObject.

Reimplemented in CbcIntegerPseudoCostBranchingObject, and CbcDynamicPseudoCostBranchingObject.

7.68.3.3 void CbcIntegerBranchingObject::fillPart (int variable, int way, double value)

Does part of constructor.

7.68.3.4 virtual double CbcIntegerBranchingObject::branch() [virtual]

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

Returns change in guessed objective on next branch

Implements CbcBranchingObject.

Reimplemented in CbcIntegerPseudoCostBranchingObject, and CbcDynamicPseudoCostBranchingObject.

7.68.3.5 virtual void CbcIntegerBranchingObject::fix (OsiSolverInterface * solver, double * lower, double * upper, int branchState) const [virtual]

Update bounds in solver as in 'branch' and update given bounds.

branchState is -1 for 'down' +1 for 'up'

Reimplemented from CbcBranchingObject.

7.68.3.6 virtual bool CbcIntegerBranchingObject::tighten (OsiSolverInterface *) [virtual]

Change (tighten) bounds in object to reflect bounds in solver.

Return true if now fixed

Reimplemented from CbcBranchingObject.

7.68.3.7 virtual void CbcIntegerBranchingObject::print() [virtual]

Print something about branch - only if log level high.

7.68.3.8 const double* CbcIntegerBranchingObject::downBounds() const [inline]

Lower and upper bounds for down branch.

Definition at line 93 of file CbcSimpleInteger.hpp.

7.68.3.9 const double* CbcIntegerBranchingObject::upBounds() const [inline]

Lower and upper bounds for up branch.

Definition at line 97 of file CbcSimpleInteger.hpp.

7.68.3.10 void CbcIntegerBranchingObject::setDownBounds (const double bounds[2]) [inline]

Set lower and upper bounds for down branch.

Definition at line 101 of file CbcSimpleInteger.hpp.

7.68.3.11 void CbcIntegerBranchingObject::setUpBounds (const double bounds[2]) [inline]

Set lower and upper bounds for up branch.

Definition at line 105 of file CbcSimpleInteger.hpp.

7.68.3.12 virtual CbcBranchObjType CbcIntegerBranchingObject::type() const [inline], [virtual]

Return the type (an integer identifier) of this.

Implements CbcBranchingObject.

Reimplemented in CbcIntegerPseudoCostBranchingObject, and CbcDynamicPseudoCostBranchingObject.

Definition at line 133 of file CbcSimpleInteger.hpp.

7.68.3.13 virtual CbcRangeCompare CbcIntegerBranchingObject::compareBranchingObject (const CbcBranchingObject * brObj, const bool replacelfOverlap = false) [virtual]

Compare the this with brObj.

this and brobj must be os the same type and must have the same original object, but they may have different feasible regions. Return the appropriate CbcRangeCompare value (first argument being the sub/superset if that's the case). In case of overlap (and if replaceIfOverlap is true) replace the current branching object with one whose feasible region is the overlap.

Implements CbcBranchingObject.

Reimplemented in CbcIntegerPseudoCostBranchingObject.

7.68.4 Member Data Documentation

7.68.4.1 double CbcIntegerBranchingObject::down_[2] [protected]

Lower [0] and upper [1] bounds for the down arm (way = -1)

Definition at line 150 of file CbcSimpleInteger.hpp.

7.68.4.2 double CbcIntegerBranchingObject::up_[2] [protected]

Lower [0] and upper [1] bounds for the up arm (way_ = 1)

Definition at line 152 of file CbcSimpleInteger.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcSimpleInteger.hpp

7.69 CbcIntegerPseudoCostBranchingObject Class Reference

Simple branching object for an integer variable with pseudo costs.

#include <CbcSimpleIntegerDynamicPseudoCost.hpp>

Inheritance diagram for CbcIntegerPseudoCostBranchingObject:



Public Member Functions

CbcIntegerPseudoCostBranchingObject ()

Default constructor.

CbcIntegerPseudoCostBranchingObject (CbcModel *model, int variable, int way, double value)

Create a standard floor/ceiling branch object.

CbcIntegerPseudoCostBranchingObject (CbcModel *model, int variable, int way, double lowerValue, double upperValue)

Create a degenerate branch object.

CbcIntegerPseudoCostBranchingObject (const CbcIntegerPseudoCostBranchingObject &)

Copy constructor.

CbcIntegerPseudoCostBranchingObject & operator= (const CbcIntegerPseudoCostBranchingObject &rhs)

Assignment operator.

virtual CbcBranchingObject * clone () const

Clone

 $\bullet \ \, \text{virtual} \sim \! \text{CbcIntegerPseudoCostBranchingObject ()} \\$

Destructor.

• virtual double branch ()

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

• double changeInGuessed () const

Change in guessed.

• void setChangeInGuessed (double value)

Set change in guessed.

virtual CbcBranchObjType type () const

Return the type (an integer identifier) of this.

 virtual CbcRangeCompare compareBranchingObject (const CbcBranchingObject *brObj, const bool replaceIf-Overlap=false)

Compare the this with brObj.

Protected Attributes

double changeInGuessed

Change in guessed objective value for next branch.

7.69.1 Detailed Description

Simple branching object for an integer variable with pseudo costs.

This object can specify a two-way branch on an integer variable. For each arm of the branch, the upper and lower bounds on the variable can be independently specified.

Variable holds the index of the integer variable in the integerVariable array of the model.

Definition at line 389 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.69.2 Constructor & Destructor Documentation

7.69.2.1 CbcIntegerPseudoCostBranchingObject::CbcIntegerPseudoCostBranchingObject ()

Default constructor.

7.69.2.2 CbcIntegerPseudoCostBranchingObject::CbcIntegerPseudoCostBranchingObject (CbcModel * model, int variable, int way, double value)

Create a standard floor/ceiling branch object.

Specifies a simple two-way branch. Let value = x*. One arm of the branch will be is lb <= x <= floor(x*), the other ceil(x*) <= x <= ub. Specify way = -1 to set the object state to perform the down arm first, way = 1 for the up arm.

7.69.2.3 CbcIntegerPseudoCostBranchingObject::CbcIntegerPseudoCostBranchingObject (CbcModel * model, int variable, int way, double lowerValue, double upperValue)

Create a degenerate branch object.

Specifies a 'one-way branch'. Calling branch() for this object will always result in lowerValue \le x \le upperValue. Used to fix a variable when lowerValue = upperValue.

7.69.2.4 CbcIntegerPseudoCostBranchingObject::CbcIntegerPseudoCostBranchingObject (const CbcIntegerPseudoCostBranchingObject &)

Copy constructor.

 $\textbf{7.69.2.5} \quad \textbf{virtual CbcIntegerPseudoCostBranchingObject::} \sim \textbf{CbcIntegerPseudoCostBranchingObject ()} \quad [\texttt{virtual}]$

Destructor.

- 7.69.3 Member Function Documentation
- 7.69.3.1 CbcIntegerPseudoCostBranchingObject& CbcIntegerPseudoCostBranchingObject::operator= (const CbcIntegerPseudoCostBranchingObject & rhs)

Assignment operator.

7.69.3.2 virtual CbcBranchingObject* CbcIntegerPseudoCostBranchingObject::clone()const [virtual]

Clone.

Reimplemented from CbcIntegerBranchingObject.

7.69.3.3 virtual double CbcIntegerPseudoCostBranchingObject::branch() [virtual]

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

This version also changes guessed objective value

Reimplemented from CbcIntegerBranchingObject.

7.69.3.4 double CbcIntegerPseudoCostBranchingObject::changeInGuessed()const [inline]

Change in guessed.

Definition at line 436 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.69.3.5 void CbcIntegerPseudoCostBranchingObject::setChangeInGuessed (double value) [inline]

Set change in guessed.

Definition at line 440 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.69.3.6 virtual CbcBranchObjType CbcIntegerPseudoCostBranchingObject::type()const [inline], [virtual]

Return the type (an integer identifier) of this.

Reimplemented from CbcIntegerBranchingObject.

Definition at line 445 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.69.3.7 virtual CbcRangeCompare CbcIntegerPseudoCostBranchingObject::compareBranchingObject (const CbcBranchingObject * brObj, const bool replacelfOverlap = false) [virtual]

Compare the this with brObj.

this and brobj must be os the same type and must have the same original object, but they may have different feasible regions. Return the appropriate CbcRangeCompare value (first argument being the sub/superset if that's the case). In case of overlap (and if replaceIfoverlap is true) replace the current branching object with one whose feasible region is the overlap.

Reimplemented from CbcIntegerBranchingObject.

7.69.4 Member Data Documentation

7.69.4.1 double CbcIntegerPseudoCostBranchingObject::changeInGuessed_ [protected]

Change in guessed objective value for next branch.

Definition at line 462 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcSimpleIntegerDynamicPseudoCost.hpp

7.70 CbcLongCliqueBranchingObject Class Reference

Unordered Clique Branching Object class.

#include <CbcClique.hpp>

Inheritance diagram for CbcLongCliqueBranchingObject:



Public Member Functions

- CbcLongCliqueBranchingObject ()
- CbcLongCliqueBranchingObject (CbcModel *model, const CbcClique *clique, int way, int numberOnDownSide, const int *down, int numberOnUpSide, const int *up)
- CbcLongCliqueBranchingObject (const CbcLongCliqueBranchingObject &)
- CbcLongCliqueBranchingObject & operator= (const CbcLongCliqueBranchingObject &rhs)
- virtual CbcBranchingObject * clone () const

Clone.

- virtual ~CbcLongCliqueBranchingObject ()
- virtual double branch ()

Does next branch and updates state.

virtual void print ()

Print something about branch - only if log level high.

virtual CbcBranchObjType type () const

Return the type (an integer identifier) of this.

• virtual int compareOriginalObject (const CbcBranchingObject *brObj) const

Compare the original object of this with the original object of brobj.

 virtual CbcRangeCompare compareBranchingObject (const CbcBranchingObject *brObj, const bool replaceIf-Overlap=false)

Compare the this with brObj.

Additional Inherited Members

7.70.1 Detailed Description

Unordered Clique Branching Object class.

These are for cliques which are > 64 members Variable is number of clique.

Definition at line 234 of file CbcClique.hpp.

- 7.70.2 Constructor & Destructor Documentation
- 7.70.2.1 CbcLongCliqueBranchingObject::CbcLongCliqueBranchingObject ()
- 7.70.2.2 CbcLongCliqueBranchingObject::CbcLongCliqueBranchingObject (CbcModel * model, const CbcClique * clique, int way, int numberOnDownSide, const int * down, int numberOnUpSide, const int * up)
- 7.70.2.3 CbcLongCliqueBranchingObject::CbcLongCliqueBranchingObject (const CbcLongCliqueBranchingObject &)
- 7.70.2.4 virtual CbcLongCliqueBranchingObject::~CbcLongCliqueBranchingObject() [virtual]

7.70.3 Member Function Documentation

7.70.3.1 CbcLongCliqueBranchingObject& CbcLongCliqueBranchingObject::operator= (const CbcLongCliqueBranchingObject & rhs)

7.70.3.2 virtual CbcBranchingObject* CbcLongCliqueBranchingObject::clone() const [virtual]

Clone.

Implements CbcBranchingObject.

7.70.3.3 virtual double CbcLongCliqueBranchingObject::branch() [virtual]

Does next branch and updates state.

Implements CbcBranchingObject.

7.70.3.4 virtual void CbcLongCliqueBranchingObject::print() [virtual]

Print something about branch - only if log level high.

7.70.3.5 virtual CbcBranchObjType CbcLongCliqueBranchingObject::type() const [inline], [virtual]

Return the type (an integer identifier) of this.

Implements CbcBranchingObject.

Definition at line 269 of file CbcClique.hpp.

7.70.3.6 virtual int CbcLongCliqueBranchingObject::compareOriginalObject (const CbcBranchingObject * brObj) const [virtual]

Compare the original object of this with the original object of brObj.

Assumes that there is an ordering of the original objects. This method should be invoked only if this and brObj are of the same type. Return negative/0/positive depending on whether this is smaller/same/larger than the argument.

Reimplemented from CbcBranchingObject.

7.70.3.7 virtual CbcRangeCompare CbcLongCliqueBranchingObject::compareBranchingObject (const CbcBranchingObject * brObj. const bool replacelfOverlap = false) [virtual]

Compare the this with brobj.

this and brobj must be os the same type and must have the same original object, but they may have different feasible regions. Return the appropriate CbcRangeCompare value (first argument being the sub/superset if that's the case). In case of overlap (and if replaceIfoverlap is true) replace the current branching object with one whose feasible region is the overlap.

Implements CbcBranchingObject.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcClique.hpp

7.71 CbcLotsize Class Reference

Lotsize class.

#include <CbcBranchLotsize.hpp>

Inheritance diagram for CbcLotsize:



Public Member Functions

- CbcLotsize ()
- CbcLotsize (CbcModel *model, int iColumn, int numberPoints, const double *points, bool range=false)
- CbcLotsize (const CbcLotsize &)
- virtual CbcObject * clone () const

Clone.

- CbcLotsize & operator= (const CbcLotsize &rhs)
- ∼CbcLotsize ()
- virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const

Infeasibility - large is 0.5.

virtual void feasibleRegion ()

Set bounds to contain the current solution.

• virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Creates a branching object.

virtual CbcBranchingObject * preferredNewFeasible () const

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in the good direction.

virtual CbcBranchingObject * notPreferredNewFeasible () const

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a bad direction.

virtual void resetBounds (const OsiSolverInterface *solver)

Reset original upper and lower bound values from the solver.

· bool findRange (double value) const

Finds range of interest so value is feasible in range range_ or infeasible between hi[range_] and lo[range_+1].

• virtual void floorCeiling (double &floorLotsize, double &ceilingLotsize, double value, double tolerance) const

Returns floor and ceiling.

• int modelSequence () const

Model column number.

• void setModelSequence (int value)

Set model column number.

· virtual int columnNumber () const

Column number if single column object -1 otherwise, so returns >= 0 Used by heuristics.

· double originalLowerBound () const

Original variable bounds.

- · double originalUpperBound () const
- int rangeType () const

```
Type - 1 points, 2 ranges.
```

• int numberRanges () const

Number of points.

double * bound () const

Ranges.

virtual bool canDoHeuristics () const

Return true if object can take part in normal heuristics.

Additional Inherited Members

7.71.1 Detailed Description

Lotsize class.

Definition at line 13 of file CbcBranchLotsize.hpp.

- 7.71.2 Constructor & Destructor Documentation
- 7.71.2.1 CbcLotsize::CbcLotsize()
- 7.71.2.2 CbcLotsize::CbcLotsize (CbcModel * model, int iColumn, int numberPoints, const double * points, bool range = false)
- 7.71.2.3 CbcLotsize::CbcLotsize (const CbcLotsize &)
- 7.71.2.4 CbcLotsize:: ∼CbcLotsize ()
- 7.71.3 Member Function Documentation
- 7.71.3.1 virtual CbcObject* CbcLotsize::clone() const [virtual]

Clone.

Implements CbcObject.

- 7.71.3.2 CbcLotsize & CbcLotsize::operator= (const CbcLotsize & rhs)
- 7.71.3.3 virtual double CbcLotsize::infeasibility (const OsiBranchingInformation * info, int & preferredWay) const [virtual]

Infeasibility - large is 0.5.

Reimplemented from CbcObject.

7.71.3.4 virtual void CbcLotsize::feasibleRegion () [virtual]

Set bounds to contain the current solution.

More precisely, for the variable associated with this object, take the value given in the current solution, force it within the current bounds if required, then set the bounds to fix the variable at the integer nearest the solution value.

Implements CbcObject.

7.71.3.5 virtual CbcBranchingObject* CbcLotsize::createCbcBranch (OsiSolverInterface * solver, const OsiBranchingInformation * info, int way) [virtual]

Creates a branching object.

Reimplemented from CbcObject.

```
7.71.3.6 virtual CbcBranchingObject* CbcLotsize::preferredNewFeasible() const [virtual]
```

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in the good direction.

The preferred branching object will force the variable to be +/-1 from its current value, depending on the reduced cost and objective sense. If movement in the direction which improves the objective is impossible due to bounds on the variable, the branching object will move in the other direction. If no movement is possible, the method returns NULL.

Only the bounds on this variable are considered when determining if the new point is feasible.

Reimplemented from CbcObject.

```
7.71.3.7 virtual CbcBranchingObject* CbcLotsize::notPreferredNewFeasible() const [virtual]
```

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a bad direction.

As for preferredNewFeasible(), but the preferred branching object will force movement in a direction that degrades the objective.

Reimplemented from CbcObject.

```
7.71.3.8 virtual void CbcLotsize::resetBounds ( const OsiSolverInterface * solver ) [virtual]
```

Reset original upper and lower bound values from the solver.

Handy for updating bounds held in this object after bounds held in the solver have been tightened.

Reimplemented from CbcObject.

```
7.71.3.9 bool CbcLotsize::findRange ( double value ) const
```

Finds range of interest so value is feasible in range range_ or infeasible between hi[range_] and lo[range_+1].

Returns true if feasible.

```
7.71.3.10 virtual void CbcLotsize::floorCeiling ( double & floorLotsize, double & ceilingLotsize, double value, double tolerance ) const [virtual]
```

Returns floor and ceiling.

Reimplemented from CbcObject.

```
7.71.3.11 int CbcLotsize::modelSequence() const [inline]
```

Model column number.

Definition at line 97 of file CbcBranchLotsize.hpp.

```
7.71.3.12 void CbcLotsize::setModelSequence (int value) [inline]
```

Set model column number.

Definition at line 101 of file CbcBranchLotsize.hpp.

```
7.71.3.13 virtual int CbcLotsize::columnNumber() const [virtual]
```

Column number if single column object -1 otherwise, so returns \geq = 0 Used by heuristics.

7.71.3.14 double CbcLotsize::originalLowerBound () const [inline]

Original variable bounds.

Definition at line 111 of file CbcBranchLotsize.hpp.

7.71.3.15 double CbcLotsize::originalUpperBound () const [inline]

Definition at line 114 of file CbcBranchLotsize.hpp.

7.71.3.16 int CbcLotsize::rangeType() const [inline]

Type - 1 points, 2 ranges.

Definition at line 118 of file CbcBranchLotsize.hpp.

7.71.3.17 int CbcLotsize::numberRanges () const [inline]

Number of points.

Definition at line 122 of file CbcBranchLotsize.hpp.

7.71.3.18 double* CbcLotsize::bound () const [inline]

Ranges.

Definition at line 126 of file CbcBranchLotsize.hpp.

7.71.3.19 virtual bool CbcLotsize::canDoHeuristics() const [inline], [virtual]

Return true if object can take part in normal heuristics.

Definition at line 131 of file CbcBranchLotsize.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcBranchLotsize.hpp

7.72 CbcLotsizeBranchingObject Class Reference

Lotsize branching object.

#include <CbcBranchLotsize.hpp>

Inheritance diagram for CbcLotsizeBranchingObject:



Public Member Functions

CbcLotsizeBranchingObject ()

Default constructor.

• CbcLotsizeBranchingObject (CbcModel *model, int variable, int way, double value, const CbcLotsize *lotsize)

Create a lotsize floor/ceiling branch object.

• CbcLotsizeBranchingObject (CbcModel *model, int variable, int way, double lowerValue, double upperValue)

Create a degenerate branch object.

• CbcLotsizeBranchingObject (const CbcLotsizeBranchingObject &)

Copy constructor.

CbcLotsizeBranchingObject & operator= (const CbcLotsizeBranchingObject &rhs)

Assignment operator.

virtual CbcBranchingObject * clone () const

Clone.

virtual ~CbcLotsizeBranchingObject ()

Destructor.

virtual double branch ()

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

virtual void print ()

Print something about branch - only if log level high.

virtual CbcBranchObjType type () const

Return the type (an integer identifier) of this.

 virtual CbcRangeCompare compareBranchingObject (const CbcBranchingObject *brObj, const bool replaceIf-Overlap=false)

Compare the this with brObj.

Protected Attributes

double down_ [2]

Lower [0] and upper [1] bounds for the down arm (way_ = -1)

• double up_ [2]

Lower [0] and upper [1] bounds for the up arm (way_ = 1)

7.72.1 Detailed Description

Lotsize branching object.

This object can specify a two-way branch on an integer variable. For each arm of the branch, the upper and lower bounds on the variable can be independently specified.

Variable_holds the index of the integer variable in the integerVariable_array of the model.

Definition at line 166 of file CbcBranchLotsize.hpp.

7.72.2 Constructor & Destructor Documentation

7.72.2.1 CbcLotsizeBranchingObject::CbcLotsizeBranchingObject ()

Default constructor.

7.72.2.2 CbcLotsizeBranchingObject::CbcLotsizeBranchingObject (CbcModel * model, int variable, int way, double value, const CbcLotsize * lotsize)

Create a lotsize floor/ceiling branch object.

Specifies a simple two-way branch. Let value = x*. One arm of the branch will be is $lb \le x \le valid$ range below(x*), the other valid range above(x*) $\le x \le ub$. Specify way = -1 to set the object state to perform the down arm first, way = 1 for the up arm.

7.72.2.3 CbcLotsizeBranchingObject::CbcLotsizeBranchingObject (CbcModel * model, int variable, int way, double lowerValue, double upperValue)

Create a degenerate branch object.

Specifies a 'one-way branch'. Calling branch() for this object will always result in lowerValue <= x <= upperValue. Used to fix in valid range

7.72.2.4 CbcLotsizeBranchingObject::CbcLotsizeBranchingObject (const CbcLotsizeBranchingObject &)

Copy constructor.

7.72.2.5 virtual CbcLotsizeBranchingObject::~CbcLotsizeBranchingObject() [virtual]

Destructor.

- 7.72.3 Member Function Documentation
- 7.72.3.1 CbcLotsizeBranchingObject& CbcLotsizeBranchingObject::operator= (const CbcLotsizeBranchingObject & rhs)

Assignment operator.

7.72.3.2 virtual CbcBranchingObject* CbcLotsizeBranchingObject::clone() const [virtual]

Clone.

Implements CbcBranchingObject.

7.72.3.3 virtual double CbcLotsizeBranchingObject::branch() [virtual]

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

Implements CbcBranchingObject.

7.72.3.4 virtual void CbcLotsizeBranchingObject::print() [virtual]

Print something about branch - only if log level high.

7.72.3.5 virtual CbcBranchObjType CbcLotsizeBranchingObject::type()const [inline], [virtual]

Return the type (an integer identifier) of this.

Implements CbcBranchingObject.

Definition at line 216 of file CbcBranchLotsize.hpp.

7.72.3.6 virtual CbcRangeCompare CbcLotsizeBranchingObject::compareBranchingObject (const CbcBranchingObject * brObj, const bool replacelfOverlap = false) [virtual]

Compare the this with brObj.

this and brobj must be os the same type and must have the same original object, but they may have different feasible regions. Return the appropriate CbcRangeCompare value (first argument being the sub/superset if that's the case). In case of overlap (and if replaceIfoverlap is true) replace the current branching object with one whose feasible region is the overlap.

Implements CbcBranchingObject.

7.72.4 Member Data Documentation

7.72.4.1 double CbcLotsizeBranchingObject::down_[2] [protected]

Lower [0] and upper [1] bounds for the down arm (way_ = -1)

Definition at line 236 of file CbcBranchLotsize.hpp.

7.72.4.2 double CbcLotsizeBranchingObject::up_[2] [protected]

Lower [0] and upper [1] bounds for the up arm (way_ = 1)

Definition at line 238 of file CbcBranchLotsize.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcBranchLotsize.hpp

7.73 CbcMessage Class Reference

#include <CbcMessage.hpp>

Inheritance diagram for CbcMessage:



Public Member Functions

Constructors etc

CbcMessage (Language language=us_en)
 Constructor.

7.73.1 Detailed Description

Definition at line 81 of file CbcMessage.hpp.

7.73.2 Constructor & Destructor Documentation

```
7.73.2.1 CbcMessage::CbcMessage ( Language language = us_en )
```

Constructor.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcMessage.hpp

7.74 CbcModel Class Reference

Simple Branch and bound class.

```
#include <CbcModel.hpp>
```

Public Types

- enum CbcIntParam {
 CbcMaxNumNode = 0, CbcMaxNumSol, CbcFathomDiscipline, CbcPrinting,
 CbcNumberBranches, CbcLastIntParam }
- enum CbcDblParam {

CbcIntegerTolerance = 0, CbcInfeasibilityWeight, CbcCutoffIncrement, CbcAllowableGap,
CbcAllowableFractionGap, CbcMaximumSeconds, CbcCurrentCutoff, CbcOptimizationDirection,
CbcCurrentObjectiveValue, CbcCurrentMinimizationObjectiveValue, CbcStartSeconds, CbcHeuristicGap,
CbcHeuristicFractionGap, CbcSmallestChange, CbcSumChange, CbcLargestChange,
CbcSmallChange, CbcLastDblParam }

Public Member Functions

- void setMIPStart (const std::vector< std::pair< std::string, double >> &mips)
- const std::vector< std::pairstd::string, double > > & getMIPStart ()

Presolve methods

- CbcModel * findCliques (bool makeEquality, int atLeastThisMany, int lessThanThis, int defaultValue=1000) Identify cliques and construct corresponding objects.
- CbcModel * integerPresolve (bool weak=false)

Do integer presolve, creating a new (presolved) model.

bool integerPresolveThisModel (OsiSolverInterface *originalSolver, bool weak=false)

Do integer presolve, modifying the current model.

void originalModel (CbcModel *presolvedModel, bool weak)

Put back information into the original model after integer presolve.

• bool tightenVubs (int type, bool allowMultipleBinary=false, double useCutoff=1.0e50)

For variables involved in VUB constraints, see if we can tighten bounds by solving lp's.

bool tightenVubs (int numberVubs, const int *which, double useCutoff=1.0e50)

For variables involved in VUB constraints, see if we can tighten bounds by solving lp's.

void analyzeObjective ()

Analyze problem to find a minimum change in the objective function.

• void AddIntegers ()

Add additional integers.

void saveModel (OsiSolverInterface *saveSolver, double *checkCutoffForRestart, bool *feasible)

Save copy of the model.

· void flipModel ()

Flip direction of optimization on all models.

Object manipulation routines

See OsiObject for an explanation of 'object' in the context of CbcModel.

• int numberObjects () const

Get the number of objects.

void setNumberObjects (int number)

Set the number of objects.

OsiObject ** objects () const

Get the array of objects.

const OsiObject * object (int which) const

Get the specified object.

• OsiObject * modifiableObject (int which) const

Get the specified object.

- void setOptionalInteger (int index)
- void deleteObjects (bool findIntegers=true)

Delete all object information (and just back to integers if true)

void addObjects (int numberObjects, OsiObject **objects)

Add in object information.

void addObjects (int numberObjects, CbcObject **objects)

Add in object information.

void synchronizeModel ()

Ensure attached objects point to this model.

void findIntegers (bool startAgain, int type=0)

Identify integer variables and create corresponding objects.

Parameter set/get methods

The set methods return true if the parameter was set to the given value, false if the value of the parameter is out of range.

The get methods return the value of the parameter.

bool setIntParam (CbcIntParam key, int value)

Set an integer parameter.

bool setDblParam (CbcDblParam key, double value)

Set a double parameter.

• int getIntParam (CbcIntParam key) const

Get an integer parameter.

· double getDblParam (CbcDblParam key) const

Get a double parameter.

void setCutoff (double value)

Set cutoff bound on the objective function.

• double getCutoff () const

Get the cutoff bound on the objective function - always as minimize.

bool setMaximumNodes (int value)

Set the maximum node limit .

int getMaximumNodes () const

Get the maximum node limit.

• bool setMaximumSolutions (int value)

Set the maximum number of solutions desired.

int getMaximumSolutions () const

Get the maximum number of solutions desired.

bool setPrintingMode (int value)

Set the printing mode.

int getPrintingMode () const

Get the printing mode.

bool setMaximumSeconds (double value)

Set the maximum number of seconds desired.

double getMaximumSeconds () const

Get the maximum number of seconds desired.

double getCurrentSeconds () const

Current time since start of branchAndbound.

· bool maximumSecondsReached () const

Return true if maximum time reached.

• bool setIntegerTolerance (double value)

Set the integrality tolerance.

double getIntegerTolerance () const

Get the integrality tolerance.

• bool setInfeasibilityWeight (double value)

Set the weight per integer infeasibility .

double getInfeasibilityWeight () const

Get the weight per integer infeasibility.

bool setAllowableGap (double value)

Set the allowable gap between the best known solution and the best possible solution.

double getAllowableGap () const

Get the allowable gap between the best known solution and the best possible solution.

bool setAllowableFractionGap (double value)

Set the fraction allowable gap between the best known solution and the best possible solution.

• double getAllowableFractionGap () const

Get the fraction allowable gap between the best known solution and the best possible solution.

bool setAllowablePercentageGap (double value)

Set the percentage allowable gap between the best known solution and the best possible solution.

· double getAllowablePercentageGap () const

Get the percentage allowable gap between the best known solution and the best possible solution.

bool setHeuristicGap (double value)

Set the heuristic gap between the best known solution and the best possible solution.

double getHeuristicGap () const

Get the heuristic gap between the best known solution and the best possible solution.

• bool setHeuristicFractionGap (double value)

Set the fraction heuristic gap between the best known solution and the best possible solution.

double getHeuristicFractionGap () const

Get the fraction heuristic gap between the best known solution and the best possible solution.

bool setCutoffIncrement (double value)

Set the CbcModel::CbcCutoffIncrement desired.

• double getCutoffIncrement () const

Get the CbcModel::CbcCutoffIncrement desired.

• bool canStopOnGap () const

See if can stop on gap.

void setHotstartSolution (const double *solution, const int *priorities=NULL)

Pass in target solution and optional priorities.

void setMinimumDrop (double value)

Set the minimum drop to continue cuts.

double getMinimumDrop () const

Get the minimum drop to continue cuts.

void setMaximumCutPassesAtRoot (int value)

Set the maximum number of cut passes at root node (default 20) Minimum drop can also be used for fine tuning.

int getMaximumCutPassesAtRoot () const

Get the maximum number of cut passes at root node.

void setMaximumCutPasses (int value)

Set the maximum number of cut passes at other nodes (default 10) Minimum drop can also be used for fine tuning.

int getMaximumCutPasses () const

Get the maximum number of cut passes at other nodes (default 10)

int getCurrentPassNumber () const

Get current cut pass number in this round of cuts.

void setCurrentPassNumber (int value)

Set current cut pass number in this round of cuts.

void setNumberStrong (int number)

Set the maximum number of candidates to be evaluated for strong branching.

• int numberStrong () const

Get the maximum number of candidates to be evaluated for strong branching.

void setPreferredWay (int value)

Set global preferred way to branch -1 down, +1 up, 0 no preference.

int getPreferredWay () const

Get the preferred way to branch (default 0)

· int whenCuts () const

Get at which depths to do cuts.

void setWhenCuts (int value)

Set at which depths to do cuts.

bool doCutsNow (int allowForTopOfTree) const

Return true if we want to do cuts If allowForTopOfTree zero then just does on multiples of depth if 1 then allows for doing at top of tree if 2 then says if cuts allowed anywhere apart from root.

void setNumberBeforeTrust (int number)

Set the number of branches before pseudo costs believed in dynamic strong branching.

• int numberBeforeTrust () const

get the number of branches before pseudo costs believed in dynamic strong branching.

void setNumberPenalties (int number)

Set the number of variables for which to compute penalties in dynamic strong branching.

• int numberPenalties () const

get the number of variables for which to compute penalties in dynamic strong branching.

const CbcFullNodeInfo * topOfTree () const

Pointer to top of tree.

void setNumberAnalyzeIterations (int number)

Number of analyze iterations to do.

- int numberAnalyzeIterations () const
- double penaltyScaleFactor () const

Get scale factor to make penalties match strong.

void setPenaltyScaleFactor (double value)

Set scale factor to make penalties match strong.

void setProblemType (int number)

Problem type as set by user or found by analysis.

- int problemType () const
- int currentDepth () const

Current depth.

void setHowOftenGlobalScan (int number)

Set how often to scan global cuts.

int howOftenGlobalScan () const

Get how often to scan global cuts.

int * originalColumns () const

Original columns as created by integerPresolve or preprocessing.

void setOriginalColumns (const int *originalColumns, int numberGood=COIN INT MAX)

Set original columns as created by preprocessing.

OsiRowCut * conflictCut (const OsiSolverInterface *solver, bool &localCuts)

Create conflict cut (well - most of)

void setPrintFrequency (int number)

Set the print frequency.

int printFrequency () const

Get the print frequency.

Methods returning info on how the solution process terminated

· bool isAbandoned () const

Are there a numerical difficulties?

bool isProvenOptimal () const

Is optimality proven?

bool isProvenInfeasible () const

Is infeasiblity proven (or none better than cutoff)?

· bool isContinuousUnbounded () const

Was continuous solution unbounded.

bool isProvenDualInfeasible () const

Was continuous solution unbounded.

· bool isNodeLimitReached () const

Node limit reached?

bool isSecondsLimitReached () const

Time limit reached?

bool isSolutionLimitReached () const

Solution limit reached?

int getIterationCount () const

Get how many iterations it took to solve the problem.

void incrementIterationCount (int value)

Increment how many iterations it took to solve the problem.

int getNodeCount () const

Get how many Nodes it took to solve the problem (including those in complete fathoming B&B inside CLP).

· void incrementNodeCount (int value)

Increment how many nodes it took to solve the problem.

int getExtraNodeCount () const

Get how many Nodes were enumerated in complete fathoming B&B inside CLP.

• int status () const

Final status of problem Some of these can be found out by is.....

- void setProblemStatus (int value)
- int secondaryStatus () const

Secondary status of problem -1 unset (status_ will also be -1) 0 search completed with solution 1 linear relaxation not feasible (or worse than cutoff) 2 stopped on gap 3 stopped on nodes 4 stopped on time 5 stopped on user event 6 stopped on solutions 7 linear relaxation unbounded 8 stopped on iteration limit.

- void setSecondaryStatus (int value)
- bool isInitialSolveAbandoned () const

Are there numerical difficulties (for initialSolve)?

• bool isInitialSolveProvenOptimal () const

Is optimality proven (for initialSolve)?

• bool isInitialSolveProvenPrimalInfeasible () const

Is primal infeasiblity proven (for initialSolve)?

· bool isInitialSolveProvenDualInfeasible () const

Is dual infeasiblity proven (for initialSolve)?

Problem information methods

These methods call the solver's query routines to return information about the problem referred to by the current object.

Querying a problem that has no data associated with it result in zeros for the number of rows and columns, and NULL pointers from the methods that return vectors.

Const pointers returned from any data-query method are valid as long as the data is unchanged and the solver is not called.

• int numberRowsAtContinuous () const

Number of rows in continuous (root) problem.

int getNumCols () const

Get number of columns.

int getNumRows () const

Get number of rows.

• CoinBigIndex getNumElements () const

Get number of nonzero elements.

int numberIntegers () const

Number of integers in problem.

- const int * integerVariable () const
- char integerType (int i) const

Whether or not integer.

const char * integerType () const

Whether or not integer.

const double * getColLower () const

Get pointer to array[getNumCols()] of column lower bounds.

const double * getColUpper () const

Get pointer to array[getNumCols()] of column upper bounds.

const char * getRowSense () const

Get pointer to array[getNumRows()] of row constraint senses.

const double * getRightHandSide () const

Get pointer to array[getNumRows()] of rows right-hand sides.

const double * getRowRange () const

Get pointer to array[getNumRows()] of row ranges.

const double * getRowLower () const

Get pointer to array[getNumRows()] of row lower bounds.

const double * getRowUpper () const

Get pointer to array[getNumRows()] of row upper bounds.

const double * getObjCoefficients () const

Get pointer to array[getNumCols()] of objective function coefficients.

double getObjSense () const

Get objective function sense (1 for min (default), -1 for max)

· bool isContinuous (int collndex) const

Return true if variable is continuous.

bool isBinary (int collndex) const

Return true if variable is binary.

bool isInteger (int collndex) const

Return true if column is integer.

bool isIntegerNonBinary (int colIndex) const

Return true if variable is general integer.

· bool isFreeBinary (int collndex) const

Return true if variable is binary and not fixed at either bound.

const CoinPackedMatrix * getMatrixByRow () const

Get pointer to row-wise copy of matrix.

const CoinPackedMatrix * getMatrixByCol () const

Get pointer to column-wise copy of matrix.

double getInfinity () const

Get solver's value for infinity.

const double * getCbcColLower () const

Get pointer to array[getNumCols()] (for speed) of column lower bounds.

const double * getCbcColUpper () const

Get pointer to array[getNumCols()] (for speed) of column upper bounds.

const double * getCbcRowLower () const

Get pointer to array[getNumRows()] (for speed) of row lower bounds.

const double * getCbcRowUpper () const

Get pointer to array[getNumRows()] (for speed) of row upper bounds.

const double * getCbcColSolution () const

Get pointer to array[getNumCols()] (for speed) of primal solution vector.

const double * getCbcRowPrice () const

Get pointer to array[getNumRows()] (for speed) of dual prices.

const double * getCbcReducedCost () const

Get a pointer to array[getNumCols()] (for speed) of reduced costs.

const double * getCbcRowActivity () const

Get pointer to array[getNumRows()] (for speed) of row activity levels.

Methods related to querying the solution

double * continuousSolution () const

Holds solution at continuous (after cuts if branchAndBound called)

int * usedInSolution () const

Array marked whenever a solution is found if non-zero.

void incrementUsed (const double *solution)

Increases usedInSolution for nonzeros.

• void setBestSolution (CBC_Message how, double &objectiveValue, const double *solution, int fixVariables=0)

Record a new incumbent solution and update objective Value.

void setBestObjectiveValue (double objectiveValue)

Just update objectiveValue.

CbcEventHandler::CbcAction dealWithEventHandler (CbcEventHandler::CbcEvent event, double objValue, const double *solution)

Deals with event handler and solution.

virtual double checkSolution (double cutoff, double *solution, int fixVariables, double originalObjValue)

Call this to really test if a valid solution can be feasible Solution is number columns in size.

bool feasibleSolution (int &numberIntegerInfeasibilities, int &numberObjectInfeasibilities) const

Test the current solution for feasiblility.

double * currentSolution () const

Solution to the most recent lp relaxation.

• const double * testSolution () const

For testing infeasibilities - will point to currentSolution_ or solver->getColSolution()

- void setTestSolution (const double *solution)
- void reserveCurrentSolution (const double *solution=NULL)

Make sure region there and optionally copy solution.

const double * getColSolution () const

Get pointer to array[getNumCols()] of primal solution vector.

const double * getRowPrice () const

Get pointer to array[getNumRows()] of dual prices.

const double * getReducedCost () const

Get a pointer to array[getNumCols()] of reduced costs.

const double * getRowActivity () const

Get pointer to array[getNumRows()] of row activity levels.

double getCurrentObjValue () const

Get current objective function value.

double getCurrentMinimizationObjValue () const

Get current minimization objective function value.

double getMinimizationObjValue () const

Get best objective function value as minimization.

• void setMinimizationObjValue (double value)

Set best objective function value as minimization.

double getObjValue () const

Get best objective function value.

double getBestPossibleObjValue () const

Get best possible objective function value.

void setObjValue (double value)

Set best objective function value.

double getSolverObjValue () const

Get solver objective function value (as minimization)

double * bestSolution () const

The best solution to the integer programming problem.

void setBestSolution (const double *solution, int numberColumns, double objectiveValue, bool check=false)

User callable setBestSolution.

int getSolutionCount () const

Get number of solutions.

void setSolutionCount (int value)

Set number of solutions (so heuristics will be different)

int numberSavedSolutions () const

Number of saved solutions (including best)

int maximumSavedSolutions () const

Maximum number of extra saved solutions.

void setMaximumSavedSolutions (int value)

Set maximum number of extra saved solutions.

const double * savedSolution (int which) const

Return a saved solution (0==best) - NULL if off end.

double savedSolutionObjective (int which) const

Return a saved solution objective (0==best) - COIN DBL MAX if off end.

void deleteSavedSolution (int which)

Delete a saved solution and move others up.

• int phase () const

Current phase (so heuristics etc etc can find out).

int getNumberHeuristicSolutions () const

Get number of heuristic solutions.

void setNumberHeuristicSolutions (int value)

Set number of heuristic solutions.

void setObjSense (double s)

Set objective function sense (1 for min (default), -1 for max,)

· double getContinuousObjective () const

Value of objective at continuous.

- void setContinuousObjective (double value)
- int getContinuousInfeasibilities () const

Number of infeasibilities at continuous.

- void setContinuousInfeasibilities (int value)
- double rootObjectiveAfterCuts () const

Value of objective after root node cuts added.

double sumChangeObjective () const

Sum of Changes to objective by first solve.

· int numberGlobalViolations () const

Number of times global cuts violated.

- void clearNumberGlobalViolations ()
- · bool resolveAfterTakeOffCuts () const

Whether to force a resolve after takeOffCuts.

void setResolveAfterTakeOffCuts (bool yesNo)

• int maximumRows () const

Maximum number of rows.

CoinWarmStartBasis & workingBasis ()

Work basis for temporary use.

• int getStopNumberIterations () const

Get number of "iterations" to stop after.

void setStopNumberIterations (int value)

Set number of "iterations" to stop after.

CbcModel * heuristicModel () const

A pointer to model from CbcHeuristic.

void setHeuristicModel (CbcModel *model)

Set a pointer to model from CbcHeuristic.

Node selection

- CbcCompareBase * nodeComparison () const
- void setNodeComparison (CbcCompareBase *compare)
- void setNodeComparison (CbcCompareBase &compare)

Problem feasibility checking

- CbcFeasibilityBase * problemFeasibility () const
- void setProblemFeasibility (CbcFeasibilityBase *feasibility)
- void setProblemFeasibility (CbcFeasibilityBase &feasibility)

Tree methods and subtree methods

CbcTree * tree () const

Tree method e.g. heap (which may be overridden by inheritance)

void passInTreeHandler (CbcTree &tree)

For modifying tree handling (original is cloned)

void passInSubTreeModel (CbcModel &model)

For passing in an CbcModel to do a sub Tree (with derived tree handlers).

CbcModel * subTreeModel (OsiSolverInterface *solver=NULL) const

For retrieving a copy of subtree model with given OsiSolver.

int numberStoppedSubTrees () const

Returns number of times any subtree stopped on nodes, time etc.

void incrementSubTreeStopped ()

Says a sub tree was stopped.

• int typePresolve () const

Whether to automatically do presolve before branch and bound (subTrees).

void setTypePresolve (int value)

Branching Decisions

See the CbcBranchDecision class for additional information.

• CbcBranchDecision * branchingMethod () const

Get the current branching decision method.

void setBranchingMethod (CbcBranchDecision *method)

Set the branching decision method.

void setBranchingMethod (CbcBranchDecision &method)

Set the branching method.

CbcCutModifier * cutModifier () const

Get the current cut modifier method.

void setCutModifier (CbcCutModifier *modifier)

Set the cut modifier method.

void setCutModifier (CbcCutModifier &modifier)

Set the cut modifier method.

Row (constraint) and Column (variable) cut generation

• int stateOfSearch () const

State of search 0 - no solution 1 - only heuristic solutions 2 - branched to a solution 3 - no solution but many nodes.

- void setStateOfSearch (int state)
- int searchStrategy () const

Strategy worked out - mainly at root node for use by CbcNode.

void setSearchStrategy (int value)

Set strategy worked out - mainly at root node for use by CbcNode.

• int strongStrategy () const

Stong branching strategy.

void setStrongStrategy (int value)

Set strong branching strategy.

• int numberCutGenerators () const

Get the number of cut generators.

CbcCutGenerator ** cutGenerators () const

Get the list of cut generators.

CbcCutGenerator * cutGenerator (int i) const

Get the specified cut generator.

CbcCutGenerator * virginCutGenerator (int i) const

Get the specified cut generator before any changes.

void addCutGenerator (CglCutGenerator *generator, int howOften=1, const char *name=NULL, bool nor-mal=true, bool atSolution=false, bool infeasible=false, int howOftenInSub=-100, int whatDepth=-1, int whatDepthInSub=-1)

Add one generator - up to user to delete generators.

Strategy and sub models

See the CbcStrategy class for additional information.

CbcStrategy * strategy () const

Get the current strategy.

void setStrategy (CbcStrategy &strategy)

Set the strategy. Clones.

void setStrategy (CbcStrategy *strategy)

Set the strategy. assigns.

CbcModel * parentModel () const

Get the current parent model.

void setParentModel (CbcModel &parentModel)

Set the parent model.

Heuristics and priorities

• void addHeuristic (CbcHeuristic *generator, const char *name=NULL, int before=-1)

Add one heuristic - up to user to delete.

CbcHeuristic * heuristic (int i) const

Get the specified heuristic.

• int numberHeuristics () const

Get the number of heuristics.

void setNumberHeuristics (int value)

Set the number of heuristics.

• CbcHeuristic * lastHeuristic () const

Pointer to heuristic solver which found last solution (or NULL)

void setLastHeuristic (CbcHeuristic *last)

set last heuristic which found a solution

void passInPriorities (const int *priorities, bool ifNotSimpleIntegers)

Pass in branching priorities.

• int priority (int sequence) const

Returns priority level for an object (or 1000 if no priorities exist)

void passInEventHandler (const CbcEventHandler *eventHandler)

Set an event handler.

CbcEventHandler * getEventHandler () const

Retrieve a pointer to the event handler.

Setting/Accessing application data

void setApplicationData (void *appData)

Set application data.

void * getApplicationData () const

Get application data.

void passInSolverCharacteristics (OsiBabSolver *solverCharacteristics)

For advanced applications you may wish to modify the behavior of Cbc e.g.

const OsiBabSolver * solverCharacteristics () const

Get solver characteristics.

Message handling etc

void passInMessageHandler (CoinMessageHandler *handler)

Pass in Message handler (not deleted at end)

void newLanguage (CoinMessages::Language language)

Set language.

- void setLanguage (CoinMessages::Language language)
- CoinMessageHandler * messageHandler () const

Return handler.

• CoinMessages & messages ()

Return messages.

CoinMessages * messagesPointer ()

Return pointer to messages.

void setLogLevel (int value)

Set log level.

• int logLevel () const

Get log level.

void setDefaultHandler (bool yesNo)

Set flag to say if handler_ is the default handler.

• bool defaultHandler () const

Check default handler.

Specialized

void setSpecialOptions (int value)

Set special options 0 bit (1) - check if cuts valid (if on debugger list) 1 bit (2) - use current basis to check integer solution (rather than all slack) 2 bit (4) - don't check integer solution (by solving LP) 3 bit (8) - fast analyze 4 bit (16) - non-linear model - so no well defined CoinPackedMatrix 5 bit (32) - keep names 6 bit (64) - try for dominated columns 7 bit (128) - SOS type 1 but all declared integer 8 bit (256) - Set to say solution just found, unset by doing cuts 9 bit (512) - Try reduced model after 100 nodes 10 bit (1024) - Switch on some heuristics even if seems unlikely 11 bit (2048) - Mark as in small branch and bound 12 bit (4096) - Funny cuts so do slow way (in some places) 13 bit (8192) - Funny cuts so do

slow way (in other places) 14 bit (16384) - Use Cplex! for fathoming 15 bit (32768) - Try reduced model after 0 nodes 16 bit (65536) - Original model had integer bounds 17 bit (131072) - Perturbation switched off 18 bit (262144) - donor CbcModel 19 bit (524288) - recipient CbcModel 20 bit (1048576) - waiting for sub model to return 22 bit (4194304) - do not initialize random seed in solver (user has) 23 bit (8388608) - leave solver_ with cuts 24 bit (16777216) - just get feasible if no cutoff.

• int specialOptions () const

Get special options.

void setRandomSeed (int value)

Set random seed.

• int getRandomSeed () const

Get random seed.

void setMultipleRootTries (int value)

Set multiple root tries.

int getMultipleRootTries () const

Get multiple root tries.

void sayEventHappened ()

Tell model to stop on event.

· bool normalSolver () const

Says if normal solver i.e. has well defined CoinPackedMatrix.

bool waitingForMiniBranchAndBound () const

Says if model is sitting there waiting for mini branch and bound to finish This is because an event handler may only have access to parent model in mini branch and bound.

void setMoreSpecialOptions (int value)

Set more special options at present bottom 6 bits used for shadow price mode 1024 for experimental hotstart 2048,4096 breaking out of cuts 8192 slowly increase minimum drop 16384 gomory 32768 more heuristics in sub trees 65536 no cuts in preprocessing 131072 Time limits elapsed 18 bit (262144) - Perturb fathom nodes 19 bit (524288) - No limit on fathom nodes 20 bit (1048576) - Reduce sum of infeasibilities before cuts 21 bit (2097152) - Reduce sum of infeasibilities after cuts 22 bit (4194304) - Conflict analysis 23 bit (8388608) - Conflict analysis - temporary bit 24 bit (16777216) - Add cutoff as LP constraint (out) 25 bit (33554432) - diving/reordering 26 bit (67108864) - load global cuts from file 27 bit (134217728) - append binding global cuts to file 28 bit (268435456) - idiot branching 29 bit (536870912) - don't make fake objective.

• int moreSpecialOptions () const

Get more special options.

void setMoreSpecialOptions2 (int value)

Set more more special options 0 bit (1) - find switching variables 1 bit (2) - using fake objective until solution 2 bit (4) - switching variables exist 3 bit (8) - skip most of setBestSolution checks 4 bit (16) - very lightweight preprocessing in smallB&B 5 bit (32) - event handler needs to be cloned when parallel.

• int moreSpecialOptions2 () const

Get more special options2.

void setCutoffAsConstraint (bool yesNo)

Set cutoff as constraint.

void setUseElapsedTime (bool yesNo)

Set time method.

• bool useElapsedTime () const

Get time method.

void * temporaryPointer () const

Get useful temporary pointer.

void setTemporaryPointer (void *pointer)

Set useful temporary pointer.

• void goToDantzig (int numberNodes, ClpDualRowPivot *&savePivotMethod)

Go to dantzig pivot selection if easy problem (clp only)

• bool ownObjects () const

Now we may not own objects - just point to solver's objects.

void checkModel ()

Check original model before it gets messed up.

Constructors and destructors etc

CbcModel ()

Default Constructor.

CbcModel (const OsiSolverInterface &)

Constructor from solver.

void assignSolver (OsiSolverInterface *&solver, bool deleteSolver=true)

Assign a solver to the model (model assumes ownership)

• void setModelOwnsSolver (bool ourSolver)

Set ownership of solver.

bool modelOwnsSolver ()

Get ownership of solver.

CbcModel (const CbcModel &rhs, bool cloneHandler=false)

Copy constructor.

virtual CbcModel * clone (bool cloneHandler)

Clone

CbcModel & operator= (const CbcModel &rhs)

Assignment operator.

virtual ∼CbcModel ()

Destructor.

OsiSolverInterface * solver () const

Returns solver - has current state.

OsiSolverInterface * swapSolver (OsiSolverInterface *solver)

Returns current solver - sets new one.

OsiSolverInterface * continuousSolver () const

Returns solver with continuous state.

void createContinuousSolver ()

Create solver with continuous state.

void clearContinuousSolver ()

Clear solver with continuous state.

OsiSolverInterface * referenceSolver () const

A copy of the solver, taken at constructor or by saveReferenceSolver.

void saveReferenceSolver ()

Save a copy of the current solver so can be reset to.

void resetToReferenceSolver ()

Uses a copy of reference solver to be current solver.

void gutsOfDestructor ()

Clears out as much as possible (except solver)

void gutsOfDestructor2 ()

Clears out enough to reset CbcModel as if no branch and bound done.

void resetModel ()

Clears out enough to reset CbcModel cutoff etc.

void gutsOfCopy (const CbcModel &rhs, int mode=0)

Most of copy constructor mode - 0 copy but don't delete before 1 copy and delete before 2 copy and delete before (but use virgin generators)

void moveInfo (const CbcModel &rhs)

Move status, nodes etc etc across.

semi-private i.e. users should not use

• int getNodeCount2 () const

Get how many Nodes it took to solve the problem.

void setPointers (const OsiSolverInterface *solver)

Set pointers for speed.

int reducedCostFix ()

Perform reduced cost fixing.

void synchronizeHandlers (int makeDefault)

Makes all handlers same.

void saveExtraSolution (const double *solution, double objectiveValue)

Save a solution to saved list.

void saveBestSolution (const double *solution, double objectiveValue)

Save a solution to best and move current to saved.

void deleteSolutions ()

Delete best and saved solutions.

int resolve (OsiSolverInterface *solver)

Encapsulates solver resolve.

 int chooseBranch (CbcNode *&newNode, int numberPassesLeft, CbcNode *oldNode, OsiCuts &cuts, bool &resolved, CoinWarmStartBasis *lastws, const double *lowerBefore, const double *upperBefore, OsiSolver-Branch *&branches)

Encapsulates choosing a variable - anyAction -2, infeasible (-1 round again), 0 done.

- int chooseBranch (CbcNode *newNode, int numberPassesLeft, bool &resolved)
- CoinWarmStartBasis * getEmptyBasis (int ns=0, int na=0) const

Return an empty basis object of the specified size.

 int takeOffCuts (OsiCuts &cuts, bool allowResolve, OsiCuts *saveCuts, int numberNewCuts=0, const OsiRow-Cut **newCuts=NULL)

Remove inactive cuts from the model.

• int addCuts (CbcNode *node, CoinWarmStartBasis *&lastws, bool canFix)

Determine and install the active cuts that need to be added for the current subproblem.

bool addCuts1 (CbcNode *node, CoinWarmStartBasis *&lastws)

Traverse the tree from node to root and prep the model.

void previousBounds (CbcNode *node, CbcNodeInfo *where, int iColumn, double &lower, double &upper, int force)

Returns bounds just before where - initially original bounds.

void setObjectiveValue (CbcNode *thisNode, const CbcNode *parentNode) const

Set objective value in a node.

void convertToDynamic ()

If numberBeforeTrust > 0 then we are going to use CbcBranchDynamic.

void synchronizeNumberBeforeTrust (int type=0)

Set numberBeforeTrust in all objects.

void zapIntegerInformation (bool leaveObjects=true)

Zap integer information in problem (may leave object info)

int cliquePseudoCosts (int doStatistics)

Use cliques for pseudocost information - return nonzero if infeasible.

void pseudoShadow (int type)

Fill in useful estimates.

• void fillPseudoCosts (double *downCosts, double *upCosts, int *priority=NULL, int *numberDown=NULL, int *numberUp=NULL, int *numberUpInfeasible=NULL) const

Return pseudo costs If not all integers or not pseudo costs - returns all zero Length of arrays are numberIntegers() and entries correspond to integerVariable()[i] User must allocate arrays before call.

void doHeuristicsAtRoot (int deleteHeuristicsAfterwards=0)

Do heuristics at root.

· void adjustHeuristics ()

Adjust heuristics based on model.

const double * hotstartSolution () const

Get the hotstart solution.

const int * hotstartPriorities () const

Get the hotstart priorities.

CbcCountRowCut ** addedCuts () const

Return the list of cuts initially collected for this subproblem.

int currentNumberCuts () const

Number of entries in the list returned by addedCuts()

CbcRowCuts * globalCuts ()

Global cuts.

void setNextRowCut (const OsiRowCut &cut)

Copy and set a pointer to a row cut which will be added instead of normal branching.

CbcNode * currentNode () const

Get a pointer to current node (be careful)

CglTreeProbingInfo * probingInfo () const

Get a pointer to probing info.

CoinThreadRandom * randomNumberGenerator ()

Thread specific random number generator.

void setNumberStrongIterations (int number)

Set the number of iterations done in strong branching.

• int numberStrongIterations () const

Get the number of iterations done in strong branching.

• int maximumNumberIterations () const

Get maximum number of iterations (designed to be used in heuristics)

void setMaximumNumberIterations (int value)

Set maximum number of iterations (designed to be used in heuristics)

void setFastNodeDepth (int value)

Set depth for fast nodes.

· int fastNodeDepth () const

Get depth for fast nodes.

int continuousPriority () const

Get anything with priority >= this can be treated as continuous.

void setContinuousPriority (int value)

Set anything with priority >= this can be treated as continuous.

- void incrementExtra (int nodes, int iterations)
- int numberExtralterations () const

Number of extra iterations.

· void incrementStrongInfo (int numberTimes, int numberIterations, int numberFixed, bool ifInfeasible)

Increment strong info.

• const int * strongInfo () const

Return strong info.

• int * mutableStrongInfo ()

Return mutable strong info.

CglStored * storedRowCuts () const

Get stored row cuts for donor/recipient CbcModel.

void setStoredRowCuts (CglStored *cuts)

Set stored row cuts for donor/recipient CbcModel.

• bool allDynamic () const

Says whether all dynamic integers.

void generateCpp (FILE *fp, int options)

Create C++ lines to get to current state.

• OsiBranchingInformation usefulInformation () const

Generate an OsiBranchingInformation object.

void setBestSolutionBasis (const CoinWarmStartBasis &bestSolutionBasis)

Warm start object produced by heuristic or strong branching.

void redoWalkBack ()

Redo walkback arrays.

Solve methods

• void initialSolve ()

Solve the initial LP relaxation.

void branchAndBound (int doStatistics=0)

Invoke the branch & cut algorithm.

void addUpdateInformation (const CbcObjectUpdateData &data)

Adds an update information object.

int doOneNode (CbcModel *baseModel, CbcNode *&node, CbcNode *&newNode)

Do one node - broken out for clarity? also for parallel (when baseModel!=this) Returns 1 if solution found node NULL on return if no branches left newNode NULL if no new node created.

int resolve (CbcNodeInfo *parent, int whereFrom, double *saveSolution=NULL, double *saveLower=NULL, double *saveUpper=NULL)

Reoptimise an LP relaxation.

void makeGlobalCuts (int numberRows, const int *which)

Make given rows (L or G) into global cuts and remove from lp.

void makeGlobalCut (const OsiRowCut *cut)

Make given cut into a global cut.

void makeGlobalCut (const OsiRowCut &cut)

Make given cut into a global cut.

void makeGlobalCut (const OsiColCut *cut)

Make given column cut into a global cut.

void makeGlobalCut (const OsiColCut &cut)

Make given column cut into a global cut.

• void makePartialCut (const OsiRowCut *cut, const OsiSolverInterface *solver=NULL)

Make partial cut into a global cut and save.

void makeGlobalCuts ()

Make partial cuts into global cuts.

const int * whichGenerator () const

Which cut generator generated this cut.

Multithreading

• CbcThread * masterThread () const

Get pointer to masterthread.

CbcNodeInfo ** walkback () const

Get pointer to walkback.

int getNumberThreads () const

Get number of threads.

void setNumberThreads (int value)

Set number of threads.

int getThreadMode () const

Get thread mode.

void setThreadMode (int value)

Set thread mode always use numberThreads for branching 1 set then deterministic 2 set then use numberThreads for root cuts 4 set then use numberThreads in root mini branch and bound 8 set and numberThreads - do heuristics numberThreads at a time 8 set and numberThreads==0 do all heuristics at once default is 0.

int parallelMode () const

Return -2 if deterministic threaded and main thread -1 if deterministic threaded and serial thread 0 if serial 1 if opportunistic threaded.

· bool isLocked () const

From here to end of section - code in CbcThread.cpp until class changed Returns true if locked.

- void lockThread ()
- void unlockThread ()
- void setInfoInChild (int type, CbcThread *info)

Set information in a child -3 pass pointer to child thread info -2 just stop -1 delete simple child stuff 0 delete opportunistic child stuff 1 delete deterministic child stuff.

void moveToModel (CbcModel *baseModel, int mode)

Move/copy information from one model to another -1 - initialization 0 - from base model 1 - to base model (and reset) 2 - add in final statistics etc (and reset so can do clean destruction)

int splitModel (int numberModels, CbcModel **model, int numberNodes)

Split up nodes.

void startSplitModel (int numberIterations)

Start threads

void mergeModels (int numberModel, CbcModel **model, int numberNodes)

Merge models.

static bool haveMultiThreadSupport ()

Indicates whether Cbc library has been compiled with multithreading support.

7.74.1 Detailed Description

Simple Branch and bound class.

The initialSolve() method solves the initial LP relaxation of the MIP problem. The branchAndBound() method can then be called to finish using a branch and cut algorithm.

Search Tree Traversal

Subproblems (aka nodes) requiring additional evaluation are stored using the CbcNode and CbcNodeInfo objects. Ancestry linkage is maintained in the CbcNodeInfo object. Evaluation of a subproblem within branchAndBound() proceeds as follows:

- The node representing the most promising parent subproblem is popped from the heap which holds the set of subproblems requiring further evaluation.
- Using branching instructions stored in the node, and information in its ancestors, the model and solver are adjusted to create the active subproblem.
- If the parent subproblem will require further evaluation (*i.e.*, there are branches remaining) its node is pushed back on the heap. Otherwise, the node is deleted. This may trigger recursive deletion of ancestors.
- The newly created subproblem is evaluated.
- If the subproblem requires further evaluation, a node is created. All information needed to recreate the subproblem (branching information, row and column cuts) is placed in the node and the node is added to the set of subproblems awaiting further evaluation.

Note that there is never a node representing the active subproblem; the model and solver represent the active subproblem.

Row (Constraint) Cut Handling

For a typical subproblem, the sequence of events is as follows:

• The subproblem is rebuilt for further evaluation: One result of a call to addCuts() is a traversal of ancestors, leaving a list of all cuts used in the ancestors in #addedCuts_. This list is then scanned to construct a basis that includes only tight cuts. Entries for loose cuts are set to NULL.

- The subproblem is evaluated: One result of a call to solveWithCuts() is the return of a set of newly generated cuts for the subproblem. #addedCuts is also kept up-to-date as old cuts become loose.
- The subproblem is stored for further processing: A call to CbcNodeInfo::addCuts() adds the newly generated cuts to the CbcNodeInfo object associated with this node.

See CbcCountRowCut for details of the bookkeeping associated with cut management.

Definition at line 100 of file CbcModel.hpp.

7.74.2 Member Enumeration Documentation

7.74.2.1 enum CbcModel::CbcIntParam

Enumerator

CbcMaxNumNode The maximum number of nodes before terminating.

CbcMaxNumSol The maximum number of solutions before terminating.

CbcFathomDiscipline Fathoming discipline. Controls objective function comparisons for purposes of fathoming by bound or determining monotonic variables.

If 1, action is taken only when the current objective is strictly worse than the target. Implementation is handled by adding a small tolerance to the target.

CbcPrinting Adjusts printout 1 does different node message with number unsatisfied on last branch.

CbcNumberBranches Number of branches (may be more than number of nodes as may include strong branching)

CbcLastIntParam Just a marker, so that a static sized array can store parameters.

Definition at line 104 of file CbcModel.hpp.

7.74.2.2 enum CbcModel::CbcDblParam

Enumerator

CbcIntegerTolerance The maximum amount the value of an integer variable can vary from integer and still be considered feasible.

CbcInfeasibilityWeight The objective is assumed to worsen by this amount for each integer infeasibility.

CbcCutoffIncrement The amount by which to tighten the objective function cutoff when a new solution is discovered.

CbcAllowableGap Stop when the gap between the objective value of the best known solution and the best bound on the objective of any solution is less than this. This is an absolute value. Conversion from a percentage is left to the client.

CbcAllowableFractionGap Stop when the gap between the objective value of the best known solution and the best bound on the objective of any solution is less than this fraction of of the absolute value of best known solution. Code stops if either this test or CbcAllowableGap test succeeds

CbcMaximumSeconds The maximum number of seconds before terminating. A double should be adequate!

CbcCurrentCutoff Cutoff - stored for speed.

CbcOptimizationDirection Optimization direction - stored for speed.

CbcCurrentObjectiveValue Current objective value.

CbcCurrentMinimizationObjectiveValue Current minimization objective value.

CbcStartSeconds The time at start of model. So that other pieces of code can access

CbcHeuristicGap Stop doing heuristics when the gap between the objective value of the best known solution and the best bound on the objective of any solution is less than this. This is an absolute value. Conversion from a percentage is left to the client.

CbcHeuristicFractionGap Stop doing heuristics when the gap between the objective value of the best known solution and the best bound on the objective of any solution is less than this fraction of of the absolute value of best known solution. Code stops if either this test or CbcAllowableGap test succeeds

CbcSmallestChange Smallest non-zero change on a branch.

CbcSumChange Sum of non-zero changes on a branch.

CbcLargestChange Largest non-zero change on a branch.

CbcSmallChange Small non-zero change on a branch to be used as guess.

CbcLastDblParam Just a marker, so that a static sized array can store parameters.

Definition at line 130 of file CbcModel.hpp.

```
7.74.3 Constructor & Destructor Documentation

7.74.3.1 CbcModel::CbcModel ( )

Default Constructor.

7.74.3.2 CbcModel::CbcModel ( const OsiSolverInterface & )

Constructor from solver.

7.74.3.3 CbcModel::CbcModel ( const CbcModel & rhs, bool cloneHandler = false )

Copy constructor .

If cloneHandler is true then message handler is cloned

7.74.3.4 virtual CbcModel::~CbcModel ( ) [virtual]
```

7.74.4 Member Function Documentation

7.74.4.1 void CbcModel::initialSolve ()

Solve the initial LP relaxation.

Destructor.

Invoke the solver's initialSolve() method.

7.74.4.2 void CbcModel::branchAndBound (int doStatistics = 0)

Invoke the branch & cut algorithm.

The method assumes that initialSolve() has been called to solve the LP relaxation. It processes the root node, then proceeds to explore the branch & cut search tree. The search ends when the tree is exhausted or one of several execution limits is reached. If doStatistics is 1 summary statistics are printed if 2 then also the path to best solution (if found by branching) if 3 then also one line per node

7.74.4.3 void CbcModel::addUpdateInformation (const CbcObjectUpdateData & data)

Adds an update information object.

```
7.74.4.4 int CbcModel::doOneNode ( CbcModel * baseModel, CbcNode *& node, CbcNode *& newNode )
```

Do one node - broken out for clarity? also for parallel (when baseModel!=this) Returns 1 if solution found node NULL on return if no branches left newNode NULL if no new node created.

```
7.74.4.5 int CbcModel::resolve ( CbcNodelnfo * parent, int whereFrom, double * saveSolution = NULL, double * saveUower = NULL, double * saveUpper = NULL)
```

Reoptimise an LP relaxation.

Invoke the solver's resolve() method. whereFrom - 0 - initial continuous 1 - resolve on branch (before new cuts) 2 - after new cuts 3 - obsolete code or something modified problem in unexpected way 10 - after strong branching has fixed variables at root 11 - after strong branching has fixed variables in tree

returns 1 feasible, 0 infeasible, -1 feasible but skip cuts

```
7.74.4.6 void CbcModel::makeGlobalCuts ( int numberRows, const int * which )
```

Make given rows (L or G) into global cuts and remove from lp.

```
7.74.4.7 void CbcModel::makeGlobalCut ( const OsiRowCut * cut )
```

Make given cut into a global cut.

```
7.74.4.8 void CbcModel::makeGlobalCut ( const OsiRowCut & cut )
```

Make given cut into a global cut.

```
7.74.4.9 void CbcModel::makeGlobalCut ( const OsiColCut * cut )
```

Make given column cut into a global cut.

```
7.74.4.10 void CbcModel::makeGlobalCut ( const OsiColCut & cut )
```

Make given column cut into a global cut.

```
7.74.4.11 void CbcModel::makePartialCut ( const OsiRowCut * cut, const OsiSolverInterface * solver = NULL )
```

Make partial cut into a global cut and save.

```
7.74.4.12 void CbcModel::makeGlobalCuts ( )
```

Make partial cuts into global cuts.

```
7.74.4.13 const int* CbcModel::whichGenerator ( ) const [inline]
```

Which cut generator generated this cut.

Definition at line 364 of file CbcModel.hpp.

7.74.4.14 CbcModel* CbcModel::findCliques (bool makeEquality, int atLeastThisMany, int lessThanThis, int defaultValue = 1000)

Identify cliques and construct corresponding objects.

Find cliques with size in the range [atLeastThisMany, lessThanThis] and construct corresponding CbcClique objects. If makeEquality is true then a new model may be returned if modifications had to be made, otherwise this is returned. If the problem is infeasible #numberObjects_ is set to -1. A client must use deleteObjects() before a second call to findCliques(). If priorities exist, clique priority is set to the default.

7.74.4.15 CbcModel* CbcModel::integerPresolve (bool weak = false)

Do integer presolve, creating a new (presolved) model.

Returns the new model, or NULL if feasibility is lost. If weak is true then just does a normal presolve

Todo It remains to work out the cleanest way of getting a solution to the original problem at the end. So this is very preliminary.

7.74.4.16 bool CbcModel::integerPresolveThisModel (OsiSolverInterface * originalSolver, bool weak = false)

Do integer presolve, modifying the current model.

Returns true if the model remains feasible after presolve.

7.74.4.17 void CbcModel::originalModel (CbcModel * presolvedModel, bool weak)

Put back information into the original model after integer presolve.

7.74.4.18 bool CbcModel::tightenVubs (int type, bool allowMultipleBinary = false, double useCutoff = 1.0e50)

For variables involved in VUB constraints, see if we can tighten bounds by solving lp's.

Returns false if feasibility is lost. If CglProbing is available, it will be tried as well to see if it can tighten bounds. This routine is just a front end for tighten Vubs (int, const int*, double).

If type = -1 all variables are processed (could be very slow). If type = 0 only variables involved in VUBs are processed. If type = n > 0, only the n most expensive VUB variables are processed, where it is assumed that x is at its maximum so delta would have to go to 1 (if x not at bound).

If allowMultipleBinary is true, then a VUB constraint is a row with one continuous variable and any number of binary variables.

If useCutoff < 1.0e30, the original objective is installed as a constraint with useCutoff as a bound.

7.74.4.19 bool CbcModel::tightenVubs (int numberVubs, const int * which, double useCutoff = 1.0e50)

For variables involved in VUB constraints, see if we can tighten bounds by solving lp's.

This version is just handed a list of variables to be processed.

7.74.4.20 void CbcModel::analyzeObjective ()

Analyze problem to find a minimum change in the objective function.

7.74.4.21 void CbcModel::AddIntegers ()

Add additional integers.

```
7.74.4.22 void CbcModel::saveModel ( OsiSolverInterface * saveSolver, double * checkCutoffForRestart, bool * feasible )
Save copy of the model.
7.74.4.23 void CbcModel::flipModel()
Flip direction of optimization on all models.
7.74.4.24 int CbcModel::numberObjects ( ) const [inline]
Get the number of objects.
Definition at line 462 of file CbcModel.hpp.
7.74.4.25 void CbcModel::setNumberObjects (int number) [inline]
Set the number of objects.
Definition at line 466 of file CbcModel.hpp.
7.74.4.26 OsiObject** CbcModel::objects() const [inline]
Get the array of objects.
Definition at line 471 of file CbcModel.hpp.
7.74.4.27 const OsiObject* CbcModel::object (int which ) const [inline]
Get the specified object.
Definition at line 476 of file CbcModel.hpp.
7.74.4.28 OsiObject* CbcModel::modifiableObject ( int which ) const [inline]
Get the specified object.
Definition at line 480 of file CbcModel.hpp.
7.74.4.29 void CbcModel::setOptionalInteger (int index)
7.74.4.30 void CbcModel::deleteObjects ( bool findIntegers = true )
Delete all object information (and just back to integers if true)
7.74.4.31 void CbcModel::addObjects ( int numberObjects, OsiObject ** objects )
Add in object information.
Objects are cloned; the owner can delete the originals.
7.74.4.32 void CbcModel::addObjects (int numberObjects, CbcObject ** objects)
Add in object information.
Objects are cloned; the owner can delete the originals.
7.74.4.33 void CbcModel::synchronizeModel ( )
Ensure attached objects point to this model.
```

7.74.4.34 void CbcModel::findIntegers (bool startAgain, int type = 0) Identify integer variables and create corresponding objects. Record integer variables and create an CbcSimpleInteger object for each one. If startAgain is true, a new scan is forced, overwriting any existing integer variable information. If type > 0 then 1==PseudoCost, 2 new ones low priority 7.74.4.35 bool CbcModel::setIntParam (CbcIntParam key, int value) [inline] Set an integer parameter. Definition at line 538 of file CbcModel.hpp. 7.74.4.36 bool CbcModel::setDblParam (CbcDblParam key, double value) [inline] Set a double parameter. Definition at line 543 of file CbcModel.hpp. 7.74.4.37 int CbcModel::getIntParam (CbcIntParam key) const [inline] Get an integer parameter. Definition at line 548 of file CbcModel.hpp. 7.74.4.38 double CbcModel::getDblParam (CbcDblParam key) const [inline] Get a double parameter. Definition at line 552 of file CbcModel.hpp. 7.74.4.39 void CbcModel::setCutoff (double value) Set cutoff bound on the objective function. When using strict comparison, the bound is adjusted by a tolerance to avoid accidentally cutting off the optimal solution. 7.74.4.40 double CbcModel::getCutoff() const [inline] Get the cutoff bound on the objective function - always as minimize. Definition at line 563 of file CbcModel.hpp. 7.74.4.41 bool CbcModel::setMaximumNodes (int value) [inline] Set the maximum node limit. Definition at line 570 of file CbcModel.hpp. 7.74.4.42 int CbcModel::getMaximumNodes () const [inline] Get the maximum node limit . Definition at line 575 of file CbcModel.hpp. 7.74.4.43 bool CbcModel::setMaximumSolutions (int value) [inline]

Set the maximum number of solutions desired.

Definition at line 583 of file CbcModel.hpp.

```
7.74.4.44 int CbcModel::getMaximumSolutions ( ) const [inline]
Get the maximum number of solutions desired.
Definition at line 590 of file CbcModel.hpp.
7.74.4.45 bool CbcModel::setPrintingMode (int value) [inline]
Set the printing mode.
Definition at line 594 of file CbcModel.hpp.
7.74.4.46 int CbcModel::getPrintingMode() const [inline]
Get the printing mode.
Definition at line 599 of file CbcModel.hpp.
7.74.4.47 bool CbcModel::setMaximumSeconds ( double value ) [inline]
Set the maximum number of seconds desired.
Definition at line 607 of file CbcModel.hpp.
7.74.4.48 double CbcModel::getMaximumSeconds ( ) const [inline]
Get the maximum number of seconds desired.
Definition at line 614 of file CbcModel.hpp.
7.74.4.49 double CbcModel::getCurrentSeconds ( ) const
Current time since start of branchAndbound.
7.74.4.50 bool CbcModel::maximumSecondsReached ( ) const
Return true if maximum time reached.
7.74.4.51 bool CbcModel::setIntegerTolerance ( double value ) [inline]
Set the integrality tolerance.
Definition at line 626 of file CbcModel.hpp.
7.74.4.52 double CbcModel::getIntegerTolerance() const [inline]
Get the integrality tolerance.
Definition at line 632 of file CbcModel.hpp.
7.74.4.53 bool CbcModel::setInfeasibilityWeight ( double value ) [inline]
Set the weight per integer infeasibility.
Definition at line 640 of file CbcModel.hpp.
7.74.4.54 double CbcModel::getInfeasibilityWeight() const [inline]
Get the weight per integer infeasibility.
```

Definition at line 647 of file CbcModel.hpp.

```
7.74.4.55 bool CbcModel::setAllowableGap ( double value ) [inline]
```

Set the allowable gap between the best known solution and the best possible solution.

Definition at line 654 of file CbcModel.hpp.

```
7.74.4.56 double CbcModel::getAllowableGap ( ) const [inline]
```

Get the allowable gap between the best known solution and the best possible solution.

Definition at line 660 of file CbcModel.hpp.

```
7.74.4.57 bool CbcModel::setAllowableFractionGap ( double value ) [inline]
```

Set the fraction allowable gap between the best known solution and the best possible solution.

Definition at line 667 of file CbcModel.hpp.

```
7.74.4.58 double CbcModel::getAllowableFractionGap ( ) const [inline]
```

Get the fraction allowable gap between the best known solution and the best possible solution.

Definition at line 673 of file CbcModel.hpp.

```
7.74.4.59 bool CbcModel::setAllowablePercentageGap ( double value ) [inline]
```

Set the percentage allowable gap between the best known solution and the best possible solution.

Definition at line 679 of file CbcModel.hpp.

```
7.74.4.60 double CbcModel::getAllowablePercentageGap ( ) const [inline]
```

Get the percentage allowable gap between the best known solution and the best possible solution.

Definition at line 685 of file CbcModel.hpp.

```
7.74.4.61 bool CbcModel::setHeuristicGap ( double value ) [inline]
```

Set the heuristic gap between the best known solution and the best possible solution.

Definition at line 691 of file CbcModel.hpp.

```
7.74.4.62 double CbcModel::getHeuristicGap ( ) const [inline]
```

Get the heuristic gap between the best known solution and the best possible solution.

Definition at line 697 of file CbcModel.hpp.

```
7.74.4.63 bool CbcModel::setHeuristicFractionGap ( double value ) [inline]
```

Set the fraction heuristic gap between the best known solution and the best possible solution.

Definition at line 704 of file CbcModel.hpp.

```
7.74.4.64 double CbcModel::getHeuristicFractionGap ( ) const [inline]
```

Get the fraction heuristic gap between the best known solution and the best possible solution.

Definition at line 710 of file CbcModel.hpp.

```
7.74.4.65 bool CbcModel::setCutoffIncrement ( double value ) [inline]
Set the CbcModel::CbcCutoffIncrement desired.
Definition at line 717 of file CbcModel.hpp.
7.74.4.66 double CbcModel::getCutoffIncrement() const [inline]
Get the CbcModel::CbcCutoffIncrement desired.
Definition at line 724 of file CbcModel.hpp.
7.74.4.67 bool CbcModel::canStopOnGap ( ) const
See if can stop on gap.
7.74.4.68 void CbcModel::setHotstartSolution ( const double * solution, const int * priorities = NULL )
Pass in target solution and optional priorities.
If priorities then >0 means only branch if incorrect while <0 means branch even if correct. +1 or -1 are highest priority
7.74.4.69 void CbcModel::setMinimumDrop ( double value ) [inline]
Set the minimum drop to continue cuts.
Definition at line 737 of file CbcModel.hpp.
7.74.4.70 double CbcModel::getMinimumDrop ( ) const [inline]
Get the minimum drop to continue cuts.
Definition at line 741 of file CbcModel.hpp.
7.74.4.71 void CbcModel::setMaximumCutPassesAtRoot(int value) [inline]
Set the maximum number of cut passes at root node (default 20) Minimum drop can also be used for fine tuning.
Definition at line 747 of file CbcModel.hpp.
7.74.4.72 int CbcModel::getMaximumCutPassesAtRoot()const [inline]
Get the maximum number of cut passes at root node.
Definition at line 751 of file CbcModel.hpp.
7.74.4.73 void CbcModel::setMaximumCutPasses (int value) [inline]
Set the maximum number of cut passes at other nodes (default 10) Minimum drop can also be used for fine tuning.
Definition at line 757 of file CbcModel.hpp.
7.74.4.74 int CbcModel::getMaximumCutPasses ( ) const [inline]
Get the maximum number of cut passes at other nodes (default 10)
Definition at line 761 of file CbcModel.hpp.
7.74.4.75 int CbcModel::getCurrentPassNumber() const [inline]
Get current cut pass number in this round of cuts.
```

(1 is first pass)

Definition at line 766 of file CbcModel.hpp.

7.74.4.76 void CbcModel::setCurrentPassNumber(int value) [inline]

Set current cut pass number in this round of cuts.

(1 is first pass)

Definition at line 771 of file CbcModel.hpp.

7.74.4.77 void CbcModel::setNumberStrong (int number)

Set the maximum number of candidates to be evaluated for strong branching.

A value of 0 disables strong branching.

7.74.4.78 int CbcModel::numberStrong() const [inline]

Get the maximum number of candidates to be evaluated for strong branching.

Definition at line 784 of file CbcModel.hpp.

7.74.4.79 void CbcModel::setPreferredWay (int value) [inline]

Set global preferred way to branch -1 down, +1 up, 0 no preference.

Definition at line 789 of file CbcModel.hpp.

7.74.4.80 int CbcModel::getPreferredWay() const [inline]

Get the preferred way to branch (default 0)

Definition at line 793 of file CbcModel.hpp.

7.74.4.81 int CbcModel::whenCuts () const [inline]

Get at which depths to do cuts.

Definition at line 797 of file CbcModel.hpp.

7.74.4.82 void CbcModel::setWhenCuts (int value) [inline]

Set at which depths to do cuts.

Definition at line 801 of file CbcModel.hpp.

7.74.4.83 bool CbcModel::doCutsNow (int allowForTopOfTree) const

Return true if we want to do cuts If allowForTopOfTree zero then just does on multiples of depth if 1 then allows for doing at top of tree if 2 then says if cuts allowed anywhere apart from root.

7.74.4.84 void CbcModel::setNumberBeforeTrust (int number)

Set the number of branches before pseudo costs believed in dynamic strong branching.

A value of 0 disables dynamic strong branching.

7.74.4.85 int CbcModel::numberBeforeTrust() const [inline]

get the number of branches before pseudo costs believed in dynamic strong branching.

Definition at line 819 of file CbcModel.hpp. 7.74.4.86 void CbcModel::setNumberPenalties (int number) Set the number of variables for which to compute penalties in dynamic strong branching. A value of 0 disables penalties. 7.74.4.87 int CbcModel::numberPenalties () const [inline] get the number of variables for which to compute penalties in dynamic strong branching. Definition at line 830 of file CbcModel.hpp. 7.74.4.88 const CbcFullNodeInfo* CbcModel::topOfTree() const [inline] Pointer to top of tree. Definition at line 834 of file CbcModel.hpp. 7.74.4.89 void CbcModel::setNumberAnalyzeIterations (int number) [inline] Number of analyze iterations to do. Definition at line 837 of file CbcModel.hpp. 7.74.4.90 int CbcModel::numberAnalyzeIterations () const [inline] Definition at line 840 of file CbcModel.hpp. 7.74.4.91 double CbcModel::penaltyScaleFactor() const [inline] Get scale factor to make penalties match strong. Should/will be computed Definition at line 845 of file CbcModel.hpp. 7.74.4.92 void CbcModel::setPenaltyScaleFactor (double value) Set scale factor to make penalties match strong. Should/will be computed 7.74.4.93 void CbcModel::setProblemType (int number) [inline] Problem type as set by user or found by analysis. This will be extended 0 - not known 1 - Set partitioning <= 2 - Set partitioning == 3 - Set covering 4 - all +- 1 or all +1 and odd Definition at line 858 of file CbcModel.hpp. 7.74.4.94 int CbcModel::problemType() const [inline] Definition at line 861 of file CbcModel.hpp. 7.74.4.95 int CbcModel::currentDepth () const [inline]

Current depth.

Definition at line 865 of file CbcModel.hpp.

```
7.74.4.96 void CbcModel::setHowOftenGlobalScan (int number)
Set how often to scan global cuts.
7.74.4.97 int CbcModel::howOftenGlobalScan ( ) const [inline]
Get how often to scan global cuts.
Definition at line 872 of file CbcModel.hpp.
7.74.4.98 int* CbcModel::originalColumns ( ) const [inline]
Original columns as created by integerPresolve or preprocessing.
Definition at line 876 of file CbcModel.hpp.
7.74.4.99 void CbcModel::setOriginalColumns ( const int * originalColumns, int numberGood = COIN_INT_MAX )
Set original columns as created by preprocessing.
7.74.4.100 OsiRowCut* CbcModel::conflictCut ( const OsiSolverInterface * solver, bool & localCuts )
Create conflict cut (well - most of)
7.74.4.101 void CbcModel::setPrintFrequency (int number) [inline]
Set the print frequency.
Controls the number of nodes evaluated between status prints. If number <=0 the print frequency is set to 100 nodes
for large problems, 1000 for small problems. Print frequency has very slight overhead if small.
Definition at line 892 of file CbcModel.hpp.
7.74.4.102 int CbcModel::printFrequency() const [inline]
Get the print frequency.
Definition at line 896 of file CbcModel.hpp.
7.74.4.103 bool CbcModel::isAbandoned ( ) const
Are there a numerical difficulties?
7.74.4.104 bool CbcModel::isProvenOptimal ( ) const
Is optimality proven?
7.74.4.105 bool CbcModel::isProvenInfeasible ( ) const
Is infeasiblity proven (or none better than cutoff)?
7.74.4.106 bool CbcModel::isContinuousUnbounded ( ) const
Was continuous solution unbounded.
7.74.4.107 bool CbcModel::isProvenDualInfeasible ( ) const
Was continuous solution unbounded.
```

```
7.74.4.108 bool CbcModel::isNodeLimitReached ( ) const
```

Node limit reached?

7.74.4.109 bool CbcModel::isSecondsLimitReached () const

Time limit reached?

7.74.4.110 bool CbcModel::isSolutionLimitReached () const

Solution limit reached?

```
7.74.4.111 int CbcModel::getIterationCount ( ) const [inline]
```

Get how many iterations it took to solve the problem.

Definition at line 921 of file CbcModel.hpp.

```
7.74.4.112 void CbcModel::incrementIterationCount (int value) [inline]
```

Increment how many iterations it took to solve the problem.

Definition at line 925 of file CbcModel.hpp.

```
7.74.4.113 int CbcModel::getNodeCount() const [inline]
```

Get how many Nodes it took to solve the problem (including those in complete fathoming B&B inside CLP).

Definition at line 929 of file CbcModel.hpp.

```
7.74.4.114 void CbcModel::incrementNodeCount (int value ) [inline]
```

Increment how many nodes it took to solve the problem.

Definition at line 933 of file CbcModel.hpp.

```
7.74.4.115 int CbcModel::getExtraNodeCount() const [inline]
```

Get how many Nodes were enumerated in complete fathoming B&B inside CLP.

Definition at line 937 of file CbcModel.hpp.

```
7.74.4.116 int CbcModel::status ( ) const [inline]
```

Final status of problem Some of these can be found out by is.....

functions -1 before branchAndBound 0 finished - check isProvenOptimal or isProvenInfeasible to see if solution found (or check value of best solution) 1 stopped - on maxnodes, maxsols, maxtime 2 difficulties so run was abandoned (5 event user programmed event occurred)

Definition at line 949 of file CbcModel.hpp.

```
7.74.4.117 void CbcModel::setProblemStatus (int value) [inline]
```

Definition at line 952 of file CbcModel.hpp.

```
7.74.4.118 int CbcModel::secondaryStatus ( ) const [inline]
```

Secondary status of problem -1 unset (status_ will also be -1) 0 search completed with solution 1 linear relaxation not feasible (or worse than cutoff) 2 stopped on gap 3 stopped on nodes 4 stopped on time 5 stopped on user event 6 stopped on solutions 7 linear relaxation unbounded 8 stopped on iteration limit.

```
Definition at line 967 of file CbcModel.hpp.
7.74.4.119 void CbcModel::setSecondaryStatus (int value ) [inline]
Definition at line 970 of file CbcModel.hpp.
7.74.4.120 bool CbcModel::isInitialSolveAbandoned ( ) const
Are there numerical difficulties (for initialSolve)?
7.74.4.121 bool CbcModel::isInitialSolveProvenOptimal ( ) const
Is optimality proven (for initialSolve)?
7.74.4.122 bool CbcModel::isInitialSolveProvenPrimalInfeasible ( ) const
Is primal infeasiblity proven (for initialSolve)?
7.74.4.123 bool CbcModel::isInitialSolveProvenDualInfeasible ( ) const
Is dual infeasiblity proven (for initialSolve)?
7.74.4.124 int CbcModel::numberRowsAtContinuous ( ) const [inline]
Number of rows in continuous (root) problem.
Definition at line 998 of file CbcModel.hpp.
7.74.4.125 int CbcModel::getNumCols ( ) const [inline]
Get number of columns.
Definition at line 1003 of file CbcModel.hpp.
7.74.4.126 int CbcModel::getNumRows ( ) const [inline]
Get number of rows.
Definition at line 1008 of file CbcModel.hpp.
7.74.4.127 CoinBigIndex CbcModel::getNumElements ( ) const [inline]
Get number of nonzero elements.
Definition at line 1013 of file CbcModel.hpp.
7.74.4.128 int CbcModel::numberIntegers ( ) const [inline]
Number of integers in problem.
Definition at line 1018 of file CbcModel.hpp.
7.74.4.129 const int* CbcModel::integerVariable ( ) const [inline]
Definition at line 1022 of file CbcModel.hpp.
7.74.4.130 char CbcModel::integerType (int i) const [inline]
```

Whether or not integer.

Definition at line 1026 of file CbcModel.hpp.

```
7.74.4.131 const char* CbcModel::integerType ( ) const [inline]
```

Whether or not integer.

Definition at line 1032 of file CbcModel.hpp.

```
7.74.4.132 const double* CbcModel::getColLower( ) const [inline]
```

Get pointer to array[getNumCols()] of column lower bounds.

Definition at line 1037 of file CbcModel.hpp.

```
7.74.4.133 const double* CbcModel::getColUpper( ) const [inline]
```

Get pointer to array[getNumCols()] of column upper bounds.

Definition at line 1042 of file CbcModel.hpp.

```
7.74.4.134 const char* CbcModel::getRowSense() const [inline]
```

Get pointer to array[getNumRows()] of row constraint senses.

- 'L': <= constraint
- 'E': = constraint
- 'G': >= constraint
- · 'R': ranged constraint
- · 'N': free constraint

Definition at line 1055 of file CbcModel.hpp.

```
7.74.4.135 const double * CbcModel::getRightHandSide ( ) const [inline]
```

Get pointer to array[getNumRows()] of rows right-hand sides.

- if rowsense()[i] == 'L' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'G' then rhs()[i] == rowlower()[i]
- if rowsense()[i] == 'R' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'N' then rhs()[i] == 0.0

Definition at line 1067 of file CbcModel.hpp.

```
7.74.4.136 const double* CbcModel::getRowRange( ) const [inline]
```

Get pointer to array[getNumRows()] of row ranges.

- if rowsense()[i] == 'R' then rowrange()[i] == rowupper()[i] rowlower()[i]
- if rowsense()[i] != 'R' then rowrange()[i] is 0.0

Definition at line 1079 of file CbcModel.hpp.

```
7.74.4.137 const double* CbcModel::getRowLower( ) const [inline]
Get pointer to array[getNumRows()] of row lower bounds.
Definition at line 1084 of file CbcModel.hpp.
7.74.4.138 const double* CbcModel::getRowUpper( ) const [inline]
Get pointer to array[getNumRows()] of row upper bounds.
Definition at line 1089 of file CbcModel.hpp.
7.74.4.139 const double* CbcModel::getObjCoefficients ( ) const [inline]
Get pointer to array[getNumCols()] of objective function coefficients.
Definition at line 1094 of file CbcModel.hpp.
7.74.4.140 double CbcModel::getObjSense() const [inline]
Get objective function sense (1 for min (default), -1 for max)
Definition at line 1099 of file CbcModel.hpp.
7.74.4.141 bool CbcModel::isContinuous (int collndex) const [inline]
Return true if variable is continuous.
Definition at line 1105 of file CbcModel.hpp.
7.74.4.142 bool CbcModel::isBinary (int collndex) const [inline]
Return true if variable is binary.
Definition at line 1110 of file CbcModel.hpp.
7.74.4.143 bool CbcModel::isInteger ( int collndex ) const [inline]
Return true if column is integer.
Note: This function returns true if the the column is binary or a general integer.
Definition at line 1118 of file CbcModel.hpp.
7.74.4.144 bool CbcModel::isIntegerNonBinary (int collndex) const [inline]
Return true if variable is general integer.
Definition at line 1123 of file CbcModel.hpp.
7.74.4.145 bool CbcModel::isFreeBinary (int collndex) const [inline]
Return true if variable is binary and not fixed at either bound.
Definition at line 1128 of file CbcModel.hpp.
7.74.4.146 const CoinPackedMatrix* CbcModel::getMatrixByRow() const [inline]
Get pointer to row-wise copy of matrix.
Definition at line 1133 of file CbcModel.hpp.
```

```
7.74.4.147 const CoinPackedMatrix* CbcModel::getMatrixByCol( ) const [inline]
Get pointer to column-wise copy of matrix.
Definition at line 1138 of file CbcModel.hpp.
7.74.4.148 double CbcModel::getInfinity ( ) const [inline]
Get solver's value for infinity.
Definition at line 1143 of file CbcModel.hpp.
7.74.4.149 const double* CbcModel::getCbcColLower( ) const [inline]
Get pointer to array[getNumCols()] (for speed) of column lower bounds.
Definition at line 1147 of file CbcModel.hpp.
7.74.4.150 const double* CbcModel::getCbcColUpper( ) const [inline]
Get pointer to array[getNumCols()] (for speed) of column upper bounds.
Definition at line 1151 of file CbcModel.hpp.
7.74.4.151 const double * CbcModel::getCbcRowLower( ) const [inline]
Get pointer to array[getNumRows()] (for speed) of row lower bounds.
Definition at line 1155 of file CbcModel.hpp.
7.74.4.152 const double* CbcModel::getCbcRowUpper( ) const [inline]
Get pointer to array[getNumRows()] (for speed) of row upper bounds.
Definition at line 1159 of file CbcModel.hpp.
7.74.4.153 const double* CbcModel::getCbcColSolution() const [inline]
Get pointer to array[getNumCols()] (for speed) of primal solution vector.
Definition at line 1163 of file CbcModel.hpp.
7.74.4.154 const double* CbcModel::getCbcRowPrice() const [inline]
Get pointer to array[getNumRows()] (for speed) of dual prices.
Definition at line 1167 of file CbcModel.hpp.
7.74.4.155 const double* CbcModel::getCbcReducedCost( ) const [inline]
Get a pointer to array[getNumCols()] (for speed) of reduced costs.
Definition at line 1171 of file CbcModel.hpp.
7.74.4.156 const double* CbcModel::getCbcRowActivity( ) const [inline]
Get pointer to array[getNumRows()] (for speed) of row activity levels.
Definition at line 1175 of file CbcModel.hpp.
```

7.74.4.157 double* CbcModel::continuousSolution () const [inline]

Holds solution at continuous (after cuts if branchAndBound called)

Definition at line 1184 of file CbcModel.hpp.

7.74.4.158 int* CbcModel::usedInSolution () const [inline]

Array marked whenever a solution is found if non-zero.

Code marks if heuristic returns better so heuristic need only mark if it wants to on solutions which are worse than current Definition at line 1191 of file CbcModel.hpp.

7.74.4.159 void CbcModel::incrementUsed (const double * solution)

Increases usedInSolution for nonzeros.

7.74.4.160 void CbcModel::setBestSolution (CBC_Message how, double & objectiveValue, const double * solution, int fixVariables = 0)

Record a new incumbent solution and update objective Value.

7.74.4.161 void CbcModel::setBestObjectiveValue (double objectiveValue)

Just update objective Value.

7.74.4.162 CbcEventHandler::CbcAction CbcModel::dealWithEventHandler (CbcEventHandler::CbcEvent event, double objValue, const double * solution)

Deals with event handler and solution.

7.74.4.163 virtual double CbcModel::checkSolution (double cutoff, double * solution, int fixVariables, double originalObjValue) [virtual]

Call this to really test if a valid solution can be feasible Solution is number columns in size.

If fixVariables true then bounds of continuous solver updated. Returns objective value (worse than cutoff if not feasible) Previously computed objective value is now passed in (in case user does not do solve) virtual so user can override

7.74.4.164 bool CbcModel::feasibleSolution (int & numberIntegerInfeasibilities, int & numberObjectInfeasibilities) const

Test the current solution for feasiblility.

Scan all objects for indications of infeasibility. This is broken down into simple integer infeasibility (numberInteger-Infeasibilities) and all other reports of infeasibility (numberObjectInfeasibilities).

7.74.4.165 double* CbcModel::currentSolution () const [inline]

Solution to the most recent lp relaxation.

The solver's solution to the most recent lp relaxation.

Definition at line 1230 of file CbcModel.hpp.

7.74.4.166 const double* CbcModel::testSolution() const [inline]

For testing infeasibilities - will point to currentSolution_ or solver->getColSolution()

Definition at line 1236 of file CbcModel.hpp.

```
7.74.4.167 void CbcModel::setTestSolution ( const double * solution ) [inline]
Definition at line 1239 of file CbcModel.hpp.
7.74.4.168 void CbcModel::reserveCurrentSolution ( const double * solution = NULL )
Make sure region there and optionally copy solution.
7.74.4.169 const double* CbcModel::getColSolution() const [inline]
Get pointer to array[getNumCols()] of primal solution vector.
Definition at line 1246 of file CbcModel.hpp.
7.74.4.170 const double * CbcModel::getRowPrice ( ) const [inline]
Get pointer to array[getNumRows()] of dual prices.
Definition at line 1251 of file CbcModel.hpp.
7.74.4.171 const double* CbcModel::getReducedCost() const [inline]
Get a pointer to array[getNumCols()] of reduced costs.
Definition at line 1256 of file CbcModel.hpp.
7.74.4.172 const double * CbcModel::getRowActivity( ) const [inline]
Get pointer to array[getNumRows()] of row activity levels.
Definition at line 1261 of file CbcModel.hpp.
7.74.4.173 double CbcModel::getCurrentObjValue ( ) const [inline]
Get current objective function value.
Definition at line 1266 of file CbcModel.hpp.
7.74.4.174 double CbcModel::getCurrentMinimizationObjValue( )const [inline]
Get current minimization objective function value.
Definition at line 1270 of file CbcModel.hpp.
7.74.4.175 double CbcModel::getMinimizationObjValue() const [inline]
Get best objective function value as minimization.
Definition at line 1275 of file CbcModel.hpp.
7.74.4.176 void CbcModel::setMinimizationObjValue ( double value ) [inline]
Set best objective function value as minimization.
Definition at line 1279 of file CbcModel.hpp.
7.74.4.177 double CbcModel::getObjValue( ) const [inline]
Get best objective function value.
Definition at line 1284 of file CbcModel.hpp.
```

7.74.4.178 double CbcModel::getBestPossibleObjValue () const

Get best possible objective function value.

This is better of best possible left on tree and best solution found. If called from within branch and cut may be optimistic.

7.74.4.179 void CbcModel::setObjValue (double value) [inline]

Set best objective function value.

Definition at line 1294 of file CbcModel.hpp.

7.74.4.180 double CbcModel::getSolverObjValue() const [inline]

Get solver objective function value (as minimization)

Definition at line 1298 of file CbcModel.hpp.

7.74.4.181 double* CbcModel::bestSolution() const [inline]

The best solution to the integer programming problem.

The best solution to the integer programming problem found during the search. If no solution is found, the method returns null.

Definition at line 1308 of file CbcModel.hpp.

7.74.4.182 void CbcModel::setBestSolution (const double * solution, int numberColumns, double objectiveValue, bool check = false)

User callable setBestSolution.

If check false does not check valid If true then sees if feasible and warns if objective value worse than given (so just set to COIN_DBL_MAX if you don't care). If check true then does not save solution if not feasible

7.74.4.183 int CbcModel::getSolutionCount() const [inline]

Get number of solutions.

Definition at line 1321 of file CbcModel.hpp.

7.74.4.184 void CbcModel::setSolutionCount(int value) [inline]

Set number of solutions (so heuristics will be different)

Definition at line 1326 of file CbcModel.hpp.

7.74.4.185 int CbcModel::numberSavedSolutions () const

Number of saved solutions (including best)

7.74.4.186 int CbcModel::maximumSavedSolutions () const [inline]

Maximum number of extra saved solutions.

Definition at line 1332 of file CbcModel.hpp.

7.74.4.187 void CbcModel::setMaximumSavedSolutions (int value)

Set maximum number of extra saved solutions.

```
7.74.4.188 const double* CbcModel::savedSolution ( int which ) const
Return a saved solution (0==best) - NULL if off end.
7.74.4.189 double CbcModel::savedSolutionObjective (int which) const
Return a saved solution objective (0==best) - COIN DBL MAX if off end.
7.74.4.190 void CbcModel::deleteSavedSolution (int which)
Delete a saved solution and move others up.
7.74.4.191 int CbcModel::phase() const [inline]
Current phase (so heuristics etc etc can find out).
0 - initial solve 1 - solve with cuts at root 2 - solve with cuts 3 - other e.g. strong branching 4 - trying to validate a solution
5 - at end of search
Definition at line 1352 of file CbcModel.hpp.
7.74.4.192 int CbcModel::getNumberHeuristicSolutions ( ) const [inline]
Get number of heuristic solutions.
Definition at line 1357 of file CbcModel.hpp.
7.74.4.193 void CbcModel::setNumberHeuristicSolutions (int value) [inline]
Set number of heuristic solutions.
Definition at line 1361 of file CbcModel.hpp.
7.74.4.194 void CbcModel::setObjSense ( double s ) [inline]
Set objective function sense (1 for min (default), -1 for max,)
Definition at line 1366 of file CbcModel.hpp.
7.74.4.195 double CbcModel::getContinuousObjective( )const [inline]
Value of objective at continuous.
Definition at line 1372 of file CbcModel.hpp.
7.74.4.196 void CbcModel::setContinuousObjective ( double value ) [inline]
Definition at line 1375 of file CbcModel.hpp.
7.74.4.197 int CbcModel::getContinuousInfeasibilities ( ) const [inline]
Number of infeasibilities at continuous.
Definition at line 1379 of file CbcModel.hpp.
7.74.4.198 void CbcModel::setContinuousInfeasibilities (int value) [inline]
```

Definition at line 1382 of file CbcModel.hpp.

```
7.74.4.199 double CbcModel::rootObjectiveAfterCuts ( ) const [inline]
Value of objective after root node cuts added.
Definition at line 1386 of file CbcModel.hpp.
7.74.4.200 double CbcModel::sumChangeObjective ( ) const [inline]
Sum of Changes to objective by first solve.
Definition at line 1390 of file CbcModel.hpp.
7.74.4.201 int CbcModel::numberGlobalViolations ( ) const [inline]
Number of times global cuts violated.
When global cut pool then this should be kept for each cut and type of cut
Definition at line 1395 of file CbcModel.hpp.
7.74.4.202 void CbcModel::clearNumberGlobalViolations ( ) [inline]
Definition at line 1398 of file CbcModel.hpp.
7.74.4.203 bool CbcModel::resolveAfterTakeOffCuts ( ) const [inline]
Whether to force a resolve after takeOffCuts.
Definition at line 1402 of file CbcModel.hpp.
7.74.4.204 void CbcModel::setResolveAfterTakeOffCuts (bool yesNo) [inline]
Definition at line 1405 of file CbcModel.hpp.
7.74.4.205 int CbcModel::maximumRows ( ) const [inline]
Maximum number of rows.
Definition at line 1409 of file CbcModel.hpp.
7.74.4.206 CoinWarmStartBasis& CbcModel::workingBasis() [inline]
Work basis for temporary use.
Definition at line 1413 of file CbcModel.hpp.
7.74.4.207 int CbcModel::getStopNumberIterations ( ) const [inline]
Get number of "iterations" to stop after.
Definition at line 1417 of file CbcModel.hpp.
7.74.4.208 void CbcModel::setStopNumberIterations (int value) [inline]
Set number of "iterations" to stop after.
Definition at line 1421 of file CbcModel.hpp.
7.74.4.209 CbcModel* CbcModel::heuristicModel() const [inline]
A pointer to model from CbcHeuristic.
```

```
Definition at line 1425 of file CbcModel.hpp.
7.74.4.210 void CbcModel::setHeuristicModel ( CbcModel * model ) [inline]
Set a pointer to model from CbcHeuristic.
Definition at line 1428 of file CbcModel.hpp.
7.74.4.211 CbcCompareBase* CbcModel::nodeComparison() const [inline]
Definition at line 1435 of file CbcModel.hpp.
7.74.4.212 void CbcModel::setNodeComparison ( CbcCompareBase * compare )
7.74.4.213 void CbcModel::setNodeComparison ( CbcCompareBase & compare )
7.74.4.214 CbcFeasibilityBase* CbcModel::problemFeasibility( ) const [inline]
Definition at line 1445 of file CbcModel.hpp.
7.74.4.215 void CbcModel::setProblemFeasibility ( CbcFeasibilityBase * feasibility )
7.74.4.216 void CbcModel::setProblemFeasibility ( CbcFeasibilityBase & feasibility )
7.74.4.217 CbcTree* CbcModel::tree( ) const [inline]
Tree method e.g. heap (which may be overridden by inheritance)
Definition at line 1455 of file CbcModel.hpp.
7.74.4.218 void CbcModel::passInTreeHandler ( CbcTree & tree )
For modifying tree handling (original is cloned)
7.74.4.219 void CbcModel::passInSubTreeModel ( CbcModel & model )
For passing in an CbcModel to do a sub Tree (with derived tree handlers).
Passed in model must exist for duration of branch and bound
7.74.4.220 CbcModel* CbcModel::subTreeModel ( OsiSolverInterface * solver = NULL ) const
For retrieving a copy of subtree model with given OsiSolver.
If no subtree model will use self (up to user to reset cutoff etc). If solver NULL uses current
7.74.4.221 int CbcModel::numberStoppedSubTrees ( ) const [inline]
Returns number of times any subtree stopped on nodes, time etc.
Definition at line 1470 of file CbcModel.hpp.
7.74.4.222 void CbcModel::incrementSubTreeStopped() [inline]
Says a sub tree was stopped.
Definition at line 1474 of file CbcModel.hpp.
```

7.74.4.223 int CbcModel::typePresolve() const [inline]

Whether to automatically do presolve before branch and bound (subTrees).

0 - no 1 - ordinary presolve 2 - integer presolve (dodgy)

Definition at line 1482 of file CbcModel.hpp.

7.74.4.224 void CbcModel::setTypePresolve (int value) [inline]

Definition at line 1485 of file CbcModel.hpp.

7.74.4.225 CbcBranchDecision * CbcModel::branchingMethod() const [inline]

Get the current branching decision method.

Definition at line 1498 of file CbcModel.hpp.

7.74.4.226 void CbcModel::setBranchingMethod (CbcBranchDecision * method) [inline]

Set the branching decision method.

Definition at line 1502 of file CbcModel.hpp.

7.74.4.227 void CbcModel::setBranchingMethod (CbcBranchDecision & method) [inline]

Set the branching method.

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Definition at line 1510 of file CbcModel.hpp.

7.74.4.228 CbcCutModifier* CbcModel::cutModifier()const [inline]

Get the current cut modifier method.

Definition at line 1515 of file CbcModel.hpp.

7.74.4.229 void CbcModel::setCutModifier (CbcCutModifier * modifier)

Set the cut modifier method.

7.74.4.230 void CbcModel::setCutModifier (CbcCutModifier & modifier)

Set the cut modifier method.

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

7.74.4.231 int CbcModel::stateOfSearch () const [inline]

State of search 0 - no solution 1 - only heuristic solutions 2 - branched to a solution 3 - no solution but many nodes.

Definition at line 1536 of file CbcModel.hpp.

7.74.4.232 void CbcModel::setStateOfSearch (int state) [inline]

Definition at line 1539 of file CbcModel.hpp.

```
7.74.4.233 int CbcModel::searchStrategy ( ) const [inline]
Strategy worked out - mainly at root node for use by CbcNode.
Definition at line 1543 of file CbcModel.hpp.
7.74.4.234 void CbcModel::setSearchStrategy (int value ) [inline]
Set strategy worked out - mainly at root node for use by CbcNode.
Definition at line 1547 of file CbcModel.hpp.
7.74.4.235 int CbcModel::strongStrategy() const [inline]
Stong branching strategy.
Definition at line 1551 of file CbcModel.hpp.
7.74.4.236 void CbcModel::setStrongStrategy (int value ) [inline]
Set strong branching strategy.
Definition at line 1555 of file CbcModel.hpp.
7.74.4.237 int CbcModel::numberCutGenerators ( ) const [inline]
Get the number of cut generators.
Definition at line 1560 of file CbcModel.hpp.
7.74.4.238 CbcCutGenerator** CbcModel::cutGenerators() const [inline]
Get the list of cut generators.
Definition at line 1564 of file CbcModel.hpp.
7.74.4.239 CbcCutGenerator* CbcModel::cutGenerator(inti)const [inline]
Get the specified cut generator.
Definition at line 1568 of file CbcModel.hpp.
```

7.74.4.240 CbcCutGenerator * CbcModel::virginCutGenerator (int i) const [inline]

Get the specified cut generator before any changes.

Definition at line 1572 of file CbcModel.hpp.

7.74.4.241 void CbcModel::addCutGenerator (CglCutGenerator * generator, int howOften = 1, const char * name = NULL, bool normal = true, bool atSolution = false, bool infeasible = false, int howOftenInSub = -100, int whatDepth = -1, int whatDepthInSub = -1)

Add one generator - up to user to delete generators.

howoften affects how generator is used. 0 or 1 means always, >1 means every that number of nodes. Negative values have same meaning as positive but they may be switched off (->-100) by code if not many cuts generated at continuous. -99 is just done at root. Name is just for printout. If depth >0 overrides how often generator is called (if howOften==-1 or >0).

```
7.74.4.242 CbcStrategy* CbcModel::strategy( ) const [inline]
Get the current strategy.
Definition at line 1596 of file CbcModel.hpp.
7.74.4.243 void CbcModel::setStrategy ( CbcStrategy & strategy )
Set the strategy. Clones.
7.74.4.244 void CbcModel::setStrategy ( CbcStrategy * strategy ) [inline]
Set the strategy. assigns.
Definition at line 1602 of file CbcModel.hpp.
7.74.4.245 CbcModel* CbcModel::parentModel( ) const [inline]
Get the current parent model.
Definition at line 1606 of file CbcModel.hpp.
7.74.4.246 void CbcModel::setParentModel ( CbcModel & parentModel ) [inline]
Set the parent model.
Definition at line 1610 of file CbcModel.hpp.
7.74.4.247 void CbcModel::addHeuristic ( CbcHeuristic * generator, const char * name = NULL, int before = -1 )
Add one heuristic - up to user to delete.
The name is just used for print messages.
7.74.4.248 CbcHeuristic* CbcModel::heuristic(inti)const [inline]
Get the specified heuristic.
Definition at line 1625 of file CbcModel.hpp.
7.74.4.249 int CbcModel::numberHeuristics ( ) const [inline]
Get the number of heuristics.
Definition at line 1629 of file CbcModel.hpp.
7.74.4.250 void CbcModel::setNumberHeuristics (int value) [inline]
Set the number of heuristics.
Definition at line 1633 of file CbcModel.hpp.
7.74.4.251 CbcHeuristic* CbcModel::lastHeuristic() const [inline]
Pointer to heuristic solver which found last solution (or NULL)
Definition at line 1637 of file CbcModel.hpp.
7.74.4.252 void CbcModel::setLastHeuristic ( CbcHeuristic * last ) [inline]
set last heuristic which found a solution
```

Definition at line 1641 of file CbcModel.hpp.

7.74.4.253 void CbcModel::passInPriorities (const int * priorities, bool ifNotSimpleIntegers)

Pass in branching priorities.

If ifClique then priorities are on cliques otherwise priorities are on integer variables. Other type (if exists set to default) 1 is highest priority. (well actually -INT_MAX is but that's ugly) If hotstart > 0 then branches are created to force the variable to the value given by best solution. This enables a sort of hot start. The node choice should be greatest depth and hotstart should normally be switched off after a solution.

If ifNotSimpleIntegers true then appended to normal integers

This is now deprecated except for simple usage. If user creates Cbcobjects then set priority in them

```
7.74.4.254 int CbcModel::priority (int sequence) const [inline]
```

Returns priority level for an object (or 1000 if no priorities exist)

Definition at line 1666 of file CbcModel.hpp.

7.74.4.255 void CbcModel::passInEventHandler (const CbcEventHandler * eventHandler)

Set an event handler.

A clone of the handler passed as a parameter is stored in CbcModel.

```
7.74.4.256 CbcEventHandler* CbcModel::getEventHandler( )const [inline]
```

Retrieve a pointer to the event handler.

Definition at line 1677 of file CbcModel.hpp.

```
7.74.4.257 void CbcModel::setApplicationData (void * appData)
```

Set application data.

This is a pointer that the application can store into and retrieve from the solver interface. This field is available for the application to optionally define and use.

```
7.74.4.258 void* CbcModel::getApplicationData ( ) const
```

Get application data.

7.74.4.259 void CbcModel::passInSolverCharacteristics (OsiBabSolver * solverCharacteristics)

For advanced applications you may wish to modify the behavior of Cbc e.g.

if the solver is a NLP solver then you may not have an exact optimum solution at each step. Information could be built into OsiSolverInterface but this is an alternative so that that interface does not have to be changed. If something similar is useful to enough solvers then it could be migrated You can also pass in by using solver->setAuxiliaryInfo. You should do that if solver is odd - if solver is normal simplex then use this. NOTE - characteristics are not cloned

```
7.74.4.260 const OsiBabSolver* CbcModel::solverCharacteristics ( ) const [inline]
```

Get solver characteristics.

Definition at line 1710 of file CbcModel.hpp.

```
7.74.4.261 void CbcModel::passInMessageHandler ( CoinMessageHandler * handler )
Pass in Message handler (not deleted at end)
7.74.4.262 void CbcModel::newLanguage ( CoinMessages::Language language )
Set language.
7.74.4.263 void CbcModel::setLanguage ( CoinMessages::Language language ) [inline]
Definition at line 1723 of file CbcModel.hpp.
7.74.4.264 CoinMessageHandler* CbcModel::messageHandler( )const [inline]
Return handler.
Definition at line 1727 of file CbcModel.hpp.
7.74.4.265 CoinMessages & CbcModel::messages ( ) [inline]
Return messages.
Definition at line 1731 of file CbcModel.hpp.
7.74.4.266 CoinMessages* CbcModel::messagesPointer( ) [inline]
Return pointer to messages.
Definition at line 1735 of file CbcModel.hpp.
7.74.4.267 void CbcModel::setLogLevel (int value)
Set log level.
7.74.4.268 int CbcModel::logLevel( ) const [inline]
Get log level.
Definition at line 1741 of file CbcModel.hpp.
7.74.4.269 void CbcModel::setDefaultHandler (bool yesNo) [inline]
Set flag to say if handler is the default handler.
The default handler is deleted when the model is deleted. Other handlers (supplied by the client) will not be deleted.
Definition at line 1749 of file CbcModel.hpp.
7.74.4.270 bool CbcModel::defaultHandler ( ) const [inline]
Check default handler.
Definition at line 1753 of file CbcModel.hpp.
7.74.4.271 void CbcModel::setSpecialOptions (int value ) [inline]
```

Set special options 0 bit (1) - check if cuts valid (if on debugger list) 1 bit (2) - use current basis to check integer solution (rather than all slack) 2 bit (4) - don't check integer solution (by solving LP) 3 bit (8) - fast analyze 4 bit (16) - non-linear model - so no well defined CoinPackedMatrix 5 bit (32) - keep names 6 bit (64) - try for dominated columns 7 bit (128) - SOS type 1 but all declared integer 8 bit (256) - Set to say solution just found, unset by doing cuts 9 bit (512) - Try reduced model after 100 nodes 10 bit (1024) - Switch on some heuristics even if seems unlikely 11 bit (2048) - Mark as

in small branch and bound 12 bit (4096) - Funny cuts so do slow way (in some places) 13 bit (8192) - Funny cuts so do slow way (in other places) 14 bit (16384) - Use Cplex! for fathoming 15 bit (32768) - Try reduced model after 0 nodes 16 bit (65536) - Original model had integer bounds 17 bit (131072) - Perturbation switched off 18 bit (262144) - donor CbcModel 19 bit (524288) - recipient CbcModel 20 bit (1048576) - waiting for sub model to return 22 bit (4194304) - do not initialize random seed in solver (user has) 23 bit (8388608) - leave solver_ with cuts 24 bit (16777216) - just get feasible if no cutoff.

Definition at line 1788 of file CbcModel.hpp.

7.74.4.272 int CbcModel::specialOptions () const [inline]

Get special options.

Definition at line 1792 of file CbcModel.hpp.

7.74.4.273 void CbcModel::setRandomSeed (int value) [inline]

Set random seed.

Definition at line 1796 of file CbcModel.hpp.

7.74.4.274 int CbcModel::getRandomSeed () const [inline]

Get random seed.

Definition at line 1800 of file CbcModel.hpp.

7.74.4.275 void CbcModel::setMultipleRootTries (int value) [inline]

Set multiple root tries.

Definition at line 1804 of file CbcModel.hpp.

7.74.4.276 int CbcModel::getMultipleRootTries () const [inline]

Get multiple root tries.

Definition at line 1808 of file CbcModel.hpp.

7.74.4.277 void CbcModel::sayEventHappened() [inline]

Tell model to stop on event.

Definition at line 1812 of file CbcModel.hpp.

7.74.4.278 bool CbcModel::normalSolver() const [inline]

Says if normal solver i.e. has well defined CoinPackedMatrix.

Definition at line 1815 of file CbcModel.hpp.

7.74.4.279 bool CbcModel::waitingForMiniBranchAndBound () const [inline]

Says if model is sitting there waiting for mini branch and bound to finish This is because an event handler may only have access to parent model in mini branch and bound.

Definition at line 1822 of file CbcModel.hpp.

```
7.74.4.280 void CbcModel::setMoreSpecialOptions (int value ) [inline]
```

Set more special options at present bottom 6 bits used for shadow price mode 1024 for experimental hotstart 2048,4096 breaking out of cuts 8192 slowly increase minimum drop 16384 gomory 32768 more heuristics in sub trees 65536 no cuts in preprocessing 131072 Time limits elapsed 18 bit (262144) - Perturb fathom nodes 19 bit (524288) - No limit on fathom nodes 20 bit (1048576) - Reduce sum of infeasibilities before cuts 21 bit (2097152) - Reduce sum of infeasibilities after cuts 22 bit (4194304) - Conflict analysis 23 bit (8388608) - Conflict analysis - temporary bit 24 bit (16777216) - Add cutoff as LP constraint (out) 25 bit (33554432) - diving/reordering 26 bit (67108864) - load global cuts from file 27 bit (134217728) - append binding global cuts to file 28 bit (268435456) - idiot branching 29 bit (536870912) - don't make fake objective.

Definition at line 1847 of file CbcModel.hpp.

```
7.74.4.281 int CbcModel::moreSpecialOptions ( ) const [inline]
```

Get more special options.

Definition at line 1851 of file CbcModel.hpp.

```
7.74.4.282 void CbcModel::setMoreSpecialOptions2 (int value ) [inline]
```

Set more more special options 0 bit (1) - find switching variables 1 bit (2) - using fake objective until solution 2 bit (4) - switching variables exist 3 bit (8) - skip most of setBestSolution checks 4 bit (16) - very lightweight preprocessing in smallB&B 5 bit (32) - event handler needs to be cloned when parallel.

Definition at line 1862 of file CbcModel.hpp.

```
7.74.4.283 int CbcModel::moreSpecialOptions2 ( ) const [inline]
```

Get more special options2.

Definition at line 1866 of file CbcModel.hpp.

```
7.74.4.284 void CbcModel::setCutoffAsConstraint (bool yesNo) [inline]
```

Set cutoff as constraint.

Definition at line 1870 of file CbcModel.hpp.

```
7.74.4.285 void CbcModel::setUseElapsedTime ( bool yesNo ) [inline]
```

Set time method.

Definition at line 1874 of file CbcModel.hpp.

```
7.74.4.286 bool CbcModel::useElapsedTime ( ) const [inline]
```

Get time method.

Definition at line 1881 of file CbcModel.hpp.

```
7.74.4.287 void* CbcModel::temporaryPointer( ) const [inline]
```

Get useful temporary pointer.

Definition at line 1885 of file CbcModel.hpp.

```
7.74.4.288 void CbcModel::setTemporaryPointer (void * pointer) [inline]
```

Set useful temporary pointer.

Definition at line 1888 of file CbcModel.hpp.

7.74.4.289 void CbcModel::goToDantzig (int numberNodes, ClpDualRowPivot *& savePivotMethod)

Go to dantzig pivot selection if easy problem (clp only)

7.74.4.290 bool CbcModel::ownObjects () const [inline]

Now we may not own objects - just point to solver's objects.

Definition at line 1893 of file CbcModel.hpp.

7.74.4.291 void CbcModel::checkModel ()

Check original model before it gets messed up.

7.74.4.292 void CbcModel::assignSolver (OsiSolverInterface *& solver, bool deleteSolver = true)

Assign a solver to the model (model assumes ownership)

On return, solver will be NULL. If deleteSolver then current solver deleted (if model owned)

Note

Parameter settings in the outgoing solver are not inherited by the incoming solver.

7.74.4.293 void CbcModel::setModelOwnsSolver (bool ourSolver) [inline]

Set ownership of solver.

A parameter of false tells CbcModel it does not own the solver and should not delete it. Once you claim ownership of the solver, you're responsible for eventually deleting it. Note that CbcModel clones solvers with abandon. Unless you have a deep understanding of the workings of CbcModel, the only time you want to claim ownership is when you're about to delete the CbcModel object but want the solver to continue to exist (as, for example, when branchAndBound has finished and you want to hang on to the answer).

Definition at line 1930 of file CbcModel.hpp.

7.74.4.294 bool CbcModel::modelOwnsSolver() [inline]

Get ownership of solver.

A return value of true means that CbcModel owns the solver and will take responsibility for deleting it when that becomes necessary.

Definition at line 1939 of file CbcModel.hpp.

7.74.4.295 virtual CbcModel* CbcModel::clone (bool cloneHandler) [virtual]

Clone.

7.74.4.296 CbcModel& CbcModel::operator= (const CbcModel & rhs)

Assignment operator.

7.74.4.297 OsiSolverInterface * CbcModel::solver() const [inline]

Returns solver - has current state.

Definition at line 1958 of file CbcModel.hpp.

```
7.74.4.298 OsiSolverInterface * CbcModel::swapSolver ( OsiSolverInterface * solver ) [inline]
Returns current solver - sets new one.
Definition at line 1963 of file CbcModel.hpp.
7.74.4.299 OsiSolverInterface* CbcModel::continuousSolver( ) const [inline]
Returns solver with continuous state.
Definition at line 1970 of file CbcModel.hpp.
7.74.4.300 void CbcModel::createContinuousSolver( ) [inline]
Create solver with continuous state.
Definition at line 1975 of file CbcModel.hpp.
7.74.4.301 void CbcModel::clearContinuousSolver() [inline]
Clear solver with continuous state.
Definition at line 1979 of file CbcModel.hpp.
7.74.4.302 OsiSolverInterface* CbcModel::referenceSolver( ) const [inline]
A copy of the solver, taken at constructor or by saveReferenceSolver.
Definition at line 1985 of file CbcModel.hpp.
7.74.4.303 void CbcModel::saveReferenceSolver ( )
Save a copy of the current solver so can be reset to.
7.74.4.304 void CbcModel::resetToReferenceSolver ( )
Uses a copy of reference solver to be current solver.
Because of possible mismatches all exotic integer information is loat (apart from normal information in OsiSolver-
Interface) so SOS etc and priorities will have to be redone
7.74.4.305 void CbcModel::gutsOfDestructor()
Clears out as much as possible (except solver)
7.74.4.306 void CbcModel::gutsOfDestructor2 ( )
Clears out enough to reset CbcModel as if no branch and bound done.
7.74.4.307 void CbcModel::resetModel()
Clears out enough to reset CbcModel cutoff etc.
7.74.4.308 void CbcModel::gutsOfCopy ( const CbcModel & rhs, int mode = 0 )
Most of copy constructor mode - 0 copy but don't delete before 1 copy and delete before 2 copy and delete before (but
use virgin generators)
```

7.74.4.309 void CbcModel::moveInfo (const CbcModel & rhs)

Move status, nodes etc etc across.

7.74.4.310 static bool CbcModel::haveMultiThreadSupport() [static]

Indicates whether Cbc library has been compiled with multithreading support.

7.74.4.311 CbcThread* CbcModel::masterThread() const [inline]

Get pointer to masterthread.

Definition at line 2022 of file CbcModel.hpp.

7.74.4.312 CbcNodeInfo** CbcModel::walkback() const [inline]

Get pointer to walkback.

Definition at line 2026 of file CbcModel.hpp.

7.74.4.313 int CbcModel::getNumberThreads () const [inline]

Get number of threads.

Definition at line 2030 of file CbcModel.hpp.

7.74.4.314 void CbcModel::setNumberThreads (int value) [inline]

Set number of threads.

Definition at line 2034 of file CbcModel.hpp.

7.74.4.315 int CbcModel::getThreadMode() const [inline]

Get thread mode.

Definition at line 2038 of file CbcModel.hpp.

7.74.4.316 void CbcModel::setThreadMode (int value) [inline]

Set thread mode always use numberThreads for branching 1 set then deterministic 2 set then use numberThreads for root cuts 4 set then use numberThreads in root mini branch and bound 8 set and numberThreads - do heuristics numberThreads at a time 8 set and numberThreads==0 do all heuristics at once default is 0.

Definition at line 2050 of file CbcModel.hpp.

7.74.4.317 int CbcModel::parallelMode () const [inline]

Return -2 if deterministic threaded and main thread -1 if deterministic threaded and serial thread 0 if serial 1 if opportunistic threaded.

Definition at line 2059 of file CbcModel.hpp.

7.74.4.318 bool CbcModel::isLocked () const

From here to end of section - code in CbcThread.cpp until class changed Returns true if locked.

7.74.4.319 void CbcModel::lockThread() [inline]

Definition at line 2087 of file CbcModel.hpp.

```
7.74.4.320 void CbcModel::unlockThread() [inline]
Definition at line 2088 of file CbcModel.hpp.
7.74.4.321 void CbcModel::setInfoInChild ( int type, CbcThread * info )
Set information in a child -3 pass pointer to child thread info -2 just stop -1 delete simple child stuff 0 delete opportunistic
child stuff 1 delete deterministic child stuff.
7.74.4.322 void CbcModel::moveToModel ( CbcModel * baseModel, int mode )
Move/copy information from one model to another -1 - initialization 0 - from base model 1 - to base model (and reset) 2
- add in final statistics etc (and reset so can do clean destruction)
7.74.4.323 int CbcModel::splitModel (int numberModels, CbcModel ** model, int numberNodes)
Split up nodes.
7.74.4.324 void CbcModel::startSplitModel (int numberIterations)
Start threads.
7.74.4.325 void CbcModel::mergeModels ( int numberModel, CbcModel ** model, int numberNodes )
Merge models.
7.74.4.326 int CbcModel::getNodeCount2() const [inline]
Get how many Nodes it took to solve the problem.
Definition at line 2118 of file CbcModel.hpp.
7.74.4.327 void CbcModel::setPointers ( const OsiSolverInterface * solver )
Set pointers for speed.
7.74.4.328 int CbcModel::reducedCostFix ( )
Perform reduced cost fixing.
Fixes integer variables at their current value based on reduced cost penalties. Returns number fixed
7.74.4.329 void CbcModel::synchronizeHandlers (int makeDefault)
Makes all handlers same.
If makeDefault 1 then makes top level default and rest point to that. If 2 then each is copy
7.74.4.330 void CbcModel::saveExtraSolution ( const double * solution, double objectiveValue )
Save a solution to saved list.
7.74.4.331 void CbcModel::saveBestSolution ( const double * solution, double objectiveValue )
Save a solution to best and move current to saved.
7.74.4.332 void CbcModel::deleteSolutions ( )
Delete best and saved solutions.
```

7.74.4.333 int CbcModel::resolve (OsiSolverInterface * solver)

Encapsulates solver resolve.

7.74.4.334 int CbcModel::chooseBranch (CbcNode *& newNode, int numberPassesLeft, CbcNode * oldNode, OsiCuts & cuts, bool & resolved, CoinWarmStartBasis * lastws, const double * lowerBefore, const double * upperBefore, OsiSolverBranch *& branches)

Encapsulates choosing a variable - anyAction -2, infeasible (-1 round again), 0 done.

7.74.4.335 int CbcModel::chooseBranch (CbcNode * newNode, int numberPassesLeft, bool & resolved)

7.74.4.336 CoinWarmStartBasis * CbcModel::getEmptyBasis (int ns = 0, int na = 0) const

Return an empty basis object of the specified size.

A useful utility when constructing a basis for a subproblem from scratch. The object returned will be of the requested capacity and appropriate for the solver attached to the model.

7.74.4.337 int CbcModel::takeOffCuts (OsiCuts & cuts, bool allowResolve, OsiCuts * saveCuts, int numberNewCuts = 0, const OsiRowCut ** newCuts = NULL)

Remove inactive cuts from the model.

An OsiSolverInterface is expected to maintain a valid basis, but not a valid solution, when loose cuts are deleted. Restoring a valid solution requires calling the solver to reoptimise. If it's certain the solution will not be required, set allowResolve to false to suppress reoptimisation. If saveCuts then slack cuts will be saved On input current cuts are cuts and newCuts on exit current cuts will be correct. Returns number dropped

7.74.4.338 int CbcModel::addCuts (CbcNode * node, CoinWarmStartBasis *& lastws, bool canFix)

Determine and install the active cuts that need to be added for the current subproblem.

The whole truth is a bit more complicated. The first action is a call to addCuts1(). addCuts() then sorts through the list, installs the tight cuts in the model, and does bookkeeping (adjusts reference counts). The basis returned from addCuts1() is adjusted accordingly.

If it turns out that the node should really be fathomed by bound, addCuts() simply treats all the cuts as loose as it does the bookkeeping.

canFix true if extra information being passed

7.74.4.339 bool CbcModel::addCuts1 (CbcNode * node, CoinWarmStartBasis *& lastws)

Traverse the tree from node to root and prep the model.

addCuts1() begins the job of prepping the model to match the current subproblem. The model is stripped of all cuts, and the search tree is traversed from node to root to determine the changes required. Appropriate bounds changes are installed, a list of cuts is collected but not installed, and an appropriate basis (minus the cuts, but big enough to accommodate them) is constructed.

Returns true if new problem similar to old

Todo addCuts1() is called in contexts where it's known in advance that all that's desired is to determine a list of cuts and do the bookkeeping (adjust the reference counts). The work of installing bounds and building a basis goes to waste.

7.74.4.340 void CbcModel::previousBounds (CbcNode * node, CbcNodeInfo * where, int iColumn, double & lower, double & upper, int force)

Returns bounds just before where - initially original bounds.

Also sets downstream nodes (lower if force 1, upper if 2)

7.74.4.341 void CbcModel::setObjectiveValue (CbcNode * thisNode, const CbcNode * parentNode) const

Set objective value in a node.

This is separated out so that odd solvers can use. It may look at extra information in solverCharacteriscs_ and will also use bound from parent node

7.74.4.342 void CbcModel::convertToDynamic ()

If numberBeforeTrust >0 then we are going to use CbcBranchDynamic.

Scan and convert CbcSimpleInteger objects

7.74.4.343 void CbcModel::synchronizeNumberBeforeTrust (int type = 0)

Set numberBeforeTrust in all objects.

7.74.4.344 void CbcModel::zapIntegerInformation (bool leaveObjects = true)

Zap integer information in problem (may leave object info)

7.74.4.345 int CbcModel::cliquePseudoCosts (int doStatistics)

Use cliques for pseudocost information - return nonzero if infeasible.

7.74.4.346 void CbcModel::pseudoShadow (int type)

Fill in useful estimates.

7.74.4.347 void CbcModel::fillPseudoCosts (double * downCosts, double * upCosts, int * priority = NULL, int * numberDown = NULL, int * numberUp = NULL, int * numberUplnfeasible = NULL) const

Return pseudo costs If not all integers or not pseudo costs - returns all zero Length of arrays are numberIntegers() and entries correspond to integerVariable()[i] User must allocate arrays before call.

7.74.4.348 void CbcModel::doHeuristicsAtRoot (int deleteHeuristicsAfterwards = 0)

Do heuristics at root.

0 - don't delete 1 - delete 2 - just delete - don't even use

7.74.4.349 void CbcModel::adjustHeuristics ()

Adjust heuristics based on model.

7.74.4.350 const double* CbcModel::hotstartSolution () const [inline]

Get the hotstart solution.

Definition at line 2254 of file CbcModel.hpp.

```
7.74.4.351 const int* CbcModel::hotstartPriorities ( ) const [inline]
Get the hotstart priorities.
Definition at line 2258 of file CbcModel.hpp.
7.74.4.352 CbcCountRowCut** CbcModel::addedCuts() const [inline]
Return the list of cuts initially collected for this subproblem.
Definition at line 2263 of file CbcModel.hpp.
7.74.4.353 int CbcModel::currentNumberCuts ( ) const [inline]
Number of entries in the list returned by addedCuts()
Definition at line 2267 of file CbcModel.hpp.
7.74.4.354 CbcRowCuts* CbcModel::globalCuts() [inline]
Global cuts.
Definition at line 2271 of file CbcModel.hpp.
7.74.4.355 void CbcModel::setNextRowCut ( const OsiRowCut & cut )
Copy and set a pointer to a row cut which will be added instead of normal branching.
7.74.4.356 CbcNode* CbcModel::currentNode() const [inline]
Get a pointer to current node (be careful)
Definition at line 2277 of file CbcModel.hpp.
7.74.4.357 CglTreeProbingInfo* CbcModel::probingInfo( ) const [inline]
Get a pointer to probing info.
Definition at line 2281 of file CbcModel.hpp.
7.74.4.358 CoinThreadRandom* CbcModel::randomNumberGenerator( ) [inline]
Thread specific random number generator.
Definition at line 2285 of file CbcModel.hpp.
7.74.4.359 void CbcModel::setNumberStronglterations (int number) [inline]
Set the number of iterations done in strong branching.
Definition at line 2289 of file CbcModel.hpp.
7.74.4.360 int CbcModel::numberStronglterations ( ) const [inline]
Get the number of iterations done in strong branching.
Definition at line 2293 of file CbcModel.hpp.
7.74.4.361 int CbcModel::maximumNumberIterations ( ) const [inline]
Get maximum number of iterations (designed to be used in heuristics)
```

```
Definition at line 2297 of file CbcModel.hpp.
7.74.4.362 void CbcModel::setMaximumNumberIterations (int value) [inline]
Set maximum number of iterations (designed to be used in heuristics)
Definition at line 2301 of file CbcModel.hpp.
7.74.4.363 void CbcModel::setFastNodeDepth (int value ) [inline]
Set depth for fast nodes.
Definition at line 2305 of file CbcModel.hpp.
7.74.4.364 int CbcModel::fastNodeDepth ( ) const [inline]
Get depth for fast nodes.
Definition at line 2309 of file CbcModel.hpp.
7.74.4.365 int CbcModel::continuousPriority ( ) const [inline]
Get anything with priority >= this can be treated as continuous.
Definition at line 2313 of file CbcModel.hpp.
7.74.4.366 void CbcModel::setContinuousPriority (int value) [inline]
Set anything with priority >= this can be treated as continuous.
Definition at line 2317 of file CbcModel.hpp.
7.74.4.367 void CbcModel::incrementExtra (int nodes, int iterations) [inline]
Definition at line 2320 of file CbcModel.hpp.
7.74.4.368 int CbcModel::numberExtralterations ( ) const [inline]
Number of extra iterations.
Definition at line 2325 of file CbcModel.hpp.
7.74.4.369 void CbcModel::incrementStrongInfo ( int numberTimes, int numberIterations, int numberFixed, bool ifInfeasible )
Increment strong info.
7.74.4.370 const int* CbcModel::strongInfo() const [inline]
Return strong info.
Definition at line 2332 of file CbcModel.hpp.
7.74.4.371 int* CbcModel::mutableStrongInfo() [inline]
Return mutable strong info.
Definition at line 2337 of file CbcModel.hpp.
7.74.4.372 CglStored* CbcModel::storedRowCuts ( ) const [inline]
Get stored row cuts for donor/recipient CbcModel.
```

Definition at line 2341 of file CbcModel.hpp.

7.74.4.373 void CbcModel::setStoredRowCuts (CglStored * cuts) [inline]

Set stored row cuts for donor/recipient CbcModel.

Definition at line 2345 of file CbcModel.hpp.

7.74.4.374 bool CbcModel::allDynamic () const [inline]

Says whether all dynamic integers.

Definition at line 2349 of file CbcModel.hpp.

7.74.4.375 void CbcModel::generateCpp (FILE * fp, int options)

Create C++ lines to get to current state.

7.74.4.376 OsiBranchingInformation CbcModel::usefulInformation () const

Generate an OsiBranchingInformation object.

7.74.4.377 void CbcModel::setBestSolutionBasis (const CoinWarmStartBasis & bestSolutionBasis) [inline]

Warm start object produced by heuristic or strong branching.

If get a valid integer solution outside branch and bound then it can take a reasonable time to solve LP which produces clean solution. If this object has any size then it will be used in solve.

Definition at line 2362 of file CbcModel.hpp.

7.74.4.378 void CbcModel::redoWalkBack ()

Redo walkback arrays.

7.74.4.379 void CbcModel::setMIPStart (const std::vector< std::pair< std::string, double > > & mips) [inline]

Definition at line 2369 of file CbcModel.hpp.

7.74.4.380 const std::vector < std::pair < std::string, double > > & CbcModel::getMIPStart () [inline]

Definition at line 2373 of file CbcModel.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcModel.hpp

7.75 CbcNode Class Reference

Information required while the node is live.

#include <CbcNode.hpp>

Inheritance diagram for CbcNode:



Public Member Functions

CbcNode ()

Default Constructor.

• CbcNode (CbcModel *model, CbcNode *lastNode)

Construct and increment parent reference count.

CbcNode (const CbcNode &)

Copy constructor.

CbcNode & operator= (const CbcNode &rhs)

Assignment operator.

∼CbcNode ()

Destructor.

 void createInfo (CbcModel *model, CbcNode *lastNode, const CoinWarmStartBasis *lastws, const double *last-Lower, const double *lastUpper, int numberOldActiveCuts, int numberNewCuts)

Create a description of the subproblem at this node.

int chooseBranch (CbcModel *model, CbcNode *lastNode, int numberPassesLeft)

Create a branching object for the node.

• int chooseDynamicBranch (CbcModel *model, CbcNode *lastNode, OsiSolverBranch *&branches, int number-PassesLeft)

Create a branching object for the node - when dynamic pseudo costs.

 int chooseOsiBranch (CbcModel *model, CbcNode *lastNode, OsiBranchingInformation *usefulInfo, int branch-State)

Create a branching object for the node.

int chooseClpBranch (CbcModel *model, CbcNode *lastNode)

Create a branching object for the node.

- int analyze (CbcModel *model, double *results)
- void decrementCuts (int change=1)

Decrement active cut counts.

void decrementParentCuts (CbcModel *model, int change=1)

Decrement all active cut counts in chain starting at parent.

void nullNodeInfo ()

Nulls out node info.

void initializeInfo ()

Initialize reference counts in attached CbcNodeInfo.

int branch (OsiSolverInterface *solver)

Does next branch and updates state.

double checklsCutoff (double cutoff)

Double checks in case node can change its mind! Returns objective value Can change objective etc.

- CbcNodeInfo * nodeInfo () const
- double objective Value () const
- void setObjectiveValue (double value)
- int numberBranches () const

Number of arms defined for the attached OsiBranchingObject.

- int way () const
- int depth () const

Depth in branch-and-cut search tree.

void setDepth (int value)

Set depth in branch-and-cut search tree.

• int numberUnsatisfied () const

Get the number of objects unsatisfied at this node.

void setNumberUnsatisfied (int value)

Set the number of objects unsatisfied at this node.

• double sumInfeasibilities () const

Get sum of "infeasibilities" reported by each object.

· void setSumInfeasibilities (double value)

Set sum of "infeasibilities" reported by each object.

- · double guessedObjectiveValue () const
- void setGuessedObjectiveValue (double value)
- const OsiBranchingObject * branchingObject () const

Branching object for this node.

• OsiBranchingObject * modifiableBranchingObject () const

Modifiable branching object for this node.

void setBranchingObject (OsiBranchingObject *branchingObject)

Set branching object for this node (takes ownership)

• int nodeNumber () const

The node number.

- void setNodeNumber (int node)
- bool onTree () const

Returns true if on tree.

• void setOnTree (bool yesNo)

Sets true if on tree.

· bool active () const

Returns true if active.

• void setActive (bool yesNo)

Sets true if active.

• int getState () const

Get state (really for debug)

void setState (int value)

Set state (really for debug)

void print () const

Print.

· void checkInfo () const

Debug.

7.75.1 Detailed Description

Information required while the node is live.

When a subproblem is initially created, it is represented by an CbcNode object and an attached CbcNodeInfo object.

The CbcNode contains information (depth, branching instructions), that's needed while the subproblem remains 'live', *i.e.*, while the subproblem is not fathomed and there are branch arms still be be evaluated. The CbcNode is deleted when the last branch arm has been evaluated.

The CbcNodeInfo object contains the information needed to maintain the search tree and recreate the subproblem for the node. It remains in existence until there are no nodes remaining in the subtree rooted at this node.

Definition at line 49 of file CbcNode.hpp.

```
7.75.2 Constructor & Destructor Documentation
```

7.75.2.1 CbcNode::CbcNode()

Default Constructor.

7.75.2.2 CbcNode::CbcNode (CbcModel * model, CbcNode * lastNode)

Construct and increment parent reference count.

7.75.2.3 CbcNode::CbcNode (const CbcNode &)

Copy constructor.

7.75.2.4 CbcNode::~CbcNode()

Destructor.

7.75.3 Member Function Documentation

7.75.3.1 CbcNode& CbcNode::operator= (const CbcNode & rhs)

Assignment operator.

7.75.3.2 void CbcNode::createInfo (CbcModel * model, CbcNode * lastNode, const CoinWarmStartBasis * lastws, const double * lastLower, const double * lastUpper, int numberOldActiveCuts, int numberNewCuts)

Create a description of the subproblem at this node.

The CbcNodeInfo structure holds the information (basis & variable bounds) required to recreate the subproblem for this node. It also links the node to its parent (via the parent's CbcNodeInfo object).

If lastNode == NULL, a CbcFullNodeInfo object will be created. All parameters except model are unused.

If lastNode != NULL, a CbcPartialNodeInfo object will be created. Basis and bounds information will be stored in the form of differences between the parent subproblem and this subproblem. (More precisely, lastws, lastUpper, lastLower, numberOldActiveCuts, and numberNewCuts are used.)

7.75.3.3 int CbcNode::chooseBranch (CbcModel * model, CbcNode * lastNode, int numberPassesLeft)

Create a branching object for the node.

The routine scans the object list of the model and selects a set of unsatisfied objects as candidates for branching. The

candidates are evaluated, and an appropriate branch object is installed.

The numberPassesLeft is decremented to stop fixing one variable each time and going on and on (e.g. for stock cutting, air crew scheduling)

If evaluation determines that an object is monotone or infeasible, the routine returns immediately. In the case of a monotone object, the branch object has already been called to modify the model.

Return value:

- · 0: A branching object has been installed
- -1: A monotone object was discovered
- · -2: An infeasible object was discovered

7.75.3.4 int CbcNode::chooseDynamicBranch (CbcModel * model, CbcNode * lastNode, OsiSolverBranch *& branches, int numberPassesLeft)

Create a branching object for the node - when dynamic pseudo costs.

The routine scans the object list of the model and selects a set of unsatisfied objects as candidates for branching. The candidates are evaluated, and an appropriate branch object is installed. This version gives preference in evaluation to variables which have not been evaluated many times. It also uses numberStrong to say give up if last few tries have not changed incumbent. See Achterberg, Koch and Martin.

The numberPassesLeft is decremented to stop fixing one variable each time and going on and on (e.g. for stock cutting, air crew scheduling)

If evaluation determines that an object is monotone or infeasible, the routine returns immediately. In the case of a monotone object, the branch object has already been called to modify the model.

Return value:

- 0: A branching object has been installed
- · -1: A monotone object was discovered
- -2: An infeasible object was discovered
- >0: Number of quich branching objects (and branches will be non NULL)

7.75.3.5 int CbcNode::chooseOsiBranch (CbcModel * model, CbcNode * lastNode, OsiBranchingInformation * usefulInfo, int branchState)

Create a branching object for the node.

The routine scans the object list of the model and selects a set of unsatisfied objects as candidates for branching. The candidates are evaluated, and an appropriate branch object is installed.

The numberPassesLeft is decremented to stop fixing one variable each time and going on and on (e.g. for stock cutting, air crew scheduling)

If evaluation determines that an object is monotone or infeasible, the routine returns immediately. In the case of a monotone object, the branch object has already been called to modify the model.

Return value:

- 0: A branching object has been installed
- -1: A monotone object was discovered

· -2: An infeasible object was discovered

Branch state:

- -1: start
- -1: A monotone object was discovered
- · -2: An infeasible object was discovered

```
7.75.3.6 int CbcNode::chooseClpBranch ( CbcModel * model, CbcNode * lastNode )
```

Create a branching object for the node.

The routine scans the object list of the model and selects a set of unsatisfied objects as candidates for branching. It then solves a series of problems and a CbcGeneral branch object is installed.

If evaluation determines that an object is infeasible, the routine returns immediately.

Return value:

- · 0: A branching object has been installed
- -2: An infeasible object was discovered

```
7.75.3.7 int CbcNode::analyze ( CbcModel * model, double * results )
```

```
7.75.3.8 void CbcNode::decrementCuts (int change = 1)
```

Decrement active cut counts.

```
7.75.3.9 void CbcNode::decrementParentCuts ( CbcModel * model, int change = 1 )
```

Decrement all active cut counts in chain starting at parent.

```
7.75.3.10 void CbcNode::nullNodeInfo()
```

Nulls out node info.

```
7.75.3.11 void CbcNode::initializeInfo ( )
```

Initialize reference counts in attached CbcNodeInfo.

This is a convenience routine, which will initialize the reference counts in the attached CbcNodeInfo object based on the attached OsiBranchingObject.

See Also

CbcNodeInfo::initializeInfo(int).

```
7.75.3.12 int CbcNode::branch ( OsiSolverInterface * solver )
```

Does next branch and updates state.

```
7.75.3.13 double CbcNode::checklsCutoff ( double cutoff )
```

Double checks in case node can change its mind! Returns objective value Can change objective etc.

```
7.75.3.14 CbcNodeInfo* CbcNode::nodeInfo() const [inline]
Definition at line 216 of file CbcNode.hpp.
7.75.3.15 double CbcNode::objectiveValue ( ) const [inline]
Definition at line 221 of file CbcNode.hpp.
7.75.3.16 void CbcNode::setObjectiveValue ( double value ) [inline]
Definition at line 224 of file CbcNode.hpp.
7.75.3.17 int CbcNode::numberBranches ( ) const [inline]
Number of arms defined for the attached OsiBranchingObject.
Definition at line 228 of file CbcNode.hpp.
7.75.3.18 int CbcNode::way ( ) const
7.75.3.19 int CbcNode::depth ( ) const [inline]
Depth in branch-and-cut search tree.
Definition at line 243 of file CbcNode.hpp.
7.75.3.20 void CbcNode::setDepth (int value) [inline]
Set depth in branch-and-cut search tree.
Definition at line 247 of file CbcNode.hpp.
7.75.3.21 int CbcNode::numberUnsatisfied ( ) const [inline]
Get the number of objects unsatisfied at this node.
Definition at line 251 of file CbcNode.hpp.
7.75.3.22 void CbcNode::setNumberUnsatisfied (int value) [inline]
Set the number of objects unsatisfied at this node.
Definition at line 255 of file CbcNode.hpp.
7.75.3.23 double CbcNode::sumInfeasibilities ( ) const [inline]
Get sum of "infeasibilities" reported by each object.
Definition at line 259 of file CbcNode.hpp.
7.75.3.24 void CbcNode::setSumInfeasibilities ( double value ) [inline]
Set sum of "infeasibilities" reported by each object.
Definition at line 263 of file CbcNode.hpp.
7.75.3.25 double CbcNode::guessedObjectiveValue( )const [inline]
Definition at line 267 of file CbcNode.hpp.
```

```
7.75.3.26 void CbcNode::setGuessedObjectiveValue ( double value ) [inline]
Definition at line 270 of file CbcNode.hpp.
7.75.3.27 const OsiBranchingObject* CbcNode::branchingObject( ) const [inline]
Branching object for this node.
Definition at line 274 of file CbcNode.hpp.
7.75.3.28 OsiBranchingObject* CbcNode::modifiableBranchingObject( ) const [inline]
Modifiable branching object for this node.
Definition at line 278 of file CbcNode.hpp.
7.75.3.29 void CbcNode::setBranchingObject ( OsiBranchingObject * branchingObject ) [inline]
Set branching object for this node (takes ownership)
Definition at line 282 of file CbcNode.hpp.
7.75.3.30 int CbcNode::nodeNumber() const [inline]
The node number.
Definition at line 286 of file CbcNode.hpp.
7.75.3.31 void CbcNode::setNodeNumber(int node) [inline]
Definition at line 289 of file CbcNode.hpp.
7.75.3.32 bool CbcNode::onTree() const [inline]
Returns true if on tree.
Definition at line 293 of file CbcNode.hpp.
7.75.3.33 void CbcNode::setOnTree ( bool yesNo ) [inline]
Sets true if on tree.
Definition at line 297 of file CbcNode.hpp.
7.75.3.34 bool CbcNode::active ( ) const [inline]
Returns true if active.
Definition at line 302 of file CbcNode.hpp.
7.75.3.35 void CbcNode::setActive (bool yesNo) [inline]
Sets true if active.
Definition at line 306 of file CbcNode.hpp.
7.75.3.36 int CbcNode::getState() const [inline]
Get state (really for debug)
Definition at line 311 of file CbcNode.hpp.
```

7.75.3.37 void CbcNode::setState (int value) [inline]

Set state (really for debug)

Definition at line 314 of file CbcNode.hpp.

7.75.3.38 void CbcNode::print () const

Print.

7.75.3.39 void CbcNode::checkInfo() const [inline]

Debug.

Definition at line 319 of file CbcNode.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcNode.hpp

7.76 CbcNodeInfo Class Reference

Information required to recreate the subproblem at this node.

#include <CbcNodeInfo.hpp>

Inheritance diagram for CbcNodeInfo:



Public Member Functions

 virtual void applyToModel (CbcModel *model, CoinWarmStartBasis *&basis, CbcCountRowCut **addCuts, int ¤tNumberCuts) const =0

Modify model according to information at node.

virtual int applyBounds (int iColumn, double &lower, double &upper, int force)=0

Just apply bounds to one variable - force means overwrite by lower,upper (1=>infeasible)

virtual CbcNodeInfo * buildRowBasis (CoinWarmStartBasis &basis) const =0

Builds up row basis backwards (until original model).

virtual CbcNodeInfo * clone () const =0

Clone.

• virtual void allBranchesGone ()

Called when number branches left down to zero.

void increment (int amount=1)

Increment number of references.

• int decrement (int amount=1)

Decrement number of references and return number left.

• void initializeInfo (int number)

Initialize reference counts.

· int numberBranchesLeft () const

Return number of branches left in object.

void setNumberBranchesLeft (int value)

Set number of branches left in object.

int numberPointingToThis () const

Return number of objects pointing to this.

void setNumberPointingToThis (int number)

Set number of objects pointing to this.

void incrementNumberPointingToThis ()

Increment number of objects pointing to this.

• int branchedOn ()

Say one branch taken.

· void throwAway ()

Say thrown away.

CbcNodeInfo * parent () const

Parent of this.

• void nullParent ()

Set parent null.

- void addCuts (OsiCuts &cuts, int numberToBranch, int numberPointingToThis)
- void addCuts (int numberCuts, CbcCountRowCut **cuts, int numberToBranch)
- void deleteCuts (int numberToDelete, CbcCountRowCut **cuts)

Delete cuts (decrements counts) Slow unless cuts in same order as saved.

- void deleteCuts (int numberToDelete, int *which)
- void deleteCut (int whichOne)

Really delete a cut.

void decrementCuts (int change=1)

Decrement active cut counts.

void incrementCuts (int change=1)

Increment active cut counts.

void decrementParentCuts (CbcModel *model, int change=1)

Decrement all active cut counts in chain starting at parent.

void incrementParentCuts (CbcModel *model, int change=1)

Increment all active cut counts in parent chain.

CbcCountRowCut ** cuts () const

Array of pointers to cuts.

• int numberCuts () const

Number of row cuts (this node)

- void setNumberCuts (int value)
- void nullOwner ()

Set owner null.

- const CbcNode * owner () const
- CbcNode * mutableOwner () const
- int nodeNumber () const

The node number.

- void setNodeNumber (int node)
- void deactivate (int mode=3)

Deactivate node information.

• bool allActivated () const

Say if normal.

· bool marked () const

Say if marked.

· void mark ()

Mark.

· void unmark ()

Unmark.

const OsiBranchingObject * parentBranch () const

Branching object for the parent.

• void unsetParentBasedData ()

If we need to take off parent based data.

Constructors & destructors

• CbcNodeInfo ()

Default Constructor.

CbcNodeInfo (const CbcNodeInfo &)

Copy constructor.

• CbcNodeInfo (CbcNodeInfo *parent, CbcNode *owner)

Construct with parent and owner.

virtual ∼CbcNodeInfo ()

Destructor.

Protected Attributes

int numberPointingToThis_

Number of other nodes pointing to this node.

CbcNodeInfo * parent_

parent

• OsiBranchingObject * parentBranch_

Copy of the branching object of the parent when the node is created.

CbcNode * owner_

Owner.

int numberCuts_

Number of row cuts (this node)

int nodeNumber

The node number.

• CbcCountRowCut ** cuts_

Array of pointers to cuts.

• int numberRows_

Number of rows in problem (before these cuts).

int numberBranchesLeft

Number of branch arms left to explore at this node.

int active

Active node information.

7.76.1 Detailed Description

Information required to recreate the subproblem at this node.

When a subproblem is initially created, it is represented by a CbcNode object and an attached CbcNodeInfo object.

The CbcNode contains information needed while the subproblem remains live. The CbcNode is deleted when the last branch arm has been evaluated.

The CbcNodeInfo contains information required to maintain the branch-and-cut search tree structure (links and reference counts) and to recreate the subproblem for this node (basis, variable bounds, cutting planes). A CbcNodeInfo object remains in existence until all nodes have been pruned from the subtree rooted at this node.

The principle used to maintain the reference count is that the reference count is always the sum of all potential and actual children of the node. Specifically,

- Once it's determined how the node will branch, the reference count is set to the number of potential children (*i.e.*, the number of arms of the branch).
- As each child is created by CbcNode::branch() (converting a potential child to the active subproblem), the reference count is decremented.
- If the child survives and will become a node in the search tree (converting the active subproblem into an actual child), increment the reference count.

Notice that the active subproblem lives in a sort of limbo, neither a potential or an actual node in the branch-and-cut tree.

CbcNodeInfo objects come in two flavours. A CbcFullNodeInfo object contains a full record of the information required to recreate a subproblem. A CbcPartialNodeInfo object expresses this information in terms of differences from the parent.

Definition at line 68 of file CbcNodeInfo.hpp.

```
7.76.2 Constructor & Destructor Documentation
```

7.76.2.1 CbcNodeInfo::CbcNodeInfo()

Default Constructor.

Creates an empty NodeInfo object.

7.76.2.2 CbcNodeInfo::CbcNodeInfo (const CbcNodeInfo &)

Copy constructor.

7.76.2.3 CbcNodeInfo::CbcNodeInfo (CbcNodeInfo * parent, CbcNode * owner)

Construct with parent and owner.

As for 'construct with parent', and attached to owner.

7.76.2.4 virtual CbcNodeInfo:: ~ CbcNodeInfo() [virtual]

Destructor.

Note that the destructor will recursively delete the parent if this nodelnfo is the last child.

7.76.3 Member Function Documentation

7.76.3.1 virtual void CbcNodelnfo::applyToModel (CbcModel * model, CoinWarmStartBasis *& basis, CbcCountRowCut ** addCuts, int & currentNumberCuts) const [pure virtual]

Modify model according to information at node.

The routine modifies the model according to bound and basis information at node and adds any cuts to the addCuts array.

Implemented in CbcFullNodeInfo, and CbcPartialNodeInfo.

7.76.3.2 virtual int CbcNodelnfo::applyBounds (int iColumn, double & lower, double & upper, int force) [pure virtual]

Just apply bounds to one variable - force means overwrite by lower,upper (1=>infeasible)

Implemented in CbcFullNodeInfo, and CbcPartialNodeInfo.

7.76.3.3 virtual CbcNodeInfo* CbcNodeInfo::buildRowBasis (CoinWarmStartBasis & basis) const [pure virtual]

Builds up row basis backwards (until original model).

Returns NULL or previous one to apply . Depends on Free being 0 and impossible for cuts

Implemented in CbcFullNodeInfo, and CbcPartialNodeInfo.

7.76.3.4 virtual CbcNodeInfo* CbcNodeInfo::clone() const [pure virtual]

Clone.

Implemented in CbcFullNodeInfo, and CbcPartialNodeInfo.

7.76.3.5 virtual void CbcNodelnfo::allBranchesGone() [inline], [virtual]

Called when number branches left down to zero.

Definition at line 126 of file CbcNodeInfo.hpp.

7.76.3.6 void CbcNodeInfo::increment (int amount = 1) [inline]

Increment number of references.

Definition at line 129 of file CbcNodeInfo.hpp.

7.76.3.7 int CbcNodeInfo::decrement (int amount = 1) [inline]

Decrement number of references and return number left.

Definition at line 134 of file CbcNodeInfo.hpp.

7.76.3.8 void CbcNodeInfo::initializeInfo (int number) [inline]

Initialize reference counts.

Initialize the reference counts used for tree maintenance.

Definition at line 149 of file CbcNodeInfo.hpp.

7.76.3.9 int CbcNodeInfo::numberBranchesLeft() const [inline]

Return number of branches left in object.

Definition at line 155 of file CbcNodeInfo.hpp.

```
7.76.3.10 void CbcNodeInfo::setNumberBranchesLeft (int value) [inline]
Set number of branches left in object.
Definition at line 160 of file CbcNodeInfo.hpp.
7.76.3.11 int CbcNodeInfo::numberPointingToThis() const [inline]
Return number of objects pointing to this.
Definition at line 165 of file CbcNodeInfo.hpp.
7.76.3.12 void CbcNodeInfo::setNumberPointingToThis (int number) [inline]
Set number of objects pointing to this.
Definition at line 170 of file CbcNodeInfo.hpp.
7.76.3.13 void CbcNodeInfo::incrementNumberPointingToThis() [inline]
Increment number of objects pointing to this.
Definition at line 175 of file CbcNodeInfo.hpp.
7.76.3.14 int CbcNodeInfo::branchedOn() [inline]
Say one branch taken.
Definition at line 180 of file CbcNodeInfo.hpp.
7.76.3.15 void CbcNodeInfo::throwAway() [inline]
Say thrown away.
Definition at line 187 of file CbcNodeInfo.hpp.
7.76.3.16 CbcNodeInfo* CbcNodeInfo::parent() const [inline]
Parent of this.
Definition at line 193 of file CbcNodeInfo.hpp.
7.76.3.17 void CbcNodeInfo::nullParent() [inline]
Set parent null.
Definition at line 197 of file CbcNodeInfo.hpp.
7.76.3.18 void CbcNodeInfo::addCuts (OsiCuts & cuts, int numberToBranch, int numberPointingToThis)
7.76.3.19 void CbcNodeInfo::addCuts ( int numberCuts, CbcCountRowCut ** cuts, int numberToBranch )
7.76.3.20 void CbcNodeInfo::deleteCuts ( int numberToDelete, CbcCountRowCut ** cuts )
Delete cuts (decrements counts) Slow unless cuts in same order as saved.
7.76.3.21 void CbcNodeInfo::deleteCuts (int numberToDelete, int * which )
7.76.3.22 void CbcNodeInfo::deleteCut ( int whichOne )
Really delete a cut.
```

```
7.76.3.23 void CbcNodeInfo::decrementCuts (int change = 1)
Decrement active cut counts.
7.76.3.24 void CbcNodeInfo::incrementCuts ( int change = 1 )
Increment active cut counts.
7.76.3.25 void CbcNodelnfo::decrementParentCuts ( CbcModel * model, int change = 1 )
Decrement all active cut counts in chain starting at parent.
7.76.3.26 void CbcNodelnfo::incrementParentCuts ( CbcModel * model, int change = 1 )
Increment all active cut counts in parent chain.
7.76.3.27 CbcCountRowCut** CbcNodeInfo::cuts() const [inline]
Array of pointers to cuts.
Definition at line 226 of file CbcNodeInfo.hpp.
7.76.3.28 int CbcNodeInfo::numberCuts ( ) const [inline]
Number of row cuts (this node)
Definition at line 231 of file CbcNodeInfo.hpp.
7.76.3.29 void CbcNodeInfo::setNumberCuts (int value ) [inline]
Definition at line 234 of file CbcNodeInfo.hpp.
7.76.3.30 void CbcNodeInfo::nullOwner() [inline]
Set owner null.
Definition at line 239 of file CbcNodeInfo.hpp.
7.76.3.31 const CbcNode* CbcNodeInfo::owner() const [inline]
Definition at line 242 of file CbcNodeInfo.hpp.
7.76.3.32 CbcNode* CbcNodeInfo::mutableOwner( ) const [inline]
Definition at line 245 of file CbcNodeInfo.hpp.
7.76.3.33 int CbcNodeInfo::nodeNumber() const [inline]
The node number.
Definition at line 249 of file CbcNodeInfo.hpp.
7.76.3.34 void CbcNodeInfo::setNodeNumber ( int node ) [inline]
Definition at line 252 of file CbcNodeInfo.hpp.
7.76.3.35 void CbcNodeInfo::deactivate (int mode = 3)
Deactivate node information.
```

```
1 - bounds 2 - cuts 4 - basis!
7.76.3.36 bool CbcNodeInfo::allActivated ( ) const [inline]
Say if normal.
Definition at line 262 of file CbcNodeInfo.hpp.
7.76.3.37 bool CbcNodeInfo::marked ( ) const [inline]
Say if marked.
Definition at line 266 of file CbcNodeInfo.hpp.
7.76.3.38 void CbcNodeInfo::mark() [inline]
Mark.
Definition at line 270 of file CbcNodeInfo.hpp.
7.76.3.39 void CbcNodeInfo::unmark( ) [inline]
Unmark.
Definition at line 274 of file CbcNodeInfo.hpp.
7.76.3.40 const OsiBranchingObject* CbcNodeInfo::parentBranch( ) const [inline]
Branching object for the parent.
Definition at line 279 of file CbcNodeInfo.hpp.
7.76.3.41 void CbcNodeInfo::unsetParentBasedData ( )
If we need to take off parent based data.
7.76.4 Member Data Documentation
7.76.4.1 int CbcNodeInfo::numberPointingToThis_ [protected]
Number of other nodes pointing to this node.
Number of existing and potential search tree nodes pointing to this node. 'Existing' means referenced by parent of
some other CbcNodeInfo. 'Potential' means children still to be created (numberBranchesLeft_ of this CbcNodeInfo).
Definition at line 293 of file CbcNodeInfo.hpp.
7.76.4.2 CbcNodeInfo* CbcNodeInfo::parent_ [protected]
parent
Definition at line 296 of file CbcNodeInfo.hpp.
7.76.4.3 OsiBranchingObject* CbcNodeInfo::parentBranch_ [protected]
Copy of the branching object of the parent when the node is created.
Definition at line 299 of file CbcNodeInfo.hpp.
```

7.76.4.4 CbcNode* CbcNodeInfo::owner_ [protected]

Owner.

Definition at line 302 of file CbcNodeInfo.hpp.

7.76.4.5 int CbcNodeInfo::numberCuts_ [protected]

Number of row cuts (this node)

Definition at line 305 of file CbcNodeInfo.hpp.

7.76.4.6 int CbcNodeInfo::nodeNumber_ [protected]

The node number.

Definition at line 308 of file CbcNodeInfo.hpp.

7.76.4.7 CbcCountRowCut** CbcNodeInfo::cuts_ [protected]

Array of pointers to cuts.

Definition at line 311 of file CbcNodeInfo.hpp.

7.76.4.8 int CbcNodeInfo::numberRows_ [protected]

Number of rows in problem (before these cuts).

This means that for top of chain it must be rows at continuous

Definition at line 315 of file CbcNodeInfo.hpp.

7.76.4.9 int CbcNodeInfo::numberBranchesLeft_ [protected]

Number of branch arms left to explore at this node.

Todo There seems to be redundancy between this field and CbcBranchingObject::numberBranchesLeft_. It'd be good to sort out if both are necessary.

Definition at line 323 of file CbcNodeInfo.hpp.

7.76.4.10 int CbcNodeInfo::active_ [protected]

Active node information.

1 - bounds 2 - cuts 4 - basis!

Definition at line 329 of file CbcNodeInfo.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcNodeInfo.hpp

7.77 CbcNWay Class Reference

Define an n-way class for variables.

#include <CbcNWay.hpp>

Inheritance diagram for CbcNWay:



Public Member Functions

- CbcNWay ()
- CbcNWay (CbcModel *model, int numberMembers, const int *which, int identifier)

Useful constructor (which are matrix indices)

- CbcNWay (const CbcNWay &)
- virtual CbcObject * clone () const

Clone

CbcNWay & operator= (const CbcNWay &rhs)

Assignment operator.

virtual ∼CbcNWay ()

Destructor.

void setConsequence (int iColumn, const CbcConsequence &consequence)

Set up a consequence for a single member.

void applyConsequence (int iSequence, int state) const

Applies a consequence for a single member.

• virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const

Infeasibility - large is 0.5 (and 0.5 will give this)

virtual void feasibleRegion ()

This looks at solution and sets bounds to contain solution.

virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Creates a branching object.

• int numberMembers () const

Number of members.

• const int * members () const

Members (indices in range 0 ... numberColumns-1)

virtual void redoSequenceEtc (CbcModel *model, int numberColumns, const int *originalColumns)

Redoes data when sequence numbers change.

Protected Attributes

int numberMembers

data Number of members

int * members

Members (indices in range 0 ... numberColumns-1)

• CbcConsequence ** consequence_

Consequences (normally NULL)

```
7.77.1 Detailed Description
Define an n-way class for variables.
Only valid value is one at UB others at LB Normally 0-1
Definition at line 15 of file CbcNWay.hpp.
7.77.2 Constructor & Destructor Documentation
7.77.2.1 CbcNWay::CbcNWay()
7.77.2.2 CbcNWay::CbcNWay ( CbcModel * model, int numberMembers, const int * which, int identifier )
Useful constructor (which are matrix indices)
7.77.2.3 CbcNWay::CbcNWay ( const CbcNWay & )
7.77.2.4 virtual CbcNWay::~CbcNWay() [virtual]
Destructor.
7.77.3 Member Function Documentation
7.77.3.1 virtual CbcObject* CbcNWay::clone( )const [virtual]
Clone.
Implements CbcObject.
7.77.3.2 CbcNWay& CbcNWay::operator= ( const CbcNWay & rhs )
Assignment operator.
7.77.3.3 void CbcNWay::setConsequence (int iColumn, const CbcConsequence & consequence)
Set up a consequence for a single member.
7.77.3.4 void CbcNWay::applyConsequence (int iSequence, int state) const
Applies a consequence for a single member.
7.77.3.5 virtual double CbcNWay::infeasibility ( const OsiBranchingInformation * info, int & preferredWay ) const [virtual]
Infeasibility - large is 0.5 (and 0.5 will give this)
Reimplemented from CbcObject.
7.77.3.6 virtual void CbcNWay::feasibleRegion() [virtual]
This looks at solution and sets bounds to contain solution.
Implements CbcObject.
7.77.3.7 virtual CbcBranchingObject* CbcNWay::createCbcBranch ( OsiSolverInterface * solver, const
         OsiBranchingInformation * info, int way ) [virtual]
Creates a branching object.
```

Reimplemented from CbcObject.

7.77.3.8 int CbcNWay::numberMembers () const [inline]

Number of members.

Definition at line 57 of file CbcNWay.hpp.

7.77.3.9 const int* CbcNWay::members () const [inline]

Members (indices in range 0 ... numberColumns-1)

Definition at line 62 of file CbcNWay.hpp.

7.77.3.10 virtual void CbcNWay::redoSequenceEtc (CbcModel * model, int numberColumns, const int * originalColumns)
[virtual]

Redoes data when sequence numbers change.

Reimplemented from CbcObject.

7.77.4 Member Data Documentation

7.77.4.1 int CbcNWay::numberMembers_ [protected]

data Number of members

Definition at line 71 of file CbcNWay.hpp.

7.77.4.2 int* CbcNWay::members_ [protected]

Members (indices in range 0 ... numberColumns-1)

Definition at line 74 of file CbcNWay.hpp.

7.77.4.3 CbcConsequence** CbcNWay::consequence_ [protected]

Consequences (normally NULL)

Definition at line 76 of file CbcNWay.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcNWay.hpp

7.78 CbcNWayBranchingObject Class Reference

N way branching Object class.

#include <CbcNWay.hpp>

Inheritance diagram for CbcNWayBranchingObject:



Public Member Functions

- CbcNWayBranchingObject ()
- CbcNWayBranchingObject (CbcModel *model, const CbcNWay *nway, int numberBranches, const int *order)

Useful constructor - order had matrix indices way_ -1 corresponds to setting first, +1 to second, +3 etc.

- CbcNWayBranchingObject (const CbcNWayBranchingObject &)
- CbcNWayBranchingObject & operator= (const CbcNWayBranchingObject &rhs)
- virtual CbcBranchingObject * clone () const

Clone.

- virtual ~CbcNWayBranchingObject ()
- virtual double branch ()

Does next branch and updates state.

virtual void print ()

Print something about branch - only if log level high.

· virtual int numberBranches () const

The number of branch arms created for this branching object.

virtual bool twoWay () const

Is this a two way object (-1 down, +1 up)

• virtual CbcBranchObjType type () const

Return the type (an integer identifier) of this.

virtual int compareOriginalObject (const CbcBranchingObject *brObj) const

Compare the original object of this with the original object of brobj.

 virtual CbcRangeCompare compareBranchingObject (const CbcBranchingObject *brObj, const bool replaceIf-Overlap=false)

Compare the this with brObj.

Additional Inherited Members

7.78.1 Detailed Description

N way branching Object class.

Variable is number of set.

Definition at line 81 of file CbcNWay.hpp.

```
7.78.2 Constructor & Destructor Documentation
7.78.2.1 CbcNWayBranchingObject::CbcNWayBranchingObject()
7.78.2.2 CbcNWayBranchingObject::CbcNWayBranchingObject ( CbcModel * model, const CbcNWay * nway, int
        numberBranches, const int * order )
Useful constructor - order had matrix indices way_ -1 corresponds to setting first, +1 to second, +3 etc.
this is so -1 and +1 have similarity to normal
7.78.2.3 CbcNWayBranchingObject::CbcNWayBranchingObject ( const CbcNWayBranchingObject & )
7.78.2.4 virtual CbcNWayBranchingObject::~CbcNWayBranchingObject() [virtual]
7.78.3 Member Function Documentation
7.78.3.1 CbcNWayBranchingObject & CbcNWayBranchingObject tonst CbcNWayBranchingObject & rhs )
7.78.3.2 virtual CbcBranchingObject* CbcNWayBranchingObject::clone() const [virtual]
Clone.
Implements CbcBranchingObject.
7.78.3.3 virtual double CbcNWayBranchingObject::branch() [virtual]
Does next branch and updates state.
Implements CbcBranchingObject.
7.78.3.4 virtual void CbcNWayBranchingObject::print() [virtual]
Print something about branch - only if log level high.
7.78.3.5 virtual int CbcNWayBranchingObject::numberBranches ( ) const [inline], [virtual]
The number of branch arms created for this branching object.
Definition at line 125 of file CbcNWay.hpp.
7.78.3.6 virtual bool CbcNWayBranchingObject::twoWay() const [inline], [virtual]
Is this a two way object (-1 down, +1 up)
Definition at line 129 of file CbcNWay.hpp.
7.78.3.7 virtual CbcBranchObjType CbcNWayBranchingObject::type( )const [inline], [virtual]
Return the type (an integer identifier) of this.
Implements CbcBranchingObject.
Definition at line 134 of file CbcNWay.hpp.
7.78.3.8 virtual int CbcNWayBranchingObject::compareOriginalObject ( const CbcBranchingObject * brObj ) const
         [virtual]
```

Assumes that there is an ordering of the original objects. This method should be invoked only if this and brObj are of

Generated on Mon Oct 21 2013 19:03:07 for Cbc by Doxygen

Compare the original object of this with the original object of brobj.

the same type. Return negative/0/positive depending on whether this is smaller/same/larger than the argument. Reimplemented from CbcBranchingObject.

7.78.3.9 virtual CbcRangeCompare CbcNWayBranchingObject::compareBranchingObject (const CbcBranchingObject * brObj, const bool replacelfOverlap = false) [virtual]

Compare the this with brObj.

this and brobj must be os the same type and must have the same original object, but they may have different feasible regions. Return the appropriate CbcRangeCompare value (first argument being the sub/superset if that's the case). In case of overlap (and if replaceIfOverlap is true) replace the current branching object with one whose feasible region is the overlap.

Implements CbcBranchingObject.


The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcNWay.hpp

7.79 CbcObject Class Reference

#include <CbcObject.hpp>

Inheritance diagram for CbcObject:



Public Member Functions

- CbcObject ()
- CbcObject (CbcModel *model)
- CbcObject (const CbcObject &)
- CbcObject & operator= (const CbcObject &rhs)
- virtual CbcObject * clone () const =0

Clone.

virtual ∼CbcObject ()

Destructor.

virtual double infeasibility (const OsiBranchingInformation *, int &preferredWay) const

Infeasibility of the object.

- · virtual double infeasibility (int &) const
- virtual void feasibleRegion ()=0

For the variable(s) referenced by the object, look at the current solution and set bounds to match the solution.

• virtual double feasibleRegion (OsiSolverInterface *solver, const OsiBranchingInformation *info) const Dummy one for compatibility.

virtual double feasibleRegion (OsiSolverInterface *solver) const

For the variable(s) referenced by the object, look at the current solution and set bounds to match the solution.

• virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *, const OsiBranchingInformation *, int)

Create a branching object and indicate which way to branch first.

- virtual OsiBranchingObject * createBranch (OsiSolverInterface *, const OsiBranchingInformation *, int) const
- virtual OsiBranchingObject * createOsiBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way) const

Create an Osibranching object and indicate which way to branch first.

• virtual OsiSolverBranch * solverBranch () const

Create an OsiSolverBranch object.

virtual CbcBranchingObject * preferredNewFeasible () const

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a good direction.

virtual CbcBranchingObject * notPreferredNewFeasible () const

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a bad direction.

virtual void resetBounds (const OsiSolverInterface *)

Reset variable bounds to their original values.

Returns floor and ceiling i.e.

• virtual void floorCeiling (double &floorValue, double &ceilingValue, double value, double tolerance) const

virtual CbcObjectUpdateData createUpdateInformation (const OsiSolverInterface *solver, const CbcNode *node, const CbcBranchingObject *branchingObject)

Pass in information on branch just done and create CbcObjectUpdateData instance.

virtual void updateInformation (const CbcObjectUpdateData &)

Update object by CbcObjectUpdateData.

• int id () const

Identifier (normally column number in matrix)

void setId (int value)

Set identifier (normally column number in matrix) but 1000000000 to 1100000000 means optional branching object i.e.

bool optionalObject () const

Return true if optional branching object i.e.

```
• int position () const
           Get position in object_ list.
    • void setPosition (int position)
          Set position in object_ list.

    void setModel (CbcModel *model)

          update model
    • CbcModel * model () const
           Return model.
    • int preferredWay () const
          If -1 down always chosen first, +1 up always, 0 normal.

    void setPreferredWay (int value)

          Set -1 down always chosen first, +1 up always, 0 normal.

    virtual void redoSequenceEtc (CbcModel *, int, const int *)

           Redoes data when sequence numbers change.

    virtual void initializeForBranching (CbcModel *)

          Initialize for branching.
Protected Attributes
    • CbcModel * model
          data

    int id

           Identifier (normally column number in matrix)
    · int position_
          Position in object list.
    • int preferredWay_
           If -1 down always chosen first, +1 up always, 0 normal.
7.79.1 Detailed Description
Definition at line 67 of file CbcObject.hpp.
7.79.2 Constructor & Destructor Documentation
7.79.2.1 CbcObject::CbcObject()
7.79.2.2 CbcObject::CbcObject ( CbcModel * model )
7.79.2.3
         CbcObject::CbcObject ( const CbcObject & )
7.79.2.4 virtual CbcObject::~CbcObject() [virtual]
```

Destructor.

7.79.3 Member Function Documentation

```
7.79.3.1 CbcObject& CbcObject::operator= ( const CbcObject & rhs )
```

```
7.79.3.2 virtual CbcObject* CbcObject::clone() const [pure virtual]
```

Clone.

Implemented in CbcSimpleInteger, CbcIdiotBranch, CbcClique, CbcSimpleIntegerDynamicPseudoCost, CbcSOS, CbcBranchToFixLots, CbcFollowOn, CbcBranchAllDifferent, CbcSimpleIntegerPseudoCost, CbcGeneral, CbcBranchCut, CbcNWay, and CbcLotsize.

```
7.79.3.3 virtual double CbcObject::infeasibility ( const OsiBranchingInformation * , int & preferredWay ) const [inline], [virtual]
```

Infeasibility of the object.

This is some measure of the infeasibility of the object. It should be scaled to be in the range [0.0, 0.5], with 0.0 indicating the object is satisfied.

The preferred branching direction is returned in preferredWay,

This is used to prepare for strong branching but should also think of case when no strong branching

The object may also compute an estimate of cost of going "up" or "down". This will probably be based on pseudo-cost ideas

Reimplemented in CbcSimpleInteger, CbcIdiotBranch, CbcClique, CbcSimpleIntegerDynamicPseudoCost, CbcSOS, CbcBranchToFixLots, CbcFollowOn, CbcBranchAllDifferent, CbcNWay, CbcSimpleIntegerPseudoCost, CbcGeneral, CbcBranchCut, and CbcLotsize.

Definition at line 107 of file CbcObject.hpp.

```
7.79.3.4 virtual double CbcObject::infeasibility ( int & ) const [inline], [virtual]
```

Definition at line 111 of file CbcObject.hpp.

```
7.79.3.5 virtual void CbcObject::feasibleRegion() [pure virtual]
```

For the variable(s) referenced by the object, look at the current solution and set bounds to match the solution.

Implemented in CbcSimpleInteger, CbcIdiotBranch, CbcClique, CbcSOS, CbcFollowOn, CbcBranchCut, CbcNWay, CbcLotsize, and CbcGeneral.

```
7.79.3.6 virtual double CbcObject::feasibleRegion ( OsiSolverInterface * solver, const OsiBranchingInformation * info ) const [virtual]
```

Dummy one for compatibility.

Reimplemented in CbcSimpleInteger.

```
7.79.3.7 virtual double CbcObject::feasibleRegion ( OsiSolverInterface * solver ) const [virtual]
```

For the variable(s) referenced by the object, look at the current solution and set bounds to match the solution.

Returns measure of how much it had to move solution to make feasible

```
7.79.3.8 virtual CbcBranchingObject* CbcObject::createCbcBranch ( OsiSolverInterface * , const OsiBranchingInformation * , int ) [inline], [virtual]
```

Create a branching object and indicate which way to branch first.

The branching object has to know how to create branches (fix variables, etc.)

Reimplemented in CbcSimpleInteger, CbcIdiotBranch, CbcClique, CbcSOS, CbcBranchToFixLots, CbcSimpleInteger-DynamicPseudoCost, CbcBranchCut, CbcFollowOn, CbcNWay, CbcLotsize, CbcBranchAllDifferent, CbcGeneral, and CbcSimpleIntegerPseudoCost.

Definition at line 137 of file CbcObject.hpp.

```
7.79.3.9 virtual OsiBranchingObject* CbcObject::createBranch ( OsiSolverInterface * , const OsiBranchingInformation * , int ) const [inline], [virtual]
```

Definition at line 144 of file CbcObject.hpp.

```
7.79.3.10 virtual OsiBranchingObject* CbcObject::createOsiBranch ( OsiSolverInterface * solver, const OsiBranchingInformation * info, int way ) const [virtual]
```

Create an Osibranching object and indicate which way to branch first.

The branching object has to know how to create branches (fix variables, etc.)

```
7.79.3.11 virtual OsiSolverBranch* CbcObject::solverBranch( ) const [virtual]
```

Create an OsiSolverBranch object.

This returns NULL if branch not represented by bound changes

Reimplemented in CbcSimpleIntegerDynamicPseudoCost, and CbcSOS.

```
7.79.3.12 virtual CbcBranchingObject* CbcObject::preferredNewFeasible() const [inline],[virtual]
```

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a good direction.

If the method cannot generate a feasible point (because there aren't any, or because it isn't bright enough to find one), it should return null.

Reimplemented in CbcBranchCut, and CbcLotsize.

Definition at line 169 of file CbcObject.hpp.

```
7.79.3.13 virtual CbcBranchingObject* CbcObject::notPreferredNewFeasible( ) const [inline], [virtual]
```

Given a valid solution (with reduced costs, etc.), return a branching object which would give a new feasible point in a bad direction.

If the method cannot generate a feasible point (because there aren't any, or because it isn't bright enough to find one), it should return null.

Reimplemented in CbcBranchCut, and CbcLotsize.

Definition at line 181 of file CbcObject.hpp.

```
7.79.3.14 virtual void CbcObject::resetBounds ( const OsiSolverInterface * ) [inline], [virtual]
```

Reset variable bounds to their original values.

Bounds may be tightened, so it may be good to be able to set this info in object.

Reimplemented in CbcSimpleInteger, and CbcLotsize.

Definition at line 189 of file CbcObject.hpp.

7.79.3.15 virtual void CbcObject::floorCeiling (double & floorValue, double & ceilingValue, double value, double tolerance) const [virtual] Returns floor and ceiling i.e. closest valid points Reimplemented in CbcLotsize. 7.79.3.16 virtual CbcObjectUpdateData CbcObject::createUpdateInformation (const OsiSolverInterface * solver, const CbcNode * node, const CbcBranchingObject * branchingObject) [virtual] Pass in information on branch just done and create CbcObjectUpdateData instance. If object does not need data then backward pointer will be NULL. Assumes can get information from solver Reimplemented in CbcSimpleIntegerDynamicPseudoCost, and CbcSOS. 7.79.3.17 virtual void CbcObject::updateInformation (const CbcObjectUpdateData &) [inline], [virtual] Update object by CbcObjectUpdateData. Reimplemented in CbcSimpleIntegerDynamicPseudoCost, and CbcSOS. Definition at line 204 of file CbcObject.hpp. 7.79.3.18 int CbcObject::id() const [inline] Identifier (normally column number in matrix) Definition at line 207 of file CbcObject.hpp. 7.79.3.19 void CbcObject::setId (int value) [inline] Set identifier (normally column number in matrix) but 1000000000 to 1100000000 means optional branching object i.e. code would work without it Definition at line 214 of file CbcObject.hpp. 7.79.3.20 bool CbcObject::optionalObject() const [inline] Return true if optional branching object i.e. code would work without it Definition at line 220 of file CbcObject.hpp. 7.79.3.21 int CbcObject::position () const [inline] Get position in object list. Definition at line 225 of file CbcObject.hpp. 7.79.3.22 void CbcObject::setPosition (int position) [inline] Set position in object_list. Definition at line 230 of file CbcObject.hpp.

update model

7.79.3.23 void CbcObject::setModel (CbcModel * model) [inline]

```
Definition at line 235 of file CbcObject.hpp.
7.79.3.24 CbcModel* CbcObject::model( )const [inline]
Return model.
Definition at line 240 of file CbcObject.hpp.
7.79.3.25 int CbcObject::preferredWay() const [inline]
If -1 down always chosen first, +1 up always, 0 normal.
Definition at line 245 of file CbcObject.hpp.
7.79.3.26 void CbcObject::setPreferredWay (int value) [inline]
Set -1 down always chosen first, +1 up always, 0 normal.
Definition at line 249 of file CbcObject.hpp.
7.79.3.27 virtual void CbcObject::redoSequenceEtc ( CbcModel * , int , const int * ) [inline], [virtual]
Redoes data when sequence numbers change.
Reimplemented in CbcClique, CbcSOS, CbcBranchToFixLots, CbcNWay, and CbcGeneral.
Definition at line 253 of file CbcObject.hpp.
7.79.3.28 virtual void CbcObject::initializeForBranching ( CbcModel * ) [inline], [virtual]
Initialize for branching.
Reimplemented in CbcldiotBranch.
Definition at line 255 of file CbcObject.hpp.
7.79.4 Member Data Documentation
7.79.4.1 CbcModel* CbcObject::model_ [protected]
data
Model
Definition at line 261 of file CbcObject.hpp.
7.79.4.2 int CbcObject::id_ [protected]
Identifier (normally column number in matrix)
Definition at line 263 of file CbcObject.hpp.
7.79.4.3 int CbcObject::position_ [protected]
Position in object list.
Definition at line 265 of file CbcObject.hpp.
7.79.4.4 int CbcObject::preferredWay_ [protected]
If -1 down always chosen first, +1 up always, 0 normal.
```

Definition at line 267 of file CbcObject.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcObject.hpp

7.80 CbcObjectUpdateData Class Reference

```
#include <CbcObjectUpdateData.hpp>
```

Public Member Functions

CbcObjectUpdateData ()

Default Constructor.

 CbcObjectUpdateData (CbcObject *object, int way, double change, int status, int intDecrease_, double branching-Value)

Useful constructor.

CbcObjectUpdateData (const CbcObjectUpdateData &)

Copy constructor.

CbcObjectUpdateData & operator= (const CbcObjectUpdateData &rhs)

Assignment operator.

virtual ~CbcObjectUpdateData ()

Destructor.

Public Attributes

CbcObject * object_

data

• int way_

Branch as defined by instance of CbcObject.

int objectNumber_

Object number.

double change_

Change in objective.

int status

Status 0 Optimal, 1 infeasible, 2 unknown.

int intDecrease

Decrease in number unsatisfied.

double branchingValue_

Branching value.

· double originalObjective_

Objective value before branching.

double cutoff_

Current cutoff.

7.80.1 Detailed Description

Definition at line 14 of file CbcObjectUpdateData.hpp.

```
7.80.2 Constructor & Destructor Documentation
7.80.2.1 CbcObjectUpdateData::CbcObjectUpdateData()
Default Constructor.
7.80.2.2 CbcObjectUpdateData::CbcObjectUpdateData ( CbcObject * object, int way, double change, int status, int intDecrease_,
        double branchingValue )
Useful constructor.
7.80.2.3 CbcObjectUpdateData::CbcObjectUpdateData ( const CbcObjectUpdateData & )
Copy constructor.
7.80.2.4 virtual CbcObjectUpdateData::~CbcObjectUpdateData() [virtual]
Destructor.
7.80.3
       Member Function Documentation
7.80.3.1 CbcObjectUpdateData& CbcObjectUpdateData & rhs )
Assignment operator.
7.80.4 Member Data Documentation
7.80.4.1 CbcObject* CbcObjectUpdateData::object_
data
Object
Definition at line 43 of file CbcObjectUpdateData.hpp.
7.80.4.2 int CbcObjectUpdateData::way_
Branch as defined by instance of CbcObject.
Definition at line 45 of file CbcObjectUpdateData.hpp.
7.80.4.3 int CbcObjectUpdateData::objectNumber_
Object number.
Definition at line 47 of file CbcObjectUpdateData.hpp.
7.80.4.4 double CbcObjectUpdateData::change_
Change in objective.
Definition at line 49 of file CbcObjectUpdateData.hpp.
7.80.4.5 int CbcObjectUpdateData::status_
Status 0 Optimal, 1 infeasible, 2 unknown.
```

Definition at line 51 of file CbcObjectUpdateData.hpp.

7.80.4.6 int CbcObjectUpdateData::intDecrease_

Decrease in number unsatisfied.

Definition at line 53 of file CbcObjectUpdateData.hpp.

7.80.4.7 double CbcObjectUpdateData::branchingValue_

Branching value.

Definition at line 55 of file CbcObjectUpdateData.hpp.

7.80.4.8 double CbcObjectUpdateData::originalObjective_

Objective value before branching.

Definition at line 57 of file CbcObjectUpdateData.hpp.

7.80.4.9 double CbcObjectUpdateData::cutoff_

Current cutoff.

Definition at line 59 of file CbcObjectUpdateData.hpp.

The documentation for this class was generated from the following file:


• /home/ted/COIN/trunk/Cbc/src/CbcObjectUpdateData.hpp

7.81 CbcOsiParam Class Reference

Class for control parameters that act on a OsiSolverInterface object.

#include <CbcGenOsiParam.hpp>

Inheritance diagram for CbcOsiParam:



Public Types

Subtypes

enum CbcOsiParamCode {
 CBCOSI_FIRSTPARAM = CbcCbcParam::CBCCBC_LASTPARAM + 1, ALGORITHM, ALLSLACK, AUTOS-

```
CALE,
BARRIER, BARRIERSCALE, BASISIN, BASISOUT,
BIASLU, CHOLESKY, CRASH, CROSSOVER,
DUALBOUND, DUALPIVOT, DUALSIMPLEX, DUALTOLERANCE,
FAKEBOUND, GAMMA, IDIOT, KEEPNAMES,
KKT, MAXITERATION, MAXHOTITS, NETLIB_BARRIER,
NETLIB_DUAL, NETLIB_PRIMAL, NETWORK, OBJSCALE,
PERTURBATION, PERTVALUE, PFI, PLUSMINUS,
PRESOLVE, PRESOLVEOPTIONS, PRESOLVEPASS, PRIMALPIVOT,
PRIMALSIMPLEX, PRIMALTOLERANCE, REALLY_SCALE, RESTORE,
REVERSE, RHSSCALE, SAVE, SCALING,
SLPVALUE, SOLVERLOGLEVEL, SPARSEFACTOR, SPECIALOPTIONS,
SPRINT, TIGHTEN, CBCOSI_LASTPARAM }
```

Enumeration for parameters that control an OsiSolverInterface object.

Public Member Functions

Constructors and Destructors

Be careful how you specify parameters for the constructors! There's great potential for confusion.

· CbcOsiParam ()

Default constructor.

 CbcOsiParam (CbcOsiParamCode code, std::string name, std::string help, double lower, double upper, double dflt=0.0, bool display=true)

Constructor for a parameter with a double value.

CbcOsiParam (CbcOsiParamCode code, std::string name, std::string help, int lower, int upper, int dflt=0, bool display=true)

Constructor for a parameter with an integer value.

CbcOsiParam (CbcOsiParamCode code, std::string name, std::string help, std::string firstValue, int dflt, bool display=true)

Constructor for a parameter with keyword values.

- CbcOsiParam (CbcOsiParamCode code, std::string name, std::string help, std::string dflt, bool display=true)

 Constructor for a string parameter.
- CbcOsiParam (CbcOsiParamCode code, std::string name, std::string help, bool display=true)

Constructor for an action parameter.

CbcOsiParam (const CbcOsiParam &orig)

Copy constructor.

CbcOsiParam * clone ()

Clone

CbcOsiParam & operator= (const CbcOsiParam &rhs)

Assignment.

∼CbcOsiParam ()

Destructor.

Methods to query and manipulate a parameter object

CbcOsiParamCode paramCode () const

Get the parameter code.

void setParamCode (CbcOsiParamCode code)

Set the parameter code.

OsiSolverInterface * obj () const

Get the underlying OsiSolverInterface object.

void setObj (OsiSolverInterface *obj)

Set the underlying OsiSolverInterace object.

7.81.1 Detailed Description

Class for control parameters that act on a OsiSolverInterface object.

Adds parameter type codes and push/pull functions to the generic parameter object.

Definition at line 31 of file CbcGenOsiParam.hpp.

7.81.2 Member Enumeration Documentation

7.81.2.1 enum CbcOsiParam::CbcOsiParamCode

Enumeration for parameters that control an OsiSolverInterface object.

These are parameters that control the operation of an OsiSolverInterface object. CBCOSI_FIRSTPARAM and CBCOSI_LASTPARAM are markers to allow convenient separation of parameter groups.

Enumerator

CBCOSI_FIRSTPARAM

ALGORITHM

ALLSLACK

AUTOSCALE

BARRIER

BARRIERSCALE

BASISIN

BASISOUT

BIASLU

CHOLESKY

CRASH

CROSSOVER

DUALBOUND

DUALPIVOT

DUALSIMPLEX

DUALTOLERANCE

FAKEBOUND

GAMMA

IDIOT

KEEPNAMES

KKT

MAXITERATION

MAXHOTITS

NETLIB_BARRIER

NETLIB_DUAL

NETLIB_PRIMAL

NETWORK

OBJSCALE

PERTURBATION

PERTVALUE

PFI

PLUSMINUS

PRESOLVE

PRESOLVEOPTIONS

PRESOLVEPASS

PRIMALPIVOT

PRIMALSIMPLEX

PRIMALTOLERANCE

REALLY_SCALE

RESTORE

REVERSE

RHSSCALE

SAVE

SCALING

SLPVALUE

SOLVERLOGLEVEL

SPARSEFACTOR

SPECIALOPTIONS

SPRINT

TIGHTEN

CBCOSI LASTPARAM

Definition at line 46 of file CbcGenOsiParam.hpp.

7.81.3 Constructor & Destructor Documentation

7.81.3.1 CbcOsiParam::CbcOsiParam()

Default constructor.

7.81.3.2 CbcOsiParam::CbcOsiParam (CbcOsiParamCode code, std::string name, std::string help, double lower, double upper, double dflt = 0 . 0, bool display = true)

Constructor for a parameter with a double value.

The default value is 0.0. Be careful to clearly indicate that lower and upper are real (double) values to distinguish this constructor from the constructor for an integer parameter.

7.81.3.3 CbcOsiParam::CbcOsiParam(CbcOsiParamCode code, std::string name, std::string help, int lower, int upper, int dflt = 0, bool display = true)

Constructor for a parameter with an integer value.

The default value is 0.

7.81.3.4 CbcOsiParam::CbcOsiParam(CbcOsiParamCode code, std::string name, std::string help, std::string firstValue, int dflt. bool display = true)

Constructor for a parameter with keyword values.

The string supplied as firstValue becomes the first keyword. Additional keywords can be added using append-Kwd(). Keywords are numbered from zero. It's necessary to specify both the first keyword (firstValue) and the default keyword index (dflt) in order to distinguish this constructor from the string and action parameter constructors.

7.81.3.5 CbcOsiParam:CbcOsiParam (CbcOsiParamCode code, std::string name, std::string help, std::string dflt, bool display = true)

Constructor for a string parameter.

The default string value must be specified explicitly to distinguish a string constructor from an action parameter constructor.

7.81.3.6 CbcOsiParam::CbcOsiParam (CbcOsiParamCode code, std::string name, std::string help, bool display = true)

Constructor for an action parameter.

7.81.3.7 CbcOsiParam::CbcOsiParam (const CbcOsiParam & orig)

Copy constructor.

7.81.3.8 CbcOsiParam::~CbcOsiParam()

Destructor.

7.81.4 Member Function Documentation

7.81.4.1 CbcOsiParam * CbcOsiParam::clone ()

Clone.

7.81.4.2 CbcOsiParam& CbcOsiParam::operator= (const CbcOsiParam & rhs)

Assignment.

7.81.4.3 CbcOsiParamCode CbcOsiParam::paramCode () const [inline]

Get the parameter code.

Definition at line 141 of file CbcGenOsiParam.hpp.

7.81.4.4 void CbcOsiParam::setParamCode (CbcOsiParamCode code) [inline]

Set the parameter code.

Definition at line 147 of file CbcGenOsiParam.hpp.

7.81.4.5 OsiSolverInterface* CbcOsiParam::obj() const [inline]

Get the underlying OsiSolverInterface object.

Definition at line 153 of file CbcGenOsiParam.hpp.

7.81.4.6 void CbcOsiParam::setObj (OsiSolverInterface * obj) [inline]

Set the underlying OsiSolverInterace object.

Definition at line 159 of file CbcGenOsiParam.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcGenOsiParam.hpp

7.82 CbcOsiSolver Class Reference

This is for codes where solver needs to know about CbcModel Seems to provide only one value-added feature, a CbcModel object.

```
#include <CbcFathom.hpp>
```

Inheritance diagram for CbcOsiSolver:



Public Member Functions

Constructors and destructors

CbcOsiSolver ()

Default Constructor.

- virtual OsiSolverInterface * clone (bool copyData=true) const Clone.
- CbcOsiSolver (const CbcOsiSolver &)

Copy constructor.

• CbcOsiSolver & operator= (const CbcOsiSolver &rhs)

Assignment operator.

virtual ∼CbcOsiSolver ()

Destructor.

Sets and Gets

void setCbcModel (CbcModel *model)

Set Cbc Model.

• CbcModel * cbcModel () const

Return Cbc Model.

Protected Attributes

Private member data

CbcModel * cbcModel

Pointer back to CbcModel.

7.82.1 Detailed Description

This is for codes where solver needs to know about CbcModel Seems to provide only one value-added feature, a CbcModel object.

Definition at line 90 of file CbcFathom.hpp.

```
7.82.2 Constructor & Destructor Documentation
```

7.82.2.1 CbcOsiSolver::CbcOsiSolver()

Default Constructor.

7.82.2.2 CbcOsiSolver::CbcOsiSolver (const CbcOsiSolver &)

Copy constructor.

7.82.2.3 virtual CbcOsiSolver::~CbcOsiSolver() [virtual]

Destructor.

7.82.3 Member Function Documentation

7.82.3.1 virtual OsiSolverInterface* CbcOsiSolver::clone (bool copyData = true) const [virtual]

Clone.

Reimplemented in OsiSolverLink.

7.82.3.2 CbcOsiSolver& CbcOsiSolver::operator= (const CbcOsiSolver & rhs)

Assignment operator.

7.82.3.3 void CbcOsiSolver::setCbcModel (CbcModel * model) [inline]

Set Cbc Model.

Definition at line 117 of file CbcFathom.hpp.

7.82.3.4 CbcModel* CbcOsiSolver::cbcModel()const [inline]

Return Cbc Model.

Definition at line 121 of file CbcFathom.hpp.

7.82.4 Member Data Documentation

7.82.4.1 CbcModel* CbcOsiSolver::cbcModel [protected]

Pointer back to CbcModel.

Definition at line 134 of file CbcFathom.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcFathom.hpp

7.83 CbcParam Class Reference

Very simple class for setting parameters.

```
#include <CbcParam.hpp>
```

Public Member Functions

Constructor and destructor

• CbcParam ()

Constructors.

- CbcParam (std::string name, std::string help, double lower, double upper, CbcParameterType type, bool display=true)
- CbcParam (std::string name, std::string help, int lower, int upper, CbcParameterType type, bool display=true)
- CbcParam (std::string name, std::string help, std::string firstValue, CbcParameterType type, int defaultIndex=0, bool display=true)
- CbcParam (std::string name, std::string help, CbcParameterType type, int indexNumber=-1, bool display=true)
- CbcParam (const CbcParam &)

Copy constructor.

CbcParam & operator= (const CbcParam &rhs)

Assignment operator. This copies the data.

∼CbcParam ()

Destructor.

stuff

void append (std::string keyWord)

Insert string (only valid for keywords)

void addHelp (std::string keyWord)

Adds one help line.

• std::string name () const

Returns name.

• std::string shortHelp () const

Returns short help.

• int setDoubleParameter (CbcModel &model, double value) const

Sets a double parameter (nonzero code if error)

double doubleParameter (CbcModel &model) const

Gets a double parameter.

• int setIntParameter (CbcModel &model, int value) const

Sets a int parameter (nonzero code if error)

• int intParameter (CbcModel &model) const

Gets a int parameter.

• int setDoubleParameter (ClpSimplex *model, double value) const

Sets a double parameter (nonzero code if error)

double doubleParameter (ClpSimplex *model) const

Gets a double parameter.

• int setIntParameter (ClpSimplex *model, int value) const

Sets a int parameter (nonzero code if error)

int intParameter (ClpSimplex *model) const

Gets a int parameter.

• int setDoubleParameter (OsiSolverInterface *model, double value) const

Sets a double parameter (nonzero code if error)

• double doubleParameter (OsiSolverInterface *model) const

Gets a double parameter.

• int setIntParameter (OsiSolverInterface *model, int value) const

Sets a int parameter (nonzero code if error)

• int intParameter (OsiSolverInterface *model) const

Gets a int parameter.

int checkDoubleParameter (double value) const

Checks a double parameter (nonzero code if error)

• std::string matchName () const

Returns name which could match.

• int parameterOption (std::string check) const

Returns parameter option which matches (-1 if none)

void printOptions () const

Prints parameter options.

std::string currentOption () const

Returns current parameter option.

void setCurrentOption (int value)

Sets current parameter option.

· void setIntValue (int value)

Sets int value.

- int intValue () const
- void setDoubleValue (double value)

Sets double value.

- double doubleValue () const
- void setStringValue (std::string value)

Sets string value.

- std::string stringValue () const
- int matches (std::string input) const

Returns 1 if matches minimum, 2 if matches less, 0 if not matched.

CbcParameterType type () const

type

bool displayThis () const

whether to display

void setLonghelp (const std::string help)

Set Long help.

void printLongHelp () const

Print Long help.

· void printString () const

Print action and string.

• int indexNumber () const

type for classification

```
7.83.1 Detailed Description
Very simple class for setting parameters.
Definition at line 153 of file CbcParam.hpp.
7.83.2 Constructor & Destructor Documentation
7.83.2.1 CbcParam::CbcParam()
Constructors.
7.83.2.2 CbcParam::CbcParam ( std::string name, std::string help, double lower, double upper, CbcParameterType type, bool
         display = true )
7.83.2.3 CbcParam::CbcParam ( std::string name, std::string help, int lower, int upper, CbcParameterType type, bool display =
         true )
7.83.2.4 CbcParam::CbcParam ( std::string name, std::string help, std::string firstValue, CbcParameterType type, int
         defaultIndex = 0, bool display = true )
7.83.2.5 CbcParam::CbcParam ( std::string name, std::string help, CbcParameterType type, int indexNumber = -1, bool
         display = true )
7.83.2.6 CbcParam::CbcParam ( const CbcParam & )
Copy constructor.
7.83.2.7 CbcParam::~CbcParam()
Destructor.
7.83.3 Member Function Documentation
7.83.3.1 CbcParam& CbcParam::operator= ( const CbcParam & rhs )
Assignment operator. This copies the data.
7.83.3.2 void CbcParam::append ( std::string keyWord )
Insert string (only valid for keywords)
7.83.3.3 void CbcParam::addHelp ( std::string keyWord )
Adds one help line.
7.83.3.4 std::string CbcParam::name() const [inline]
Returns name.
Definition at line 186 of file CbcParam.hpp.
7.83.3.5 std::string CbcParam::shortHelp() const [inline]
Returns short help.
```

Definition at line 190 of file CbcParam.hpp.

7.83.3.6 int CbcParam::setDoubleParameter (CbcModel & model, double value) const

Sets a double parameter (nonzero code if error)

7.83.3.7 double CbcParam::doubleParameter (CbcModel & model) const

Gets a double parameter.

7.83.3.8 int CbcParam::setIntParameter (CbcModel & model, int value) const

Sets a int parameter (nonzero code if error)

7.83.3.9 int CbcParam::intParameter (CbcModel & model) const

Gets a int parameter.

7.83.3.10 int CbcParam::setDoubleParameter (ClpSimplex * model, double value) const

Sets a double parameter (nonzero code if error)

7.83.3.11 double CbcParam::doubleParameter (ClpSimplex * model) const

Gets a double parameter.

7.83.3.12 int CbcParam::setIntParameter (ClpSimplex * model, int value) const

Sets a int parameter (nonzero code if error)

7.83.3.13 int CbcParam::intParameter (ClpSimplex * model) const

Gets a int parameter.

7.83.3.14 int CbcParam::setDoubleParameter (OsiSolverInterface * model, double value) const

Sets a double parameter (nonzero code if error)

7.83.3.15 double CbcParam::doubleParameter (OsiSolverInterface * model) const

Gets a double parameter.

7.83.3.16 int CbcParam::setIntParameter (OsiSolverInterface * model, int value) const

Sets a int parameter (nonzero code if error)

7.83.3.17 int CbcParam::intParameter (OsiSolverInterface * model) const

Gets a int parameter.

7.83.3.18 int CbcParam::checkDoubleParameter (double value) const

Checks a double parameter (nonzero code if error)

7.83.3.19 std::string CbcParam::matchName () const

Returns name which could match.

```
7.83.3.20 int CbcParam::parameterOption ( std::string check ) const
Returns parameter option which matches (-1 if none)
7.83.3.21 void CbcParam::printOptions ( ) const
Prints parameter options.
7.83.3.22 std::string CbcParam::currentOption ( ) const [inline]
Returns current parameter option.
Definition at line 226 of file CbcParam.hpp.
7.83.3.23 void CbcParam::setCurrentOption (int value) [inline]
Sets current parameter option.
Definition at line 230 of file CbcParam.hpp.
7.83.3.24 void CbcParam::setIntValue (int value) [inline]
Sets int value.
Definition at line 234 of file CbcParam.hpp.
7.83.3.25 int CbcParam::intValue ( ) const [inline]
Definition at line 237 of file CbcParam.hpp.
7.83.3.26 void CbcParam::setDoubleValue ( double value ) [inline]
Sets double value.
Definition at line 241 of file CbcParam.hpp.
7.83.3.27 double CbcParam::doubleValue() const [inline]
Definition at line 244 of file CbcParam.hpp.
7.83.3.28 void CbcParam::setStringValue ( std::string value ) [inline]
Sets string value.
Definition at line 248 of file CbcParam.hpp.
7.83.3.29 std::string CbcParam::stringValue ( ) const [inline]
Definition at line 251 of file CbcParam.hpp.
7.83.3.30 int CbcParam::matches ( std::string input ) const
Returns 1 if matches minimum, 2 if matches less, 0 if not matched.
7.83.3.31 CbcParameterType CbcParam::type() const [inline]
type
Definition at line 257 of file CbcParam.hpp.
```

```
7.83.3.32 bool CbcParam::displayThis ( ) const [inline]
whether to display
Definition at line 261 of file CbcParam.hpp.
7.83.3.33 void CbcParam::setLonghelp ( const std::string help ) [inline]
Set Long help.
Definition at line 265 of file CbcParam.hpp.
7.83.3.34 void CbcParam::printLongHelp ( ) const
Print Long help.
7.83.3.35 void CbcParam::printString ( ) const
Print action and string.
7.83.3.36 int CbcParam::indexNumber ( ) const [inline]
type for classification
Definition at line 273 of file CbcParam.hpp.
```

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcParam.hpp

7.84 CbcGenCtlBlk::cbcParamsInfo_struct Struct Reference

Start and end of CbcModel parameters in parameter vector.

```
#include <CbcGenCtlBlk.hpp>
```

Public Attributes

- int first_
- int last_

7.84.1 Detailed Description

Start and end of CbcModel parameters in parameter vector.

Definition at line 605 of file CbcGenCtlBlk.hpp.

7.84.2 Member Data Documentation

7.84.2.1 int CbcGenCtlBlk::cbcParamsInfo_struct::first_

Definition at line 606 of file CbcGenCtlBlk.hpp.

7.84.2.2 int CbcGenCtlBlk::cbcParamsInfo_struct::last_

Definition at line 607 of file CbcGenCtlBlk.hpp.

The documentation for this struct was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcGenCtlBlk.hpp

7.85 CbcPartialNodeInfo Class Reference

Holds information for recreating a subproblem by incremental change from the parent.

#include <CbcPartialNodeInfo.hpp>

Inheritance diagram for CbcPartialNodeInfo:



Public Member Functions

 virtual void applyToModel (CbcModel *model, CoinWarmStartBasis *&basis, CbcCountRowCut **addCuts, int ¤tNumberCuts) const

Modify model according to information at node.

virtual int applyBounds (int iColumn, double &lower, double &upper, int force)

Just apply bounds to one variable - force means overwrite by lower,upper (1=>infeasible)

• virtual CbcNodeInfo * buildRowBasis (CoinWarmStartBasis &basis) const

Builds up row basis backwards (until original model).

- CbcPartialNodeInfo ()
- CbcPartialNodeInfo (CbcNodeInfo *parent, CbcNode *owner, int numberChangedBounds, const int *variables, const double *boundChanges, const CoinWarmStartDiff *basisDiff)
- CbcPartialNodeInfo (const CbcPartialNodeInfo &)
- ∼CbcPartialNodeInfo ()
- virtual CbcNodeInfo * clone () const

Clone

const CoinWarmStartDiff * basisDiff () const

Basis diff information.

const int * variables () const

Which variable (top bit if upper bound changing)

- const double * newBounds () const
- int numberChangedBounds () const

Number of bound changes.

Protected Attributes

CoinWarmStartDiff * basisDiff

Basis diff information.

int * variables_

Which variable (top bit if upper bound changing)

- double * newBounds
- int numberChangedBounds

Number of bound changes.

7.85.1 Detailed Description

Holds information for recreating a subproblem by incremental change from the parent.

A CbcPartialNodeInfo object contains changes to the bounds and basis, and additional cuts, required to recreate a subproblem by modifying and augmenting the parent subproblem.

Definition at line 39 of file CbcPartialNodeInfo.hpp.

```
7.85.2 Constructor & Destructor Documentation
```

```
7.85.2.1 CbcPartialNodeInfo::CbcPartialNodeInfo()
```

7.85.2.2 CbcPartialNodeInfo::CbcPartialNodeInfo (CbcNodeInfo * parent, CbcNode * owner, int numberChangedBounds, const int * variables, const double * boundChanges, const CoinWarmStartDiff * basisDiff)

```
7.85.2.3 CbcPartialNodeInfo::CbcPartialNodeInfo ( const CbcPartialNodeInfo & )
```

```
7.85.2.4 CbcPartialNodeInfo:: ~ CbcPartialNodeInfo ( )
```

7.85.3 Member Function Documentation

```
7.85.3.1 virtual void CbcPartialNodeInfo::applyToModeI ( CbcModeI * modeI, CoinWarmStartBasis *& basis, CbcCountRowCut ** addCuts, int & currentNumberCuts ) const [virtual]
```

Modify model according to information at node.

The routine modifies the model according to bound and basis change information at node and adds any cuts to the addCuts array.

Implements CbcNodeInfo.

```
7.85.3.2 virtual int CbcPartialNodelnfo::applyBounds (int iColumn, double & lower, double & upper, int force ) [virtual]
```

Just apply bounds to one variable - force means overwrite by lower,upper (1=>infeasible)

Implements CbcNodeInfo.

```
7.85.3.3 virtual CbcNodeInfo* CbcPartialNodeInfo::buildRowBasis ( CoinWarmStartBasis & basis ) const [virtual]
```

Builds up row basis backwards (until original model).

Returns NULL or previous one to apply . Depends on Free being 0 and impossible for cuts

Implements CbcNodeInfo.

```
7.85.3.4 virtual CbcNodeInfo* CbcPartialNodeInfo::clone() const [virtual]
```

Clone.

Implements CbcNodeInfo.

```
7.85.3.5 const CoinWarmStartDiff* CbcPartialNodeInfo::basisDiff() const [inline]
```

Basis diff information.

Definition at line 77 of file CbcPartialNodeInfo.hpp.

7.85.3.6 const int* CbcPartialNodeInfo::variables () const [inline]

Which variable (top bit if upper bound changing)

Definition at line 81 of file CbcPartialNodeInfo.hpp.

7.85.3.7 const double* CbcPartialNodeInfo::newBounds () const [inline]

Definition at line 85 of file CbcPartialNodeInfo.hpp.

7.85.3.8 int CbcPartialNodeInfo::numberChangedBounds () const [inline]

Number of bound changes.

Definition at line 89 of file CbcPartialNodeInfo.hpp.

7.85.4 Member Data Documentation

7.85.4.1 CoinWarmStartDiff* CbcPartialNodeInfo::basisDiff_ [protected]

Basis diff information.

Definition at line 96 of file CbcPartialNodeInfo.hpp.

7.85.4.2 int* CbcPartialNodeInfo::variables_ [protected]

Which variable (top bit if upper bound changing)

Definition at line 98 of file CbcPartialNodeInfo.hpp.

7.85.4.3 double* CbcPartialNodeInfo::newBounds_ [protected]

Definition at line 100 of file CbcPartialNodeInfo.hpp.

7.85.4.4 int CbcPartialNodeInfo::numberChangedBounds_ [protected]

Number of bound changes.

Definition at line 102 of file CbcPartialNodeInfo.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcPartialNodeInfo.hpp

7.86 CbcRounding Class Reference

Rounding class.

#include <CbcHeuristic.hpp>

Inheritance diagram for CbcRounding:



Public Member Functions

- CbcRounding ()
- CbcRounding (CbcModel &model)
- CbcRounding (const CbcRounding &)
- ∼CbcRounding ()
- CbcRounding & operator= (const CbcRounding &rhs)

Assignment operator.

• virtual CbcHeuristic * clone () const

Clone.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

virtual void setModel (CbcModel *model)

update model (This is needed if cliques update matrix etc)

• virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value (only if good) This is called after cuts have been added - so can not add cuts

virtual int solution (double &objectiveValue, double *newSolution, double solutionValue)

returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value (only if good) This is called after cuts have been added - so can not add cuts Use solutionValue rather than solvers one

virtual void validate ()

Validate model i.e. sets when to 0 if necessary (may be NULL)

void setSeed (int value)

Set seed.

Protected Attributes

- CoinPackedMatrix matrix_
- CoinPackedMatrix matrixByRow
- unsigned short * down
- unsigned short * up_
- unsigned short * equal_
- int seed

7.86.1 Detailed Description

Rounding class.

Definition at line 407 of file CbcHeuristic.hpp.

7.86.2 Constructor & Destructor Documentation

7.86.2.1 CbcRounding::CbcRounding()

7.86.2.2 CbcRounding::CbcRounding (CbcModel & model)

```
CbcRounding::CbcRounding ( const CbcRounding & )
7.86.2.3
7.86.2.4 CbcRounding::~CbcRounding()
7.86.3 Member Function Documentation
7.86.3.1 CbcRounding& CbcRounding::operator= ( const CbcRounding & rhs )
Assignment operator.
7.86.3.2 virtual CbcHeuristic* CbcRounding::clone( ) const [virtual]
Clone.
Implements CbcHeuristic.
7.86.3.3 virtual void CbcRounding::generateCpp (FILE * fp ) [virtual]
Create C++ lines to get to current state.
Reimplemented from CbcHeuristic.
7.86.3.4 virtual void CbcRounding::resetModel ( CbcModel * model ) [virtual]
Resets stuff if model changes.
Implements CbcHeuristic.
7.86.3.5 virtual void CbcRounding::setModel ( CbcModel * model ) [virtual]
update model (This is needed if cliques update matrix etc)
Reimplemented from CbcHeuristic.
7.86.3.6 virtual int CbcRounding::solution ( double & objective Value, double * new Solution ) [virtual]
returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets
objective value (only if good) This is called after cuts have been added - so can not add cuts
Implements CbcHeuristic.
7.86.3.7 virtual int CbcRounding::solution ( double & objectiveValue, double * newSolution, double solutionValue )
         [virtual]
returns 0 if no solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets
objective value (only if good) This is called after cuts have been added - so can not add cuts Use solutionValue rather
than solvers one
7.86.3.8 virtual void CbcRounding::validate() [virtual]
Validate model i.e. sets when to 0 if necessary (may be NULL)
Reimplemented from CbcHeuristic.
7.86.3.9 void CbcRounding::setSeed (int value) [inline]
Set seed.
Definition at line 458 of file CbcHeuristic.hpp.
```

7.86.4 Member Data Documentation

7.86.4.1 CoinPackedMatrix CbcRounding::matrix [protected]

Definition at line 466 of file CbcHeuristic.hpp.

7.86.4.2 CoinPackedMatrix CbcRounding::matrixByRow_ [protected]

Definition at line 469 of file CbcHeuristic.hpp.

7.86.4.3 unsigned short* CbcRounding::down [protected]

Definition at line 472 of file CbcHeuristic.hpp.

7.86.4.4 unsigned short* CbcRounding::up_ [protected]

Definition at line 475 of file CbcHeuristic.hpp.

7.86.4.5 unsigned short* CbcRounding::equal_ [protected]

Definition at line 478 of file CbcHeuristic.hpp.

7.86.4.6 int CbcRounding::seed_ [protected]

Definition at line 481 of file CbcHeuristic.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcHeuristic.hpp

7.87 CbcRowCuts Class Reference

#include <CbcCountRowCut.hpp>

Public Member Functions

- CbcRowCuts (int initialMaxSize=0, int hashMultiplier=4)
- ∼CbcRowCuts ()
- CbcRowCuts (const CbcRowCuts &rhs)
- CbcRowCuts & operator= (const CbcRowCuts &rhs)
- OsiRowCut2 * cut (int sequence) const
- int numberCuts () const
- int sizeRowCuts () const
- OsiRowCut * rowCutPtr (int sequence)
- void eraseRowCut (int sequence)
- int addCutIfNotDuplicate (const OsiRowCut &cut, int whichType=0)
- int addCutIfNotDuplicateWhenGreedy (const OsiRowCut &cut, int whichType=0)
- void addCuts (OsiCuts &cs)

7.87.1 Detailed Description

Definition at line 134 of file CbcCountRowCut.hpp.

```
7.87.2 Constructor & Destructor Documentation
7.87.2.1 CbcRowCuts::CbcRowCuts (int initialMaxSize = 0, int hashMultiplier = 4)
7.87.2.2 CbcRowCuts::~CbcRowCuts()
7.87.2.3 CbcRowCuts::CbcRowCuts ( const CbcRowCuts & rhs )
7.87.3 Member Function Documentation
7.87.3.1 CbcRowCuts& CbcRowCuts::operator= ( const CbcRowCuts & rhs )
7.87.3.2 OsiRowCut2* CbcRowCuts::cut ( int sequence ) const [inline]
Definition at line 141 of file CbcCountRowCut.hpp.
7.87.3.3 int CbcRowCuts::numberCuts ( ) const [inline]
Definition at line 143 of file CbcCountRowCut.hpp.
7.87.3.4 int CbcRowCuts::sizeRowCuts ( ) const [inline]
Definition at line 145 of file CbcCountRowCut.hpp.
7.87.3.5 OsiRowCut* CbcRowCuts::rowCutPtr(int sequence) [inline]
Definition at line 147 of file CbcCountRowCut.hpp.
7.87.3.6 void CbcRowCuts::eraseRowCut (int sequence)
7.87.3.7 int CbcRowCuts::addCutlfNotDuplicate ( const OsiRowCut & cut, int whichType = 0 )
7.87.3.8 int CbcRowCuts::addCutlfNotDuplicateWhenGreedy ( const OsiRowCut & cut, int whichType = 0 )
7.87.3.9 void CbcRowCuts::addCuts (OsiCuts & cs)
```

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcCountRowCut.hpp

7.88 CbcSerendipity Class Reference

heuristic - just picks up any good solution found by solver - see OsiBabSolver

#include <CbcHeuristic.hpp>

Inheritance diagram for CbcSerendipity:



Public Member Functions

- CbcSerendipity ()
- CbcSerendipity (CbcModel &model)
- CbcSerendipity (const CbcSerendipity &)
- ∼CbcSerendipity ()
- CbcSerendipity & operator= (const CbcSerendipity &rhs)

Assignment operator.

• virtual CbcHeuristic * clone () const

Clone

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

virtual void setModel (CbcModel *model)

update model

virtual int solution (double &objectiveValue, double *newSolution)

returns 0 if no solution, 1 if valid solution.

virtual void resetModel (CbcModel *model)

Resets stuff if model changes.

Additional Inherited Members

7.88.1 Detailed Description

heuristic - just picks up any good solution found by solver - see OsiBabSolver

Definition at line 552 of file CbcHeuristic.hpp.

```
7.88.2 Constructor & Destructor Documentation
```

```
7.88.2.1 CbcSerendipity::CbcSerendipity ( )
```

- 7.88.2.2 CbcSerendipity::CbcSerendipity (CbcModel & model)
- 7.88.2.3 CbcSerendipity::CbcSerendipity (const CbcSerendipity &)
- 7.88.2.4 CbcSerendipity::~CbcSerendipity ()
- 7.88.3 Member Function Documentation
- 7.88.3.1 CbcSerendipity& CbcSerendipity::operator= (const CbcSerendipity & rhs)

Assignment operator.

```
7.88.3.2 virtual CbcHeuristic* CbcSerendipity::clone ( ) const [virtual]
```

Clone.

Implements CbcHeuristic.

7.88.3.3 virtual void CbcSerendipity::generateCpp (FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcHeuristic.

7.88.3.4 virtual void CbcSerendipity::setModel (CbcModel * model) [virtual]

update model

Reimplemented from CbcHeuristic.

7.88.3.5 virtual int CbcSerendipity::solution (double & objectiveValue, double * newSolution) [virtual]

returns 0 if no solution, 1 if valid solution.

Sets solution values if good, sets objective value (only if good) We leave all variables which are at one at this node of the tree to that value and will initially set all others to zero. We then sort all variables in order of their cost divided by the number of entries in rows which are not yet covered. We randomize that value a bit so that ties will be broken in different ways on different runs of the heuristic. We then choose the best one and set it to one and repeat the exercise.

Implements CbcHeuristic.

7.88.3.6 virtual void CbcSerendipity::resetModel (CbcModel * model) [virtual]

Resets stuff if model changes.

Implements CbcHeuristic.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcHeuristic.hpp

7.89 CbcSimpleInteger Class Reference

Define a single integer class.

#include <CbcSimpleInteger.hpp>

Inheritance diagram for CbcSimpleInteger:



Public Member Functions

- CbcSimpleInteger ()
- CbcSimpleInteger (CbcModel *model, int iColumn, double breakEven=0.5)
- CbcSimpleInteger (CbcModel *model, const OsiSimpleInteger *object)
- CbcSimpleInteger (const CbcSimpleInteger &)
- virtual CbcObject * clone () const

Clone

- CbcSimpleInteger & operator= (const CbcSimpleInteger &rhs)
- virtual ∼CbcSimpleInteger ()

OsiSimpleInteger * osiObject () const

Construct an OsiSimpleInteger object.

virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const

Infeasibility - large is 0.5.

 $\bullet \ \ virtual \ double \ feasible Region \ (OsiSolverInterface \ *solver, \ const \ OsiBranchingInformation \ *info) \ const$

Set bounds to fix the variable at the current (integer) value.

virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Create a branching object and indicate which way to branch first.

void fillCreateBranch (CbcIntegerBranchingObject *branching, const OsiBranchingInformation *info, int way)

Fills in a created branching object.

 $\bullet \ \, \text{virtual OsiSolverBranch} * solverBranch (OsiSolverInterface * solver, const OsiBranchingInformation * info) const (OsiSolverBranch * solverBranch * solverBranc$

Create an OsiSolverBranch object.

virtual void feasibleRegion ()

Set bounds to fix the variable at the current (integer) value.

virtual int columnNumber () const

Column number if single column object -1 otherwise, so returns >= 0 Used by heuristics.

void setColumnNumber (int value)

Set column number.

virtual void resetBounds (const OsiSolverInterface *solver)

Reset variable bounds to their original values.

virtual void resetSequenceEtc (int numberColumns, const int *originalColumns)

Change column numbers after preprocessing.

· double originalLowerBound () const

Original bounds.

- void setOriginalLowerBound (double value)
- double originalUpperBound () const
- void setOriginalUpperBound (double value)
- double breakEven () const

Breakeven e.g 0.7 ->> = 0.7 go up first.

void setBreakEven (double value)

Set breakeven e.g 0.7 ->> = 0.7 go up first.

Protected Attributes

double originalLower_

data

double originalUpper_

Original upper bound.

· double breakEven_

Breakeven i.e. >= this preferred is up.

int columnNumber_

Column number in model.

int preferredWay_

If -1 down always chosen first, +1 up always, 0 normal.

7.89.1 Detailed Description

Define a single integer class.

Definition at line 167 of file CbcSimpleInteger.hpp.

```
7.89.2 Constructor & Destructor Documentation
```

```
7.89.2.1 CbcSimpleInteger::CbcSimpleInteger ( )
```

```
7.89.2.2 CbcSimpleInteger::CbcSimpleInteger ( CbcModel * model, int iColumn, double breakEven = 0 . 5 )
```

```
7.89.2.3 CbcSimpleInteger::CbcSimpleInteger ( CbcModel * model, const OsiSimpleInteger * object )
```

7.89.2.4 CbcSimpleInteger::CbcSimpleInteger (const CbcSimpleInteger &)

```
7.89.2.5 virtual CbcSimpleInteger::~CbcSimpleInteger() [virtual]
```

7.89.3 Member Function Documentation

```
7.89.3.1 virtual CbcObject* CbcSimpleInteger::clone( )const [virtual]
```

Clone.

Implements CbcObject.

Reimplemented in CbcSimpleIntegerDynamicPseudoCost, and CbcSimpleIntegerPseudoCost.

7.89.3.2 CbcSimpleInteger & CbcSimpleInteger::operator= (const CbcSimpleInteger & rhs)

```
7.89.3.3 OsiSimpleInteger* CbcSimpleInteger::osiObject ( ) const
```

Construct an OsiSimpleInteger object.

7.89.3.4 virtual double CbcSimpleInteger::infeasibility (const OsiBranchingInformation * info, int & preferredWay) const [virtual]

Infeasibility - large is 0.5.

Reimplemented from CbcObject.

Reimplemented in CbcSimpleIntegerDynamicPseudoCost, and CbcSimpleIntegerPseudoCost.

```
7.89.3.5 virtual double CbcSimpleInteger::feasibleRegion (OsiSolverInterface * solver, const OsiBranchingInformation * info ) const [virtual]
```

Set bounds to fix the variable at the current (integer) value.

Given an integer value, set the lower and upper bounds to fix the variable. Returns amount it had to move variable.

Reimplemented from CbcObject.

```
7.89.3.6 virtual CbcBranchingObject* CbcSimpleInteger::createCbcBranch ( OsiSolverInterface * solver, const OsiBranchingInformation * info, int way ) [virtual]
```

Create a branching object and indicate which way to branch first.

The branching object has to know how to create branches (fix variables, etc.)

Reimplemented from CbcObject.

Reimplemented in CbcSimpleIntegerDynamicPseudoCost, and CbcSimpleIntegerPseudoCost.

7.89.3.7 void CbcSimpleInteger::fillCreateBranch (CbcIntegerBranchingObject * branching, const OsiBranchingInformation * info, int way)

Fills in a created branching object.

7.89.3.8 virtual OsiSolverBranch* CbcSimpleInteger::solverBranch (OsiSolverInterface * solver, const OsiBranchingInformation * info) const [virtual]

Create an OsiSolverBranch object.

This returns NULL if branch not represented by bound changes

7.89.3.9 virtual void CbcSimpleInteger::feasibleRegion() [virtual]

Set bounds to fix the variable at the current (integer) value.

Given an integer value, set the lower and upper bounds to fix the variable. The algorithm takes a bit of care in order to compensate for minor numerical inaccuracy.

Implements CbcObject.

7.89.3.10 virtual int CbcSimpleInteger::columnNumber() const [virtual]

Column number if single column object -1 otherwise, so returns >= 0 Used by heuristics.

7.89.3.11 void CbcSimpleInteger::setColumnNumber(int value) [inline]

Set column number.

Definition at line 235 of file CbcSimpleInteger.hpp.

7.89.3.12 virtual void CbcSimpleInteger::resetBounds (const OsiSolverInterface * solver) [virtual]

Reset variable bounds to their original values.

Bounds may be tightened, so it may be good to be able to set this info in object.

Reimplemented from CbcObject.

7.89.3.13 virtual void CbcSimpleInteger::resetSequenceEtc (int numberColumns, const int * originalColumns) [virtual]

Change column numbers after preprocessing.

7.89.3.14 double CbcSimpleInteger::originalLowerBound () const [inline]

Original bounds.

Definition at line 249 of file CbcSimpleInteger.hpp.

7.89.3.15 void CbcSimpleInteger::setOriginalLowerBound (double value) [inline]

Definition at line 252 of file CbcSimpleInteger.hpp.

7.89.3.16 double CbcSimpleInteger::originalUpperBound() const [inline]

Definition at line 255 of file CbcSimpleInteger.hpp.

7.89.3.17 void CbcSimpleInteger::setOriginalUpperBound (double value) [inline] Definition at line 258 of file CbcSimpleInteger.hpp. 7.89.3.18 double CbcSimpleInteger::breakEven() const [inline] Breakeven e.g 0.7 ->> = 0.7 go up first. Definition at line 262 of file CbcSimpleInteger.hpp. 7.89.3.19 void CbcSimpleInteger::setBreakEven (double value) [inline] Set breakeven e.g 0.7 ->> = 0.7 go up first. Definition at line 266 of file CbcSimpleInteger.hpp. 7.89.4 Member Data Documentation **7.89.4.1 double CbcSimpleInteger::originalLower** [protected] data Original lower bound Definition at line 275 of file CbcSimpleInteger.hpp. 7.89.4.2 double CbcSimpleInteger::originalUpper_ [protected] Original upper bound. Definition at line 277 of file CbcSimpleInteger.hpp. **7.89.4.3 double CbcSimpleInteger::breakEven** [protected]

Breakeven i.e. >= this preferred is up.

Definition at line 279 of file CbcSimpleInteger.hpp.

7.89.4.4 int CbcSimpleInteger::columnNumber_ [protected]

Column number in model.

Definition at line 281 of file CbcSimpleInteger.hpp.

7.89.4.5 int CbcSimpleInteger::preferredWay_ [protected]

If -1 down always chosen first, +1 up always, 0 normal.

Definition at line 283 of file CbcSimpleInteger.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcSimpleInteger.hpp

7.90 CbcSimpleIntegerDynamicPseudoCost Class Reference

Define a single integer class but with dynamic pseudo costs.

#include <CbcSimpleIntegerDynamicPseudoCost.hpp>

Inheritance diagram for CbcSimpleIntegerDynamicPseudoCost:



Public Member Functions

- CbcSimpleIntegerDynamicPseudoCost ()
- CbcSimpleIntegerDynamicPseudoCost (CbcModel *model, int iColumn, double breakEven=0.5)
- CbcSimpleIntegerDynamicPseudoCost (CbcModel *model, int iColumn, double downDynamicPseudoCost, double upDynamicPseudoCost)
- CbcSimpleIntegerDynamicPseudoCost (CbcModel *model, int dummy, int iColumn, double downDynamic-PseudoCost, double upDynamicPseudoCost)
- CbcSimpleIntegerDynamicPseudoCost (const CbcSimpleIntegerDynamicPseudoCost &)
- virtual CbcObject * clone () const

Clone

- CbcSimpleIntegerDynamicPseudoCost & operator= (const CbcSimpleIntegerDynamicPseudoCost &rhs)
- virtual ~CbcSimpleIntegerDynamicPseudoCost ()
- virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const

Infeasibility - large is 0.5.

virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Creates a branching object.

 virtual CbcObjectUpdateData createUpdateInformation (const OsiSolverInterface *solver, const CbcNode *node, const CbcBranchingObject *branchingObject)

Fills in a created branching object.

virtual void updateInformation (const CbcObjectUpdateData &data)

Update object by CbcObjectUpdateData.

void copySome (const CbcSimpleIntegerDynamicPseudoCost *otherObject)

Copy some information i.e. just variable stuff.

virtual void updateBefore (const OsiObject *rhs)

Updates stuff like pseudocosts before threads.

virtual void updateAfter (const OsiObject *rhs, const OsiObject *baseObject)

Updates stuff like pseudocosts after threads finished.

• void updateAfterMini (int numberDown, int numberDownInfeasible, double sumDown, int numberUp, int number-UpInfeasible, double sumUp)

Updates stuff like pseudocosts after mini branch and bound.

virtual OsiSolverBranch * solverBranch () const

Create an OsiSolverBranch object.

double downDynamicPseudoCost () const

Down pseudo cost.

void setDownDynamicPseudoCost (double value)

Set down pseudo cost.

void updateDownDynamicPseudoCost (double value)

Modify down pseudo cost in a slightly different way.

double upDynamicPseudoCost () const

Up pseudo cost.

void setUpDynamicPseudoCost (double value)

Set up pseudo cost.

void updateUpDynamicPseudoCost (double value)

Modify up pseudo cost in a slightly different way.

double downShadowPrice () const

Down pseudo shadow price cost.

void setDownShadowPrice (double value)

Set down pseudo shadow price cost.

double upShadowPrice () const

Up pseudo shadow price cost.

void setUpShadowPrice (double value)

Set up pseudo shadow price cost.

• double upDownSeparator () const

Up down separator.

void setUpDownSeparator (double value)

Set up down separator.

• double sumDownCost () const

Down sum cost.

void setSumDownCost (double value)

Set down sum cost.

void addToSumDownCost (double value)

Add to down sum cost and set last and square.

double sumUpCost () const

Up sum cost.

void setSumUpCost (double value)

Set up sum cost.

void addToSumUpCost (double value)

Add to up sum cost and set last and square.

double sumDownChange () const

Down sum change.

void setSumDownChange (double value)

Set down sum change.

void addToSumDownChange (double value)

Add to down sum change.

• double sumUpChange () const

Up sum change.

void setSumUpChange (double value)

Set up sum change.

void addToSumUpChange (double value)

Add to up sum change and set last and square.

double sumDownDecrease () const

Sum down decrease number infeasibilities from strong or actual.

void setSumDownDecrease (double value)

Set sum down decrease number infeasibilities from strong or actual.

void addToSumDownDecrease (double value)

Add to sum down decrease number infeasibilities from strong or actual.

double sumUpDecrease () const

Sum up decrease number infeasibilities from strong or actual.

void setSumUpDecrease (double value)

Set sum up decrease number infeasibilities from strong or actual.

void addToSumUpDecrease (double value)

Add to sum up decrease number infeasibilities from strong or actual.

• int numberTimesDown () const

Down number times.

void setNumberTimesDown (int value)

Set down number times.

void incrementNumberTimesDown ()

Increment down number times.

int numberTimesUp () const

Up number times.

void setNumberTimesUp (int value)

Set up number times.

void incrementNumberTimesUp ()

Increment up number times.

• int numberTimesDownInfeasible () const

Down number times infeasible.

void setNumberTimesDownInfeasible (int value)

Set down number times infeasible.

void incrementNumberTimesDownInfeasible ()

Increment down number times infeasible.

• int numberTimesUpInfeasible () const

Up number times infeasible.

void setNumberTimesUpInfeasible (int value)

Set up number times infeasible.

void incrementNumberTimesUpInfeasible ()

Increment up number times infeasible.

int numberBeforeTrust () const

Number of times before trusted.

void setNumberBeforeTrust (int value)

Set number of times before trusted.

void incrementNumberBeforeTrust ()

Increment number of times before trusted.

virtual double upEstimate () const

Return "up" estimate.

· virtual double downEstimate () const

Return "down" estimate (default 1.0e-5)

• int method () const

method - see below for details

void setMethod (int value)

Set method.

void setDownInformation (double changeObjectiveDown, int changeInfeasibilityDown)

Pass in information on a down branch.

void setUpInformation (double changeObjectiveUp, int changeInfeasibilityUp)

Pass in information on a up branch.

void setProbingInformation (int fixedDown, int fixedUp)

Pass in probing information.

void print (int type=0, double value=0.0) const

Print - 0 -summary, 1 just before strong.

bool same (const CbcSimpleIntegerDynamicPseudoCost *obj) const

Same - returns true if contents match(ish)

Protected Attributes

· double downDynamicPseudoCost_

data

double upDynamicPseudoCost_

Up pseudo cost.

double upDownSeparator_

Up/down separator If > 0.0 then do first branch up if value-floor(value) >= this value.

· double sumDownCost_

Sum down cost from strong or actual.

double sumUpCost_

Sum up cost from strong or actual.

double sumDownChange

Sum of all changes to x when going down.

double sumUpChange

Sum of all changes to x when going up.

double downShadowPrice

Current pseudo-shadow price estimate down.

double upShadowPrice_

Current pseudo-shadow price estimate up.

double sumDownDecrease

Sum down decrease number infeasibilities from strong or actual.

• double sumUpDecrease_

Sum up decrease number infeasibilities from strong or actual.

double lastDownCost

Last down cost from strong (i.e. as computed by last strong)

double lastUpCost_

Last up cost from strong (i.e. as computed by last strong)

· int lastDownDecrease_

Last down decrease number infeasibilities from strong (i.e. as computed by last strong)

int lastUpDecrease_

Last up decrease number infeasibilities from strong (i.e. as computed by last strong)

int numberTimesDown_

Number of times we have gone down.

int numberTimesUp_

Number of times we have gone up.

int numberTimesDownInfeasible

Number of times we have been infeasible going down.

· int numberTimesUpInfeasible_

Number of times we have been infeasible going up.

int numberBeforeTrust_

Number of branches before we trust.

int numberTimesDownLocalFixed

Number of local probing fixings going down.

int numberTimesUpLocalFixed_

Number of local probing fixings going up.

double numberTimesDownTotalFixed_

Number of total probing fixings going down.

double numberTimesUpTotalFixed_

Number of total probing fixings going up.

· int numberTimesProbingTotal_

Number of times probing done.

int method

Number of times infeasible when tested.

7.90.1 Detailed Description

Define a single integer class but with dynamic pseudo costs.

Based on work by Achterberg, Koch and Martin.

It is wild overkill but to keep design all twiddly things are in each. This could be used for fine tuning.

Definition at line 35 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

- 7.90.2 Constructor & Destructor Documentation
- 7.90.2.1 CbcSimpleIntegerDynamicPseudoCost::CbcSimpleIntegerDynamicPseudoCost ()
- 7.90.2.2 CbcSimpleIntegerDynamicPseudoCost::CbcSimpleIntegerDynamicPseudoCost (CbcModel * model, int iColumn, double breakEven = 0 . 5)
- 7.90.2.3 CbcSimpleIntegerDynamicPseudoCost::CbcSimpleIntegerDynamicPseudoCost (CbcModel * model, int iColumn, double downDynamicPseudoCost, double upDynamicPseudoCost)
- 7.90.2.4 CbcSimpleIntegerDynamicPseudoCost::CbcSimpleIntegerDynamicPseudoCost (CbcModel * model, int dummy, int iColumn, double downDynamicPseudoCost, double upDynamicPseudoCost)
- 7.90.2.5 CbcSimpleIntegerDynamicPseudoCost::CbcSimpleIntegerDynamicPseudoCost (const CbcSimpleIntegerDynamicPseudoCost &)
- 7.90.2.6 virtual CbcSimpleIntegerDynamicPseudoCost::~CbcSimpleIntegerDynamicPseudoCost() [virtual]
- 7.90.3 Member Function Documentation

```
7.90.3.1 virtual CbcObject* CbcSimpleIntegerDynamicPseudoCost::clone( ) const [virtual]
```

Clone.

Reimplemented from CbcSimpleInteger.

7.90.3.2 CbcSimpleIntegerDynamicPseudoCost& CbcSimpleIntegerDynamicPseudoCost::operator= (const CbcSimpleIntegerDynamicPseudoCost & rhs)

7.90.3.3 virtual double CbcSimpleIntegerDynamicPseudoCost::infeasibility (const OsiBranchingInformation * info, int & preferredWay) const [virtual]

Infeasibility - large is 0.5.

Reimplemented from CbcSimpleInteger.

7.90.3.4 virtual CbcBranchingObject* CbcSimpleIntegerDynamicPseudoCost::createCbcBranch (OsiSolverInterface * solver, const OsiBranchingInformation * info, int way) [virtual]

Creates a branching object.

Reimplemented from CbcSimpleInteger.

```
7.90.3.5 virtual CbcObjectUpdateData CbcSimpleIntegerDynamicPseudoCost::createUpdateInformation ( const OsiSolverInterface * solver, const CbcNode * node, const CbcBranchingObject * branchingObject )

[virtual]
```

Fills in a created branching object.

Pass in information on branch just done and create CbcObjectUpdateData instance. If object does not need data then backward pointer will be NULL. Assumes can get information from solver

Reimplemented from CbcObject.

7.90.3.6 virtual void CbcSimpleIntegerDynamicPseudoCost::updateInformation (const CbcObjectUpdateData & data)
[virtual]

Update object by CbcObjectUpdateData.

Reimplemented from CbcObject.

7.90.3.7 void CbcSimpleIntegerDynamicPseudoCost::copySome (const CbcSimpleIntegerDynamicPseudoCost * otherObject)

Copy some information i.e. just variable stuff.

7.90.3.8 virtual void CbcSimpleIntegerDynamicPseudoCost::updateBefore (const OsiObject * rhs) [virtual]

Updates stuff like pseudocosts before threads.

7.90.3.9 virtual void CbcSimpleIntegerDynamicPseudoCost::updateAfter (const OsiObject * rhs, const OsiObject * baseObject)

[virtual]

Updates stuff like pseudocosts after threads finished.

7.90.3.10 void CbcSimpleIntegerDynamicPseudoCost::updateAfterMini (int *numberDown,* int *numberDownInfeasible,* double *sumDown,* int *numberUp,* int *numberUpInfeasible,* double *sumUp*)

Updates stuff like pseudocosts after mini branch and bound.

7.90.3.11 virtual OsiSolverBranch* CbcSimpleIntegerDynamicPseudoCost::solverBranch()const [virtual] Create an OsiSolverBranch object. This returns NULL if branch not represented by bound changes Reimplemented from CbcObject. 7.90.3.12 double CbcSimpleIntegerDynamicPseudoCost::downDynamicPseudoCost() const [inline] Down pseudo cost. Definition at line 103 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.13 void CbcSimpleIntegerDynamicPseudoCost::setDownDynamicPseudoCost (double value) Set down pseudo cost. 7.90.3.14 void CbcSimpleIntegerDynamicPseudoCost::updateDownDynamicPseudoCost (double value) Modify down pseudo cost in a slightly different way. 7.90.3.15 double CbcSimpleIntegerDynamicPseudoCost::upDynamicPseudoCost()const [inline] Up pseudo cost. Definition at line 112 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.16 void CbcSimpleIntegerDynamicPseudoCost::setUpDynamicPseudoCost (double value) Set up pseudo cost. 7.90.3.17 void CbcSimpleIntegerDynamicPseudoCost::updateUpDynamicPseudoCost (double value) Modify up pseudo cost in a slightly different way. 7.90.3.18 double CbcSimpleIntegerDynamicPseudoCost::downShadowPrice() const [inline] Down pseudo shadow price cost. Definition at line 121 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.19 void CbcSimpleIntegerDynamicPseudoCost::setDownShadowPrice (double value) [inline] Set down pseudo shadow price cost. Definition at line 125 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.20 double CbcSimpleIntegerDynamicPseudoCost::upShadowPrice() const [inline] Up pseudo shadow price cost. Definition at line 129 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.21 void CbcSimpleIntegerDynamicPseudoCost::setUpShadowPrice (double value) [inline]

Definition at line 133 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

Set up pseudo shadow price cost.

7.90.3.22 double CbcSimpleIntegerDynamicPseudoCost::upDownSeparator() const [inline] Up down separator. Definition at line 138 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.23 void CbcSimpleIntegerDynamicPseudoCost::setUpDownSeparator (double value) [inline] Set up down separator. Definition at line 142 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.24 double CbcSimpleIntegerDynamicPseudoCost::sumDownCost() const [inline] Down sum cost. Definition at line 147 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.25 void CbcSimpleIntegerDynamicPseudoCost::setSumDownCost (double value) [inline] Set down sum cost. Definition at line 151 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.26 void CbcSimpleIntegerDynamicPseudoCost::addToSumDownCost (double value) [inline] Add to down sum cost and set last and square. Definition at line 155 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.27 double CbcSimpleIntegerDynamicPseudoCost::sumUpCost() const [inline] Up sum cost. Definition at line 161 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.28 void CbcSimpleIntegerDynamicPseudoCost::setSumUpCost (double value) [inline] Set up sum cost. Definition at line 165 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.29 void CbcSimpleIntegerDynamicPseudoCost::addToSumUpCost (double value) [inline] Add to up sum cost and set last and square. Definition at line 169 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.30 double CbcSimpleIntegerDynamicPseudoCost::sumDownChange() const [inline] Down sum change. Definition at line 175 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.3.31 void CbcSimpleIntegerDynamicPseudoCost::setSumDownChange (double value) [inline]

Definition at line 179 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

Set down sum change.

7.90.3.32 void CbcSimpleIntegerDynamicPseudoCost::addToSumDownChange (double value) [inline]
 Add to down sum change.
 Definition at line 183 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
 7.90.3.33 double CbcSimpleIntegerDynamicPseudoCost::sumUpChange () const [inline]

Up sum change.

Definition at line 188 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.3.34 void CbcSimpleIntegerDynamicPseudoCost::setSumUpChange (double value) [inline]

Set up sum change.

Definition at line 192 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.3.35 void CbcSimpleIntegerDynamicPseudoCost::addToSumUpChange (double value) [inline]

Add to up sum change and set last and square.

Definition at line 196 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.3.36 double CbcSimpleIntegerDynamicPseudoCost::sumDownDecrease() const [inline]

Sum down decrease number infeasibilities from strong or actual.

Definition at line 201 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.3.37 void CbcSimpleIntegerDynamicPseudoCost::setSumDownDecrease (double value) [inline]

Set sum down decrease number infeasibilities from strong or actual.

Definition at line 205 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.3.38 void CbcSimpleIntegerDynamicPseudoCost::addToSumDownDecrease (double value) [inline]

Add to sum down decrease number infeasibilities from strong or actual.

Definition at line 209 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.3.39 double CbcSimpleIntegerDynamicPseudoCost::sumUpDecrease () const [inline]

Sum up decrease number infeasibilities from strong or actual.

Definition at line 214 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.3.40 void CbcSimpleIntegerDynamicPseudoCost::setSumUpDecrease (double value) [inline]

Set sum up decrease number infeasibilities from strong or actual.

Definition at line 218 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.3.41 void CbcSimpleIntegerDynamicPseudoCost::addToSumUpDecrease (double value) [inline]

Add to sum up decrease number infeasibilities from strong or actual.

Definition at line 222 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

```
7.90.3.42 int CbcSimpleIntegerDynamicPseudoCost::numberTimesDown() const [inline]
Down number times.
Definition at line 227 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.43 void CbcSimpleIntegerDynamicPseudoCost::setNumberTimesDown(int value) [inline]
Set down number times.
Definition at line 231 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.44 void CbcSimpleIntegerDynamicPseudoCost::incrementNumberTimesDown() [inline]
Increment down number times.
Definition at line 235 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.45 int CbcSimpleIntegerDynamicPseudoCost::numberTimesUp ( ) const [inline]
Up number times.
Definition at line 240 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.46 void CbcSimpleIntegerDynamicPseudoCost::setNumberTimesUp(int value) [inline]
Set up number times.
Definition at line 244 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.47 void CbcSimpleIntegerDynamicPseudoCost::incrementNumberTimesUp( ) [inline]
Increment up number times.
Definition at line 248 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.48 int CbcSimpleIntegerDynamicPseudoCost::numberTimesDownInfeasible( )const [inline]
Down number times infeasible.
Definition at line 253 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.49 void CbcSimpleIntegerDynamicPseudoCost::setNumberTimesDownInfeasible(int value) [inline]
Set down number times infeasible.
Definition at line 257 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.50 void CbcSimpleIntegerDynamicPseudoCost::incrementNumberTimesDownInfeasible() [inline]
Increment down number times infeasible.
Definition at line 261 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.51 int CbcSimpleIntegerDynamicPseudoCost::numberTimesUpInfeasible ( ) const [inline]
Up number times infeasible.
Definition at line 266 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
```

```
7.90.3.52 void CbcSimpleIntegerDynamicPseudoCost::setNumberTimesUpInfeasible (int value) [inline]
Set up number times infeasible.
Definition at line 270 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.53 void CbcSimpleIntegerDynamicPseudoCost::incrementNumberTimesUpInfeasible( ) [inline]
Increment up number times infeasible.
Definition at line 274 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.54 int CbcSimpleIntegerDynamicPseudoCost::numberBeforeTrust() const [inline]
Number of times before trusted.
Definition at line 279 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.55 void CbcSimpleIntegerDynamicPseudoCost::setNumberBeforeTrust(int value) [inline]
Set number of times before trusted.
Definition at line 283 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.56 void CbcSimpleIntegerDynamicPseudoCost::incrementNumberBeforeTrust() [inline]
Increment number of times before trusted.
Definition at line 287 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.57 virtual double CbcSimpleIntegerDynamicPseudoCost::upEstimate() const [virtual]
Return "up" estimate.
7.90.3.58 virtual double CbcSimpleIntegerDynamicPseudoCost::downEstimate( ) const [virtual]
Return "down" estimate (default 1.0e-5)
7.90.3.59 int CbcSimpleIntegerDynamicPseudoCost::method() const [inline]
method - see below for details
Definition at line 297 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.60 void CbcSimpleIntegerDynamicPseudoCost::setMethod (int value) [inline]
Set method.
Definition at line 301 of file CbcSimpleIntegerDynamicPseudoCost.hpp.
7.90.3.61 void CbcSimpleIntegerDynamicPseudoCost::setDownInformation ( double changeObjectiveDown, int
         changeInfeasibilityDown )
Pass in information on a down branch.
7.90.3.62 void CbcSimpleIntegerDynamicPseudoCost::setUpInformation ( double changeObjectiveUp, int changeInfeasibilityUp )
Pass in information on a up branch.
```

7.90.3.63 void CbcSimpleIntegerDynamicPseudoCost::setProbingInformation (int fixedDown, int fixedUp)

Pass in probing information.

7.90.3.64 void CbcSimpleIntegerDynamicPseudoCost::print (int type = 0, double value = 0.0) const

Print - 0 -summary, 1 just before strong.

7.90.3.65 bool CbcSimpleIntegerDynamicPseudoCost::same (const CbcSimpleIntegerDynamicPseudoCost * obj) const

Same - returns true if contents match(ish)

7.90.4 Member Data Documentation

7.90.4.1 double CbcSimpleIntegerDynamicPseudoCost::downDynamicPseudoCost_ [protected]

data

Down pseudo cost

Definition at line 320 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.2 double CbcSimpleIntegerDynamicPseudoCost::upDynamicPseudoCost_ [protected]

Up pseudo cost.

Definition at line 322 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.3 double CbcSimpleIntegerDynamicPseudoCost::upDownSeparator_ [protected]

Up/down separator If >0.0 then do first branch up if value-floor(value) >= this value.

Definition at line 327 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.4 double CbcSimpleIntegerDynamicPseudoCost::sumDownCost_ [protected]

Sum down cost from strong or actual.

Definition at line 329 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.5 double CbcSimpleIntegerDynamicPseudoCost::sumUpCost_ [protected]

Sum up cost from strong or actual.

Definition at line 331 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.6 double CbcSimpleIntegerDynamicPseudoCost::sumDownChange_ [protected]

Sum of all changes to x when going down.

Definition at line 333 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.7 double CbcSimpleIntegerDynamicPseudoCost::sumUpChange_ [protected]

Sum of all changes to x when going up.

Definition at line 335 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90 CbcSimpleIntegerDynamicPseudoCost Class Reference 7.90.4.8 double CbcSimpleIntegerDynamicPseudoCost::downShadowPrice_ [mutable], [protected] Current pseudo-shadow price estimate down. Definition at line 337 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.4.9 double CbcSimpleIntegerDynamicPseudoCost::upShadowPrice [mutable], [protected] Current pseudo-shadow price estimate up. Definition at line 339 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.4.10 double CbcSimpleIntegerDynamicPseudoCost::sumDownDecrease_ [protected] Sum down decrease number infeasibilities from strong or actual. Definition at line 341 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.4.11 double CbcSimpleIntegerDynamicPseudoCost::sumUpDecrease_ [protected] Sum up decrease number infeasibilities from strong or actual. Definition at line 343 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.4.12 double CbcSimpleIntegerDynamicPseudoCost::lastDownCost [protected] Last down cost from strong (i.e. as computed by last strong) Definition at line 345 of file CbcSimpleIntegerDynamicPseudoCost.hpp. **7.90.4.13 double CbcSimpleIntegerDynamicPseudoCost::lastUpCost_** [protected] Last up cost from strong (i.e. as computed by last strong) Definition at line 347 of file CbcSimpleIntegerDynamicPseudoCost.hpp. 7.90.4.14 int CbcSimpleIntegerDynamicPseudoCost::lastDownDecrease_ [mutable], [protected] Last down decrease number infeasibilities from strong (i.e. as computed by last strong)

Definition at line 349 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.15 int CbcSimpleIntegerDynamicPseudoCost::lastUpDecrease [mutable], [protected]

Last up decrease number infeasibilities from strong (i.e. as computed by last strong)

Definition at line 351 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.16 int CbcSimpleIntegerDynamicPseudoCost::numberTimesDown [protected]

Number of times we have gone down.

Definition at line 353 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.17 int CbcSimpleIntegerDynamicPseudoCost::numberTimesUp_ [protected]

Number of times we have gone up.

Definition at line 355 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.18 int CbcSimpleIntegerDynamicPseudoCost::numberTimesDownInfeasible_ [protected]

Number of times we have been infeasible going down.

Definition at line 357 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.19 int CbcSimpleIntegerDynamicPseudoCost::numberTimesUpInfeasible [protected]

Number of times we have been infeasible going up.

Definition at line 359 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.20 int CbcSimpleIntegerDynamicPseudoCost::numberBeforeTrust_ [protected]

Number of branches before we trust.

Definition at line 361 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.21 int CbcSimpleIntegerDynamicPseudoCost::numberTimesDownLocalFixed_ [protected]

Number of local probing fixings going down.

Definition at line 363 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.22 int CbcSimpleIntegerDynamicPseudoCost::numberTimesUpLocalFixed_ [protected]

Number of local probing fixings going up.

Definition at line 365 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.23 double CbcSimpleIntegerDynamicPseudoCost::numberTimesDownTotalFixed_ [protected]

Number of total probing fixings going down.

Definition at line 367 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.24 double CbcSimpleIntegerDynamicPseudoCost::numberTimesUpTotalFixed_ [protected]

Number of total probing fixings going up.

Definition at line 369 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.25 int CbcSimpleIntegerDynamicPseudoCost::numberTimesProbingTotal [protected]

Number of times probing done.

Definition at line 371 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

7.90.4.26 int CbcSimpleIntegerDynamicPseudoCost::method_ [protected]

Number of times infeasible when tested.

Method - 0 - pseudo costs 1 - probing

Definition at line 377 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcSimpleIntegerDynamicPseudoCost.hpp

7.91 CbcSimpleIntegerPseudoCost Class Reference

Define a single integer class but with pseudo costs.

#include <CbcSimpleIntegerPseudoCost.hpp>

Inheritance diagram for CbcSimpleIntegerPseudoCost:



Public Member Functions

- CbcSimpleIntegerPseudoCost ()
- CbcSimpleIntegerPseudoCost (CbcModel *model, int iColumn, double breakEven=0.5)
- CbcSimpleIntegerPseudoCost (CbcModel *model, int iColumn, double downPseudoCost, double upPseudoCost)
- CbcSimpleIntegerPseudoCost (CbcModel *model, int dummy, int iColumn, double downPseudoCost, double up-PseudoCost)
- CbcSimpleIntegerPseudoCost (const CbcSimpleIntegerPseudoCost &)
- virtual CbcObject * clone () const

Clone.

- CbcSimpleIntegerPseudoCost & operator= (const CbcSimpleIntegerPseudoCost &rhs)
- virtual ~CbcSimpleIntegerPseudoCost ()
- virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const Infeasibility - large is 0.5.
- virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Creates a branching object.

• double downPseudoCost () const

Down pseudo cost.

• void setDownPseudoCost (double value)

Set down pseudo cost.

double upPseudoCost () const

Up pseudo cost.

void setUpPseudoCost (double value)

Set up pseudo cost.

• double upDownSeparator () const

Up down separator.

void setUpDownSeparator (double value)

Set up down separator.

virtual double upEstimate () const

Return "up" estimate.

· virtual double downEstimate () const

Return "down" estimate (default 1.0e-5)

• int method () const

method - see below for details

· void setMethod (int value)

Set method.

Protected Attributes

double downPseudoCost

data

double upPseudoCost

Up pseudo cost.

double upDownSeparator

Up/down separator If >0.0 then do first branch up if value-floor(value) >= this value.

int method

Method - 0 - normal - return min (up,down) 1 - if before any solution return CoinMax(up,down) 2 - if before branched solution return CoinMax(up,down) 3 - always return CoinMax(up,down)

7.91.1 Detailed Description

Define a single integer class but with pseudo costs.

Definition at line 14 of file CbcSimpleIntegerPseudoCost.hpp.

- 7.91.2 Constructor & Destructor Documentation
- 7.91.2.1 CbcSimpleIntegerPseudoCost::CbcSimpleIntegerPseudoCost ()
- 7.91.2.2 CbcSimpleIntegerPseudoCost::CbcSimpleIntegerPseudoCost (CbcModel * model, int iColumn, double breakEven = 0.5)
- 7.91.2.3 CbcSimpleIntegerPseudoCost::CbcSimpleIntegerPseudoCost (CbcModel * model, int iColumn, double downPseudoCost, double upPseudoCost)
- 7.91.2.4 CbcSimpleIntegerPseudoCost::CbcSimpleIntegerPseudoCost (CbcModel * model, int dummy, int iColumn, double downPseudoCost, double upPseudoCost)
- 7.91.2.5 CbcSimpleIntegerPseudoCost::CbcSimpleIntegerPseudoCost (const CbcSimpleIntegerPseudoCost &)
- 7.91.2.6 virtual CbcSimpleIntegerPseudoCost::~CbcSimpleIntegerPseudoCost() [virtual]
- 7.91.3 Member Function Documentation
- 7.91.3.1 virtual CbcObject* CbcSimpleIntegerPseudoCost::clone() const [virtual]

Clone.

Reimplemented from CbcSimpleInteger.

```
7.91.3.2 CbcSimpleIntegerPseudoCost& CbcSimpleIntegerPseudoCost::operator= ( const
         CbcSimpleIntegerPseudoCost & rhs )
7.91.3.3 virtual double CbcSimpleIntegerPseudoCost::infeasibility ( const OsiBranchingInformation * info, int & preferredWay )
         const [virtual]
Infeasibility - large is 0.5.
Reimplemented from CbcSimpleInteger.
7.91.3.4 virtual CbcBranchingObject* CbcSimpleIntegerPseudoCost::createCbcBranch ( OsiSolverInterface * solver, const
         OsiBranchingInformation * info, int way ) [virtual]
Creates a branching object.
Reimplemented from CbcSimpleInteger.
7.91.3.5 double CbcSimpleIntegerPseudoCost::downPseudoCost() const [inline]
Down pseudo cost.
Definition at line 51 of file CbcSimpleIntegerPseudoCost.hpp.
7.91.3.6 void CbcSimpleIntegerPseudoCost::setDownPseudoCost (double value) [inline]
Set down pseudo cost.
Definition at line 55 of file CbcSimpleIntegerPseudoCost.hpp.
7.91.3.7 double CbcSimpleIntegerPseudoCost::upPseudoCost() const [inline]
Up pseudo cost.
Definition at line 60 of file CbcSimpleIntegerPseudoCost.hpp.
7.91.3.8 void CbcSimpleIntegerPseudoCost::setUpPseudoCost ( double value ) [inline]
Set up pseudo cost.
Definition at line 64 of file CbcSimpleIntegerPseudoCost.hpp.
7.91.3.9 double CbcSimpleIntegerPseudoCost::upDownSeparator()const [inline]
Up down separator.
Definition at line 69 of file CbcSimpleIntegerPseudoCost.hpp.
7.91.3.10 void CbcSimpleIntegerPseudoCost::setUpDownSeparator ( double value ) [inline]
Set up down separator.
Definition at line 73 of file CbcSimpleIntegerPseudoCost.hpp.
7.91.3.11 virtual double CbcSimpleIntegerPseudoCost::upEstimate() const [virtual]
Return "up" estimate.
7.91.3.12 virtual double CbcSimpleIntegerPseudoCost::downEstimate() const [virtual]
Return "down" estimate (default 1.0e-5)
```

7.91.3.13 int CbcSimpleIntegerPseudoCost::method() const [inline]

method - see below for details

Definition at line 83 of file CbcSimpleIntegerPseudoCost.hpp.

7.91.3.14 void CbcSimpleIntegerPseudoCost::setMethod (int value) [inline]

Set method.

Definition at line 87 of file CbcSimpleIntegerPseudoCost.hpp.

7.91.4 Member Data Documentation

7.91.4.1 double CbcSimpleIntegerPseudoCost::downPseudoCost_ [protected]

data

Down pseudo cost

Definition at line 95 of file CbcSimpleIntegerPseudoCost.hpp.

7.91.4.2 double CbcSimpleIntegerPseudoCost::upPseudoCost_ [protected]

Up pseudo cost.

Definition at line 97 of file CbcSimpleIntegerPseudoCost.hpp.

7.91.4.3 double CbcSimpleIntegerPseudoCost::upDownSeparator_ [protected]

Up/down separator If >0.0 then do first branch up if value-floor(value) >= this value.

Definition at line 102 of file CbcSimpleIntegerPseudoCost.hpp.

7.91.4.4 int CbcSimpleIntegerPseudoCost::method_ [protected]

Method - 0 - normal - return min (up,down) 1 - if before any solution return CoinMax(up,down) 2 - if before branched solution return CoinMax(up,down) 3 - always return CoinMax(up,down)

Definition at line 109 of file CbcSimpleIntegerPseudoCost.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcSimpleIntegerPseudoCost.hpp

7.92 CbcSolver Class Reference

This allows the use of the standalone solver in a flexible manner.

```
#include <CbcSolver.hpp>
```

Public Member Functions

Solve method

• int solve (int argc, const char *argv[], int returnMode)

This takes a list of commands, does "stuff" and returns returnMode - 0 model and solver untouched - babModel updated 1 model updated - just with solution basis etc 2 model updated i.e.

• int solve (const char *input, int returnMode)

This takes a list of commands, does "stuff" and returns returnMode - 0 model and solver untouched - babModel updated 1 model updated - just with solution basis etc 2 model updated i.e.

Constructors and destructors etc

• CbcSolver ()

Default Constructor.

• CbcSolver (const OsiClpSolverInterface &)

Constructor from solver.

• CbcSolver (const CbcModel &)

Constructor from model.

CbcSolver (const CbcSolver &rhs)

Copy constructor.

CbcSolver & operator= (const CbcSolver &rhs)

Assignment operator.

∼CbcSolver ()

Destructor.

void fillParameters ()

Fill with standard parameters.

void fillValuesInSolver ()

Set default values in solvers from parameters.

void addUserFunction (CbcUser *function)

Add user function.

void setUserCallBack (CbcStopNow *function)

Set user call back.

void addCutGenerator (CglCutGenerator *generator)

Add cut generator.

miscellaneous methods to line up with old

- int * analyze (OsiClpSolverInterface *solverMod, int &numberChanged, double &increment, bool changeInt, CoinMessageHandler *generalMessageHandler)
- void updateModel (ClpSimplex *model2, int returnMode)

1 - add heuristics to model 2 - do heuristics (and set cutoff and best solution) 3 - for miplib test so skip some (out model later)

useful stuff

int intValue (CbcOrClpParameterType type) const

Get int value.

void setIntValue (CbcOrClpParameterType type, int value)

Set int value.

double doubleValue (CbcOrClpParameterType type) const

Get double value.

void setDoubleValue (CbcOrClpParameterType type, double value)

Set double value.

CbcUser * userFunction (const char *name) const

User function (NULL if no match)

CbcModel * model ()

Return original Cbc model.

CbcModel * babModel ()

Return updated Cbc model.

int numberUserFunctions () const

Number of userFunctions.

CbcUser ** userFunctionArray () const

User function array.

OsiClpSolverInterface * originalSolver () const

Copy of model on initial load (will contain output solutions)

CoinModel * originalCoinModel () const

Copy of model on initial load.

void setOriginalSolver (OsiClpSolverInterface *originalSolver)

Copy of model on initial load (will contain output solutions)

void setOriginalCoinModel (CoinModel *originalCoinModel)

Copy of model on initial load.

int numberCutGenerators () const

Number of cutgenerators.

CglCutGenerator ** cutGeneratorArray () const

Cut generator array.

double startTime () const

Start time.

void setPrinting (bool onOff)

Whether to print to std::cout.

void setReadMode (int value)

Where to start reading commands.

7.92.1 Detailed Description

This allows the use of the standalone solver in a flexible manner.

It has an original OsiClpSolverInterface and CbcModel which it can use repeatedly, e.g., to get a heuristic solution and then start again.

So I [jjf] will need a primitive scripting language which can then call solve and manipulate solution value and solution arrays.

Also provides for user callback functions. Currently two ideas in gestation, CbcUser and CbcStopNow. The latter seems limited to deciding whether or not to stop. The former seems completely general, with a notion of importing and exporting, and a 'solve', which should be interpreted as 'do whatever this user function does'.

Parameter initialisation is at last centralised in fillParameters().

Definition at line 56 of file CbcSolver.hpp.

```
7.92.2 Constructor & Destructor Documentation
```

7.92.2.1 CbcSolver::CbcSolver()

Default Constructor.

7.92.2.2 CbcSolver::CbcSolver (const OsiClpSolverInterface &)

Constructor from solver.

7.92.2.3 CbcSolver::CbcSolver (const CbcModel &)

Constructor from model.

7.92.2.4 CbcSolver::CbcSolver (const CbcSolver & rhs)

Copy constructor.

7.92.2.5 CbcSolver:: \sim CbcSolver()

Destructor.

7.92.3 Member Function Documentation

7.92.3.1 int CbcSolver::solve (int argc, const char * argv[], int returnMode)

This takes a list of commands, does "stuff" and returns returnMode - 0 model and solver untouched - babModel updated 1 model updated - just with solution basis etc 2 model updated i.e.

as babModel (babModel NULL) (only use without preprocessing)

7.92.3.2 int CbcSolver::solve (const char * input, int returnMode)

This takes a list of commands, does "stuff" and returns returnMode - 0 model and solver untouched - babModel updated 1 model updated - just with solution basis etc 2 model updated i.e.

as babModel (babModel NULL) (only use without preprocessing)

7.92.3.3 CbcSolver& CbcSolver::operator= (const CbcSolver & rhs)

Assignment operator.

7.92.3.4 void CbcSolver::fillParameters ()

Fill with standard parameters.

7.92.3.5 void CbcSolver::fillValuesInSolver ()

Set default values in solvers from parameters.

Misleading. The current code actually reads default values from the underlying solvers and installs them as default values for a subset of parameters in #parameters .

7.92.3.6 void CbcSolver::addUserFunction (CbcUser * function)

Add user function.

7.92.3.7 void CbcSolver::setUserCallBack (CbcStopNow * function)

Set user call back.

7.92.3.8 void CbcSolver::addCutGenerator (CglCutGenerator * generator)

Add cut generator.

7.92.3.9 int* CbcSolver::analyze (OsiClpSolverInterface * solverMod, int & numberChanged, double & increment, bool changeInt, CoinMessageHandler * generalMessageHandler)

7.92.3.10 void CbcSolver::updateModel (ClpSimplex * model2, int returnMode)

1 - add heuristics to model 2 - do heuristics (and set cutoff and best solution) 3 - for miplib test so skip some (out model later)

Updates model_ from babModel_ according to returnMode returnMode - 0 model and solver untouched - babModel updated 1 model updated - just with solution basis etc 2 model updated i.e. as babModel (babModel NULL) (only use without preprocessing)

```
7.92.3.11 int CbcSolver::intValue ( CbcOrClpParameterType type ) const
Get int value.
7.92.3.12 void CbcSolver::setIntValue ( CbcOrClpParameterType type, int value )
Set int value.
7.92.3.13 double CbcSolver::doubleValue ( CbcOrClpParameterType type ) const
Get double value.
7.92.3.14 void CbcSolver::setDoubleValue ( CbcOrClpParameterType type, double value )
Set double value.
7.92.3.15 CbcUser* CbcSolver::userFunction ( const char * name ) const
User function (NULL if no match)
7.92.3.16 CbcModel* CbcSolver::model() [inline]
Return original Cbc model.
Definition at line 144 of file CbcSolver.hpp.
7.92.3.17 CbcModel* CbcSolver::babModel( ) [inline]
Return updated Cbc model.
Definition at line 148 of file CbcSolver.hpp.
7.92.3.18 int CbcSolver::numberUserFunctions ( ) const [inline]
Number of userFunctions.
Definition at line 152 of file CbcSolver.hpp.
7.92.3.19 CbcUser** CbcSolver::userFunctionArray() const [inline]
User function array.
Definition at line 156 of file CbcSolver.hpp.
7.92.3.20 OsiClpSolverInterface* CbcSolver::originalSolver( ) const [inline]
Copy of model on initial load (will contain output solutions)
Definition at line 160 of file CbcSolver.hpp.
7.92.3.21 CoinModel* CbcSolver::originalCoinModel( ) const [inline]
Copy of model on initial load.
Definition at line 164 of file CbcSolver.hpp.
7.92.3.22 void CbcSolver::setOriginalSolver (OsiClpSolverInterface * originalSolver)
Copy of model on initial load (will contain output solutions)
```

```
7.92.3.23 void CbcSolver::setOriginalCoinModel ( CoinModel * originalCoinModel )

Copy of model on initial load.

7.92.3.24 int CbcSolver::numberCutGenerators ( ) const [inline]

Number of cutgenerators.

Definition at line 172 of file CbcSolver.hpp.

7.92.3.25 CglCutGenerator** CbcSolver::cutGeneratorArray ( ) const [inline]

Cut generator array.

Definition at line 176 of file CbcSolver.hpp.

7.92.3.26 double CbcSolver::startTime ( ) const [inline]

Start time.

Definition at line 180 of file CbcSolver.hpp.

7.92.3.27 void CbcSolver::setPrinting ( bool onOff ) [inline]

Whether to print to std::cout.

Definition at line 184 of file CbcSolver.hpp.
```

Where to start reading commands.

Definition at line 188 of file CbcSolver.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcSolver.hpp

7.92.3.28 void CbcSolver::setReadMode (int value) [inline]

7.93 CbcSolverUsefulData Struct Reference

Structure to hold useful arrays.

```
#include <CbcSolver.hpp>
```

Public Attributes

```
int * priorities_int * sosPriority_
```

int * branchDirection

double * primalSolution_

double * pseudoDown_

double * pseudoUp_

7.93.1 Detailed Description

Structure to hold useful arrays.

Definition at line 240 of file CbcSolver.hpp.

7.93.2 Member Data Documentation

7.93.2.1 int* CbcSolverUsefulData::priorities_

Definition at line 242 of file CbcSolver.hpp.

7.93.2.2 int * CbcSolverUsefulData::sosPriority_

Definition at line 244 of file CbcSolver.hpp.

7.93.2.3 int* CbcSolverUsefulData::branchDirection_

Definition at line 246 of file CbcSolver.hpp.

7.93.2.4 double * CbcSolverUsefulData::primalSolution_

Definition at line 248 of file CbcSolver.hpp.

7.93.2.5 double * CbcSolverUsefulData::pseudoDown_

Definition at line 250 of file CbcSolver.hpp.

7.93.2.6 double* CbcSolverUsefulData::pseudoUp_

Definition at line 252 of file CbcSolver.hpp.

The documentation for this struct was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcSolver.hpp

7.94 CbcSOS Class Reference

Branching object for Special Ordered Sets of type 1 and 2.

#include <CbcSOS.hpp>

Inheritance diagram for CbcSOS:



Public Member Functions

- CbcSOS ()
- CbcSOS (CbcModel *model, int numberMembers, const int *which, const double *weights, int identifier, int type=1)

Constructor with SOS type and member information.

- CbcSOS (const CbcSOS &)
- virtual CbcObject * clone () const

Clone.

- CbcSOS & operator= (const CbcSOS &rhs)
- virtual ∼CbcSOS ()
- virtual double infeasibility (const OsiBranchingInformation *info, int &preferredWay) const

Infeasibility - large is 0.5.

virtual void feasibleRegion ()

This looks at solution and sets bounds to contain solution.

virtual CbcBranchingObject * createCbcBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way)

Creates a branching object.

virtual CbcObjectUpdateData createUpdateInformation (const OsiSolverInterface *solver, const CbcNode *node, const CbcBranchingObject *branchingObject)

Pass in information on branch just done and create CbcObjectUpdateData instance.

virtual void updateInformation (const CbcObjectUpdateData &data)

Update object by CbcObjectUpdateData.

virtual OsiSolverBranch * solverBranch () const

Create an OsiSolverBranch object.

virtual void redoSequenceEtc (CbcModel *model, int numberColumns, const int *originalColumns)

Redoes data when sequence numbers change.

OsiSOS * osiObject (const OsiSolverInterface *solver) const

Construct an OsiSOS object.

· int numberMembers () const

Number of members.

• const int * members () const

Members (indices in range 0 ... numberColumns-1)

int sosType () const

SOS type.

• int numberTimesDown () const

Down number times.

int numberTimesUp () const

Up number times.

• const double * weights () const

Array of weights.

• void setNumberMembers (int n)

Set number of members.

• int * mutableMembers () const

Members (indices in range 0 ... numberColumns-1)

• double * mutableWeights () const

Array of weights.

· virtual bool canDoHeuristics () const

Return true if object can take part in normal heuristics.

void setIntegerValued (bool yesNo)

Set whether set is integer valued or not.

Additional Inherited Members

7.94.1 Detailed Description

Branching object for Special Ordered Sets of type 1 and 2.

SOS1 are an ordered set of variables where at most one variable can be non-zero. SOS1 are commonly defined with binary variables (interpreted as selection between alternatives) but this is not necessary. An SOS1 with all binary variables is a special case of a clique (setting any one variable to 1 forces all others to 0).

In theory, the implementation makes no assumptions about integrality in Type 1 sets. In practice, there are places where the code seems to have been written with a binary SOS mindset. Current development of SOS branching objects is proceeding in OsiSOS.

SOS2 are an ordered set of variables in which at most two consecutive variables can be non-zero and must sum to 1 (interpreted as interpolation between two discrete values). By definition the variables are non-integer.

Definition at line 29 of file CbcSOS.hpp.

7.94.2 Constructor & Destructor Documentation

```
7.94.2.1 CbcSOS::CbcSOS()
```

7.94.2.2 CbcSOS::CbcSOS (CbcModel * model, int numberMembers, const int * which, const double * weights, int identifier, int type = 1)

Constructor with SOS type and member information.

Type specifies SOS 1 or 2. Identifier is an arbitrary value.

Which should be an array of variable indices with numberMembers entries. Weights can be used to assign arbitrary weights to variables, in the order they are specified in which. If no weights are provided, a default array of 0, 1, 2, ... is generated.

```
7.94.2.3 CbcSOS::CbcSOS ( const CbcSOS & )
```

```
7.94.2.4 virtual CbcSOS::~CbcSOS() [virtual]
```

7.94.3 Member Function Documentation

```
7.94.3.1 virtual CbcObject* CbcSOS::clone() const [virtual]
```

Clone.

Implements CbcObject.

```
7.94.3.2 CbcSOS& CbcSOS::operator= ( const CbcSOS & rhs )
```

7.94.3.3 virtual double CbcSOS::infeasibility (const OsiBranchingInformation * info, int & preferredWay) const [virtual]

Infeasibility - large is 0.5.

Reimplemented from CbcObject.

```
7.94.3.4 virtual void CbcSOS::feasibleRegion ( ) [virtual]
```

This looks at solution and sets bounds to contain solution.

Implements CbcObject.

```
7.94.3.5 virtual CbcBranchingObject * CbcSOS::createCbcBranch (OsiSolverInterface * solver, const OsiBranchingInformation
        * info, int way ) [virtual]
Creates a branching object.
Reimplemented from CbcObject.
7.94.3.6 virtual CbcObjectUpdateData CbcSOS::createUpdateInformation ( const OsiSolverInterface * solver, const CbcNode
        * node, const CbcBranchingObject * branchingObject ) [virtual]
Pass in information on branch just done and create CbcObjectUpdateData instance.
If object does not need data then backward pointer will be NULL. Assumes can get information from solver
Reimplemented from CbcObject.
7.94.3.7 virtual void CbcSOS::updateInformation ( const CbcObjectUpdateData & data ) [virtual]
Update object by CbcObjectUpdateData.
Reimplemented from CbcObject.
7.94.3.8 virtual OsiSolverBranch* CbcSOS::solverBranch( ) const [virtual]
Create an OsiSolverBranch object.
This returns NULL if branch not represented by bound changes
Reimplemented from CbcObject.
7.94.3.9 virtual void CbcSOS::redoSequenceEtc ( CbcModel * model, int numberColumns, const int * originalColumns )
         [virtual]
Redoes data when sequence numbers change.
Reimplemented from CbcObject.
7.94.3.10 OsiSOS* CbcSOS::osiObject ( const OsiSolverInterface * solver ) const
Construct an OsiSOS object.
7.94.3.11 int CbcSOS::numberMembers ( ) const [inline]
Number of members.
Definition at line 95 of file CbcSOS.hpp.
7.94.3.12 const int* CbcSOS::members ( ) const [inline]
Members (indices in range 0 ... numberColumns-1)
Definition at line 100 of file CbcSOS.hpp.
7.94.3.13 int CbcSOS::sosType() const [inline]
SOS type.
Definition at line 105 of file CbcSOS.hpp.
7.94.3.14 int CbcSOS::numberTimesDown ( ) const [inline]
```

Down number times.

```
Definition at line 109 of file CbcSOS.hpp.
```

```
7.94.3.15 int CbcSOS::numberTimesUp ( ) const [inline]
```

Up number times.

Definition at line 113 of file CbcSOS.hpp.

```
7.94.3.16 const double* CbcSOS::weights ( ) const [inline]
```

Array of weights.

Definition at line 118 of file CbcSOS.hpp.

```
7.94.3.17 void CbcSOS::setNumberMembers (int n) [inline]
```

Set number of members.

Definition at line 123 of file CbcSOS.hpp.

```
7.94.3.18 int* CbcSOS::mutableMembers ( ) const [inline]
```

Members (indices in range 0 ... numberColumns-1)

Definition at line 128 of file CbcSOS.hpp.

```
7.94.3.19 double* CbcSOS::mutableWeights ( ) const [inline]
```

Array of weights.

Definition at line 133 of file CbcSOS.hpp.

```
7.94.3.20 virtual bool CbcSOS::canDoHeuristics ( ) const [inline], [virtual]
```

Return true if object can take part in normal heuristics.

Definition at line 139 of file CbcSOS.hpp.

```
7.94.3.21 void CbcSOS::setIntegerValued ( bool yesNo ) [inline]
```

Set whether set is integer valued or not.

Definition at line 143 of file CbcSOS.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcSOS.hpp

7.95 CbcSOSBranchingObject Class Reference

Branching object for Special ordered sets.

```
#include <CbcSOS.hpp>
```

Inheritance diagram for CbcSOSBranchingObject:



Public Member Functions

- CbcSOSBranchingObject ()
- CbcSOSBranchingObject (CbcModel *model, const CbcSOS *clique, int way, double separator)
- CbcSOSBranchingObject (const CbcSOSBranchingObject &)
- CbcSOSBranchingObject & operator= (const CbcSOSBranchingObject &rhs)
- virtual CbcBranchingObject * clone () const

Clone.

- virtual ~CbcSOSBranchingObject ()
- virtual double branch ()

Does next branch and updates state.

• virtual void fix (OsiSolverInterface *solver, double *lower, double *upper, int branchState) const

Update bounds in solver as in 'branch' and update given bounds.

• virtual void previousBranch ()

Reset every information so that the branching object appears to point to the previous child.

· virtual void print ()

Print something about branch - only if log level high.

virtual CbcBranchObjType type () const

Return the type (an integer identifier) of this.

virtual int compareOriginalObject (const CbcBranchingObject *brObj) const

Compare the original object of this with the original object of brobj.

 virtual CbcRangeCompare compareBranchingObject (const CbcBranchingObject *brObj, const bool replaceIf-Overlap=false)

Compare the this with brobj.

void computeNonzeroRange ()

Fill out the firstNonzero_ and lastNonzero_ data members.

Additional Inherited Members

7.95.1 Detailed Description

Branching object for Special ordered sets.

Variable_ is the set id number (redundant, as the object also holds a pointer to the set.

Definition at line 189 of file CbcSOS.hpp.

```
7.95.2 Constructor & Destructor Documentation
7.95.2.1 CbcSOSBranchingObject::CbcSOSBranchingObject()
       CbcSOSBranchingObject::CbcSOSBranchingObject ( CbcModel * model, const CbcSOS * clique, int way, double
7.95.2.2
        separator )
7.95.2.3 CbcSOSBranchingObject::CbcSOSBranchingObject ( const CbcSOSBranchingObject & )
7.95.2.4 virtual CbcSOSBranchingObject::~CbcSOSBranchingObject() [virtual]
7.95.3 Member Function Documentation
7.95.3.1 CbcSOSBranchingObject & CbcSOSBranchingObject & rhs )
7.95.3.2 virtual CbcBranchingObject* CbcSOSBranchingObject::clone() const [virtual]
Clone.
Implements CbcBranchingObject.
7.95.3.3 virtual double CbcSOSBranchingObject::branch() [virtual]
Does next branch and updates state.
Implements CbcBranchingObject.
7.95.3.4 virtual void CbcSOSBranchingObject::fix ( OsiSolverInterface * solver, double * lower, double * upper, int branchState )
        const [virtual]
Update bounds in solver as in 'branch' and update given bounds.
branchState is -1 for 'down' +1 for 'up'
Reimplemented from CbcBranchingObject.
7.95.3.5 virtual void CbcSOSBranchingObject::previousBranch() [inline], [virtual]
Reset every information so that the branching object appears to point to the previous child.
This method does not need to modify anything in any solver.
Reimplemented from CbcBranchingObject.
Definition at line 225 of file CbcSOS.hpp.
7.95.3.6 virtual void CbcSOSBranchingObject::print() [virtual]
Print something about branch - only if log level high.
7.95.3.7 virtual CbcBranchObjType CbcSOSBranchingObject::type( )const [inline], [virtual]
Return the type (an integer identifier) of this.
Implements CbcBranchingObject.
Definition at line 236 of file CbcSOS.hpp.
```

7.95.3.8 virtual int CbcSOSBranchingObject::compareOriginalObject (const CbcBranchingObject * brObj) const [virtual]

Compare the original object of this with the original object of brobj.

Assumes that there is an ordering of the original objects. This method should be invoked only if this and brObj are of the same type. Return negative/0/positive depending on whether this is smaller/same/larger than the argument.

Reimplemented from CbcBranchingObject.

7.95.3.9 virtual CbcRangeCompare CbcSOSBranchingObject::compareBranchingObject (const CbcBranchingObject * brObj, const bool replacelfOverlap = false) [virtual]

Compare the this with brObj.

this and brobj must be os the same type and must have the same original object, but they may have different feasible regions. Return the appropriate CbcRangeCompare value (first argument being the sub/superset if that's the case). In case of overlap (and if replaceIfoverlap is true) replace the current branching object with one whose feasible region is the overlap.

Implements CbcBranchingObject.

7.95.3.10 void CbcSOSBranchingObject::computeNonzeroRange ()

Fill out the firstNonzero_ and lastNonzero_ data members.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcSOS.hpp

7.96 CbcStatistics Class Reference

For gathering statistics.

#include <CbcStatistics.hpp>

Public Member Functions

- CbcStatistics ()
- CbcStatistics (CbcNode *node, CbcModel *model)
- ∼CbcStatistics ()
- CbcStatistics (const CbcStatistics &rhs)
- CbcStatistics & operator= (const CbcStatistics &rhs)
- void endOfBranch (int numberIterations, double objectiveValue)
- void updateInfeasibility (int numberInfeasibilities)
- void sayInfeasible ()
- void print (const int *sequenceLookup=NULL) const
- int node () const
- int parentNode () const
- int depth () const
- int way () const
- double value () const
- double startingObjective () const
- int startingInfeasibility () const
- double endingObjective () const
- int endingInfeasibility () const
- int numberIterations () const

Protected Attributes

```
    double value

           Value.
    • double startingObjective_
           Starting objective.

    double endingObjective_

           Ending objective.

    int id

           id

    int parentld

           parent id
    • int way_
           way -1 or +1 is first branch -10 or +10 is second branch
    • int sequence_
           sequence number branched on
    · int depth_
           depth
    · int startingInfeasibility_
           starting number of integer infeasibilities
    · int endingInfeasibility_
           ending number of integer infeasibilities

    int numberIterations

           number of iterations
7.96.1 Detailed Description
For gathering statistics.
Definition at line 13 of file CbcStatistics.hpp.
7.96.2 Constructor & Destructor Documentation
7.96.2.1 CbcStatistics::CbcStatistics ( )
7.96.2.2 CbcStatistics::CbcStatistics ( CbcNode * node, CbcModel * model )
7.96.2.3 CbcStatistics::~CbcStatistics()
7.96.2.4 CbcStatistics::CbcStatistics ( const CbcStatistics & rhs )
7.96.3 Member Function Documentation
7.96.3.1 CbcStatistics& CbcStatistics::operator= ( const CbcStatistics & rhs )
7.96.3.2 void CbcStatistics::endOfBranch (int numberIterations, double objectiveValue)
7.96.3.3
         void CbcStatistics::updateInfeasibility ( int numberInfeasibilities )
7.96.3.4 void CbcStatistics::sayInfeasible ( )
```

```
7.96.3.5 void CbcStatistics::print ( const int * sequenceLookup = NULL ) const
7.96.3.6 int CbcStatistics::node() const [inline]
Definition at line 34 of file CbcStatistics.hpp.
7.96.3.7 int CbcStatistics::parentNode() const [inline]
Definition at line 38 of file CbcStatistics.hpp.
7.96.3.8 int CbcStatistics::depth ( ) const [inline]
Definition at line 42 of file CbcStatistics.hpp.
7.96.3.9 int CbcStatistics::way ( ) const [inline]
Definition at line 46 of file CbcStatistics.hpp.
7.96.3.10 double CbcStatistics::value ( ) const [inline]
Definition at line 50 of file CbcStatistics.hpp.
7.96.3.11 double CbcStatistics::startingObjective ( ) const [inline]
Definition at line 54 of file CbcStatistics.hpp.
7.96.3.12 int CbcStatistics::startingInfeasibility ( ) const [inline]
Definition at line 58 of file CbcStatistics.hpp.
7.96.3.13 double CbcStatistics::endingObjective() const [inline]
Definition at line 62 of file CbcStatistics.hpp.
7.96.3.14 int CbcStatistics::endingInfeasibility ( ) const [inline]
Definition at line 66 of file CbcStatistics.hpp.
7.96.3.15 int CbcStatistics::numberIterations ( ) const [inline]
Definition at line 70 of file CbcStatistics.hpp.
7.96.4 Member Data Documentation
7.96.4.1 double CbcStatistics::value [protected]
Value.
Definition at line 77 of file CbcStatistics.hpp.
7.96.4.2 double CbcStatistics::startingObjective [protected]
Starting objective.
Definition at line 79 of file CbcStatistics.hpp.
```

```
7.96.4.3 double CbcStatistics::endingObjective [protected]
Ending objective.
Definition at line 81 of file CbcStatistics.hpp.
7.96.4.4 int CbcStatistics::id_ [protected]
id
Definition at line 83 of file CbcStatistics.hpp.
7.96.4.5 int CbcStatistics::parentId_ [protected]
parent id
Definition at line 85 of file CbcStatistics.hpp.
7.96.4.6 int CbcStatistics::way_ [protected]
way -1 or +1 is first branch -10 or +10 is second branch
Definition at line 87 of file CbcStatistics.hpp.
7.96.4.7 int CbcStatistics::sequence [protected]
sequence number branched on
Definition at line 89 of file CbcStatistics.hpp.
7.96.4.8 int CbcStatistics::depth_ [protected]
depth
Definition at line 91 of file CbcStatistics.hpp.
7.96.4.9 int CbcStatistics::startingInfeasibility_ [protected]
starting number of integer infeasibilities
Definition at line 93 of file CbcStatistics.hpp.
7.96.4.10 int CbcStatistics::endingInfeasibility_ [protected]
ending number of integer infeasibilities
Definition at line 95 of file CbcStatistics.hpp.
7.96.4.11 int CbcStatistics::numberIterations_ [protected]
number of iterations
Definition at line 97 of file CbcStatistics.hpp.
The documentation for this class was generated from the following file:
```

/home/ted/COIN/trunk/Cbc/src/CbcStatistics.hpp

7.97 CbcStopNow Class Reference

Support the use of a call back class to decide whether to stop.

```
#include <CbcSolver.hpp>
```

Public Member Functions

Decision methods

virtual int callBack (CbcModel *, int)
 Import.

Constructors and destructors etc

· CbcStopNow ()

Default Constructor.

CbcStopNow (const CbcStopNow &rhs)

Copy constructor.

CbcStopNow & operator= (const CbcStopNow &rhs)

Assignment operator.

virtual CbcStopNow * clone () const

Clone.

virtual ∼CbcStopNow ()

Destructor.

7.97.1 Detailed Description

Support the use of a call back class to decide whether to stop.

Definitely under construction.

Definition at line 351 of file CbcSolver.hpp.

```
7.97.2 Constructor & Destructor Documentation
```

```
7.97.2.1 CbcStopNow::CbcStopNow()
```

Default Constructor.

7.97.2.2 CbcStopNow::CbcStopNow (const CbcStopNow & rhs)

Copy constructor.

7.97.2.3 virtual CbcStopNow::~CbcStopNow() [virtual]

Destructor.

7.97.3 Member Function Documentation

7.97.3.1 virtual int CbcStopNow::callBack (CbcModel *, int) [inline], [virtual]

Import.

Values for whereFrom:

1 after initial solve by dualsimplex etc

- · 2 after preprocessing
- 3 just before branchAndBound (so user can override)
- 4 just after branchAndBound (before postprocessing)
- · 5 after postprocessing
- · 6 after a user called heuristic phase

Returns

0 if good nonzero return code to stop

Definition at line 369 of file CbcSolver.hpp.

7.97.3.2 CbcStopNow& CbcStopNow::operator= (const CbcStopNow & rhs)

Assignment operator.

7.97.3.3 virtual CbcStopNow* CbcStopNow::clone() const [virtual]

Clone.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcSolver.hpp

7.98 CbcStrategy Class Reference

Strategy base class.

#include <CbcStrategy.hpp>

Inheritance diagram for CbcStrategy:



Public Member Functions

- CbcStrategy ()
- virtual ∼CbcStrategy ()
- virtual CbcStrategy * clone () const =0

Clone

• virtual void setupCutGenerators (CbcModel &model)=0

Setup cut generators.

virtual void setupHeuristics (CbcModel &model)=0

Setup heuristics.

virtual void setupPrinting (CbcModel &model, int modelLogLevel)=0

Do printing stuff.

virtual void setupOther (CbcModel &model)=0

Other stuff e.g. strong branching and preprocessing.

void setNested (int depth)

Set model depth (i.e. how nested)

• int getNested () const

Get model depth (i.e. how nested)

void setPreProcessState (int state)

Say preProcessing done.

• int preProcessState () const

See what sort of preprocessing was done.

• CglPreProcess * process () const

Pre-processing object.

· void deletePreProcess ()

Delete pre-processing object to save memory.

virtual CbcNodeInfo * fullNodeInfo (CbcModel *model, int numberRowsAtContinuous) const

Return a new Full node information pointer (descendant of CbcFullNodeInfo)

 virtual CbcNodeInfo * partialNodeInfo (CbcModel *model, CbcNodeInfo *parent, CbcNode *owner, int number-ChangedBounds, const int *variables, const double *boundChanges, const CoinWarmStartDiff *basisDiff) const

Return a new Partial node information pointer (descendant of CbcPartialNodeInfo)

virtual void generateCpp (FILE *)

Create C++ lines to get to current state.

virtual int status (CbcModel *model, CbcNodeInfo *parent, int whereFrom)

After a CbcModel::resolve this can return a status -1 no effect 0 treat as optimal 1 as 0 but do not do any more resolves (i.e.

Protected Attributes

• int depth_

Model depth.

int preProcessState_

PreProcessing state - -1 infeasible 0 off 1 was done (so need post-processing)

• CglPreProcess * process

If preprocessing then this is object.

7.98.1 Detailed Description

Strategy base class.

Definition at line 18 of file CbcStrategy.hpp.

7.98.2 Constructor & Destructor Documentation

7.98.2.1 CbcStrategy::CbcStrategy()

7.98.2.2 virtual CbcStrategy::~CbcStrategy() [virtual]

7.98.3 Member Function Documentation

```
7.98.3.1
        virtual CbcStrategy* CbcStrategy::clone( ) const [pure virtual]
Clone.
Implemented in CbcStrategyDefaultSubTree, CbcStrategyDefault, and CbcStrategyNull.
7.98.3.2 virtual void CbcStrategy::setupCutGenerators ( CbcModel & model ) [pure virtual]
Setup cut generators.
Implemented in CbcStrategyDefaultSubTree, CbcStrategyDefault, and CbcStrategyNull.
7.98.3.3 virtual void CbcStrategy::setupHeuristics ( CbcModel & model ) [pure virtual]
Setup heuristics.
Implemented in CbcStrategyDefaultSubTree, CbcStrategyDefault, and CbcStrategyNull.
7.98.3.4 virtual void CbcStrategy::setupPrinting ( CbcModel & model, int modelLogLevel ) [pure virtual]
Do printing stuff.
Implemented in CbcStrategyDefaultSubTree, CbcStrategyDefault, and CbcStrategyNull.
7.98.3.5 virtual void CbcStrategy::setupOther ( CbcModel & model ) [pure virtual]
Other stuff e.g. strong branching and preprocessing.
Implemented in CbcStrategyDefaultSubTree, CbcStrategyDefault, and CbcStrategyNull.
7.98.3.6 void CbcStrategy::setNested (int depth ) [inline]
Set model depth (i.e. how nested)
Definition at line 37 of file CbcStrategy.hpp.
7.98.3.7 int CbcStrategy::getNested ( ) const [inline]
Get model depth (i.e. how nested)
Definition at line 41 of file CbcStrategy.hpp.
7.98.3.8 void CbcStrategy::setPreProcessState (int state) [inline]
Say preProcessing done.
Definition at line 45 of file CbcStrategy.hpp.
7.98.3.9 int CbcStrategy::preProcessState() const [inline]
See what sort of preprocessing was done.
Definition at line 49 of file CbcStrategy.hpp.
7.98.3.10 CglPreProcess* CbcStrategy::process() const [inline]
Pre-processing object.
Definition at line 53 of file CbcStrategy.hpp.
```

7.98.3.11 void CbcStrategy::deletePreProcess ()

Delete pre-processing object to save memory.

7.98.3.12 virtual CbcNodeInfo* CbcStrategy::fullNodeInfo (CbcModeI * model, int numberRowsAtContinuous) const [virtual]

Return a new Full node information pointer (descendant of CbcFullNodeInfo)

7.98.3.13 virtual CbcNodeInfo* CbcStrategy::partialNodeInfo (CbcModeI * model, CbcNodeInfo * parent, CbcNode * owner, int numberChangedBounds, const int * variables, const double * boundChanges, const CoinWarmStartDiff * basisDiff) const [virtual]

Return a new Partial node information pointer (descendant of CbcPartialNodeInfo)

7.98.3.14 virtual void CbcStrategy::generateCpp (FILE *) [inline], [virtual]

Create C++ lines to get to current state.

Reimplemented in CbcStrategyDefault.

Definition at line 66 of file CbcStrategy.hpp.

7.98.3.15 virtual int CbcStrategy::status (CbcModel * model, CbcNodelnfo * parent, int whereFrom) [virtual]

After a CbcModel::resolve this can return a status -1 no effect 0 treat as optimal 1 as 0 but do not do any more resolves (i.e.

no more cuts) 2 treat as infeasible

7.98.4 Member Data Documentation

7.98.4.1 int CbcStrategy::depth_ [protected]

Model depth.

Definition at line 81 of file CbcStrategy.hpp.

7.98.4.2 int CbcStrategy::preProcessState_ [protected]

PreProcessing state - -1 infeasible 0 off 1 was done (so need post-processing)

Definition at line 87 of file CbcStrategy.hpp.

7.98.4.3 CglPreProcess* CbcStrategy::process_ [protected]

If preprocessing then this is object.

Definition at line 89 of file CbcStrategy.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcStrategy.hpp

7.99 CbcStrategyDefault Class Reference

Default class.

#include <CbcStrategy.hpp>

Inheritance diagram for CbcStrategyDefault:



Public Member Functions

- CbcStrategyDefault (int cutsOnlyAtRoot=1, int numberStrong=5, int numberBeforeTrust=0, int printLevel=0)
- CbcStrategyDefault (const CbcStrategyDefault &)
- ∼CbcStrategyDefault ()
- virtual CbcStrategy * clone () const

Clone

virtual void setupCutGenerators (CbcModel &model)

Setup cut generators.

virtual void setupHeuristics (CbcModel &model)

Setup heuristics.

virtual void setupPrinting (CbcModel &model, int modelLogLevel)

Do printing stuff.

• virtual void setupOther (CbcModel &model)

Other stuff e.g. strong branching.

void setupPreProcessing (int desired=1, int passes=10)

Set up preProcessing - see below.

· int desiredPreProcess () const

See what sort of preprocessing wanted.

• int preProcessPasses () const

See how many passes wanted.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

Protected Attributes

- int cutsOnlyAtRoot_
- int numberStrong_
- int numberBeforeTrust
- int printLevel_
- int desiredPreProcess_

Desired pre-processing 0 - none 1 - ordinary 2 - find sos 3 - find cliques 4 - more aggressive sos 5 - add integer slacks.

int preProcessPasses

Number of pre-processing passes.

7.99.1 Detailed Description

Default class.

Definition at line 131 of file CbcStrategy.hpp.

```
7.99.2 Constructor & Destructor Documentation
7.99.2.1 CbcStrategyDefault::CbcStrategyDefault (int cutsOnlyAtRoot = 1, int numberStrong = 5, int numberBeforeTrust = 0, int
         printLevel = 0)
7.99.2.2 CbcStrategyDefault::CbcStrategyDefault ( const CbcStrategyDefault & )
7.99.2.3 CbcStrategyDefault::~CbcStrategyDefault ( )
7.99.3 Member Function Documentation
7.99.3.1 virtual CbcStrategy* CbcStrategyDefault::clone( )const [virtual]
Clone.
Implements CbcStrategy.
7.99.3.2 virtual void CbcStrategyDefault::setupCutGenerators ( CbcModel & model ) [virtual]
Setup cut generators.
Implements CbcStrategy.
7.99.3.3 virtual void CbcStrategyDefault::setupHeuristics ( CbcModel & model ) [virtual]
Setup heuristics.
Implements CbcStrategy.
7.99.3.4 virtual void CbcStrategyDefault::setupPrinting ( CbcModel & model, int modelLogLevel ) [virtual]
Do printing stuff.
Implements CbcStrategy.
7.99.3.5 virtual void CbcStrategyDefault::setupOther ( CbcModel & model ) [virtual]
Other stuff e.g. strong branching.
Implements CbcStrategy.
7.99.3.6 void CbcStrategyDefault::setupPreProcessing (int desired = 1, int passes = 10) [inline]
Set up preProcessing - see below.
Definition at line 158 of file CbcStrategy.hpp.
7.99.3.7 int CbcStrategyDefault::desiredPreProcess ( ) const [inline]
See what sort of preprocessing wanted.
Definition at line 163 of file CbcStrategy.hpp.
7.99.3.8 int CbcStrategyDefault::preProcessPasses ( ) const [inline]
See how many passes wanted.
Definition at line 167 of file CbcStrategy.hpp.
```

7.99.3.9 virtual void CbcStrategyDefault::generateCpp (FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcStrategy.

7.99.4 Member Data Documentation

7.99.4.1 int CbcStrategyDefault::cutsOnlyAtRoot_ [protected]

Definition at line 177 of file CbcStrategy.hpp.

7.99.4.2 int CbcStrategyDefault::numberStrong_ [protected]

Definition at line 180 of file CbcStrategy.hpp.

7.99.4.3 int CbcStrategyDefault::numberBeforeTrust_ [protected]

Definition at line 183 of file CbcStrategy.hpp.

7.99.4.4 int CbcStrategyDefault::printLevel_ [protected]

Definition at line 186 of file CbcStrategy.hpp.

7.99.4.5 int CbcStrategyDefault::desiredPreProcess_ [protected]

Desired pre-processing 0 - none 1 - ordinary 2 - find sos 3 - find cliques 4 - more aggressive sos 5 - add integer slacks.

Definition at line 196 of file CbcStrategy.hpp.

7.99.4.6 int CbcStrategyDefault::preProcessPasses_ [protected]

Number of pre-processing passes.

Definition at line 198 of file CbcStrategy.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcStrategy.hpp

7.100 CbcStrategyDefaultSubTree Class Reference

Default class for sub trees.

#include <CbcStrategy.hpp>

Inheritance diagram for CbcStrategyDefaultSubTree:



Public Member Functions

- CbcStrategyDefaultSubTree (CbcModel *parent=NULL, int cutsOnlyAtRoot=1, int numberStrong=5, int number-BeforeTrust=0, int printLevel=0)
- CbcStrategyDefaultSubTree (const CbcStrategyDefaultSubTree &)
- ∼CbcStrategyDefaultSubTree ()
- virtual CbcStrategy * clone () const

Clone.

virtual void setupCutGenerators (CbcModel &model)

Setup cut generators.

virtual void setupHeuristics (CbcModel &model)

Setup heuristics.

virtual void setupPrinting (CbcModel &model, int modelLogLevel)

Do printing stuff.

virtual void setupOther (CbcModel &model)

Other stuff e.g. strong branching.

Protected Attributes

- CbcModel * parentModel
- int cutsOnlyAtRoot
- int numberStrong
- int numberBeforeTrust_
- int printLevel_

7.100.1 Detailed Description

Default class for sub trees.

Definition at line 209 of file CbcStrategy.hpp.

7.100.2 Constructor & Destructor Documentation

```
7.100.2.1 CbcStrategyDefaultSubTree::CbcStrategyDefaultSubTree ( CbcModel * parent = \mathtt{NULL}, int cutsOnlyAtRoot = 1, int numberStrong = 5, int numberBeforeTrust = 0, int printLevel = 0 )
```

7.100.2.2 CbcStrategyDefaultSubTree::CbcStrategyDefaultSubTree (const CbcStrategyDefaultSubTree &)

7.100.2.3 CbcStrategyDefaultSubTree:: CbcStrategyDefaultSubTree ()

7.100.3 Member Function Documentation

7.100.3.1 virtual CbcStrategy* CbcStrategyDefaultSubTree::clone()const [virtual]

Clone.

Implements CbcStrategy.

7.100.3.2 virtual void CbcStrategyDefaultSubTree::setupCutGenerators (CbcModel & model) [virtual]

Setup cut generators.

Implements CbcStrategy.

7.100.3.3 virtual void CbcStrategyDefaultSubTree::setupHeuristics (CbcModel & model) [virtual] Setup heuristics. Implements CbcStrategy. 7.100.3.4 virtual void CbcStrategyDefaultSubTree::setupPrinting (CbcModel & model, int modelLogLevel) [virtual] Do printing stuff. Implements CbcStrategy. 7.100.3.5 virtual void CbcStrategyDefaultSubTree::setupOther (CbcModel & model) [virtual] Other stuff e.g. strong branching. Implements CbcStrategy. 7.100.4 Member Data Documentation 7.100.4.1 CbcModel* CbcStrategyDefaultSubTree::parentModel_ [protected] Definition at line 238 of file CbcStrategy.hpp. **7.100.4.2** int CbcStrategyDefaultSubTree::cutsOnlyAtRoot_ [protected] Definition at line 240 of file CbcStrategy.hpp. 7.100.4.3 int CbcStrategyDefaultSubTree::numberStrong_ [protected] Definition at line 243 of file CbcStrategy.hpp. **7.100.4.4** int CbcStrategyDefaultSubTree::numberBeforeTrust_ [protected] Definition at line 246 of file CbcStrategy.hpp. 7.100.4.5 int CbcStrategyDefaultSubTree::printLevel_ [protected] Definition at line 249 of file CbcStrategy.hpp. The documentation for this class was generated from the following file: /home/ted/COIN/trunk/Cbc/src/CbcStrategy.hpp 7.101 CbcStrategyNull Class Reference Null class. #include <CbcStrategy.hpp>

Inheritance diagram for CbcStrategyNull:



Public Member Functions

```
    CbcStrategyNull ()
```

- CbcStrategyNull (const CbcStrategyNull &rhs)
- CbcStrategyNull ()
- virtual CbcStrategy * clone () const

Clone

virtual void setupCutGenerators (CbcModel &)

Setup cut generators.

virtual void setupHeuristics (CbcModel &)

Setup heuristics.

virtual void setupPrinting (CbcModel &, int)

Do printing stuff.

virtual void setupOther (CbcModel &)

Other stuff e.g. strong branching.

Additional Inherited Members

7.101.1 Detailed Description

Null class.

Definition at line 95 of file CbcStrategy.hpp.

7.101.2 Constructor & Destructor Documentation

7.101.2.1 CbcStrategyNull::CbcStrategyNull() [inline]

Definition at line 99 of file CbcStrategy.hpp.

7.101.2.2 CbcStrategyNull::CbcStrategyNull (const CbcStrategyNull & rhs) [inline]

Definition at line 102 of file CbcStrategy.hpp.

7.101.2.3 CbcStrategyNull::~CbcStrategyNull() [inline]

Definition at line 105 of file CbcStrategy.hpp.

7.101.3 Member Function Documentation

7.101.3.1 virtual CbcStrategy* CbcStrategyNull::clone() const [inline], [virtual]

Clone.

Implements CbcStrategy.

Definition at line 108 of file CbcStrategy.hpp.

7.101.3.2 virtual void CbcStrategyNull::setupCutGenerators (CbcModel &) [inline], [virtual]

Setup cut generators.

Implements CbcStrategy.

Definition at line 113 of file CbcStrategy.hpp.

7.101.3.3 virtual void CbcStrategyNull::setupHeuristics (CbcModel &) [inline], [virtual]

Setup heuristics.

Implements CbcStrategy.

Definition at line 115 of file CbcStrategy.hpp.

7.101.3.4 virtual void CbcStrategyNull::setupPrinting (CbcModel & , int) [inline], [virtual]

Do printing stuff.

Implements CbcStrategy.

Definition at line 117 of file CbcStrategy.hpp.

7.101.3.5 virtual void CbcStrategyNull::setupOther (CbcModel &) [inline], [virtual]

Other stuff e.g. strong branching.

Implements CbcStrategy.

Definition at line 119 of file CbcStrategy.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcStrategy.hpp

7.102 CbcStrongInfo Struct Reference

Abstract base class for 'objects'.

#include <CbcObject.hpp>

Public Attributes

- CbcBranchingObject * possibleBranch
- double upMovement
- double downMovement
- int numIntInfeasUp
- int numObjInfeasUp
- bool finishedUp
- int numltersUpint numlntlnfeasDown
- int numObjInfeasDown
- bool finishedDown
- int numItersDown
- · int objectNumber
- int fix

7.102.1 Detailed Description

Abstract base class for 'objects'.

It now just has stuff that OsiObject does not have

The branching model used in Cbc is based on the idea of an *object*. In the abstract, an object is something that has a feasible region, can be evaluated for infeasibility, can be branched on (*i.e.*, there's some constructive action to be taken to move toward feasibility), and allows comparison of the effect of branching.

This class (CbcObject) is the base class for an object. To round out the branching model, the class CbcBranchingObject describes how to perform a branch, and the class CbcBranchDecision describes how to compare two CbcBranching-Objects.

To create a new type of object you need to provide three methods: #infeasibility(), #feasibleRegion(), and #createCbc-Branch(), described below.

This base class is primarily virtual to allow for any form of structure. Any form of discontinuity is allowed.

Todo The notion that all branches are binary (two arms) is wired into the implementation of CbcObject, CbcBranching-Object, and CbcBranchDecision. Changing this will require a moderate amount of recoding.

Definition at line 51 of file CbcObject.hpp.

7.102.2 Member Data Documentation

7.102.2.1 CbcBranchingObject* CbcStrongInfo::possibleBranch

Definition at line 52 of file CbcObject.hpp.

7.102.2.2 double CbcStrongInfo::upMovement

Definition at line 53 of file CbcObject.hpp.

7.102.2.3 double CbcStrongInfo::downMovement

Definition at line 54 of file CbcObject.hpp.

7.102.2.4 int CbcStrongInfo::numIntInfeasUp

Definition at line 55 of file CbcObject.hpp.

7.102.2.5 int CbcStrongInfo::numObjInfeasUp

Definition at line 56 of file CbcObject.hpp.

7.102.2.6 bool CbcStrongInfo::finishedUp

Definition at line 57 of file CbcObject.hpp.

7.102.2.7 int CbcStrongInfo::numItersUp

Definition at line 58 of file CbcObject.hpp.

7.102.2.8 int CbcStrongInfo::numIntInfeasDown

Definition at line 59 of file CbcObject.hpp.

7.102.2.9 int CbcStrongInfo::numObjInfeasDown

Definition at line 60 of file CbcObject.hpp.

7.102.2.10 bool CbcStrongInfo::finishedDown

Definition at line 61 of file CbcObject.hpp.

7.102.2.11 int CbcStrongInfo::numItersDown

Definition at line 62 of file CbcObject.hpp.

7.102.2.12 int CbcStrongInfo::objectNumber

Definition at line 63 of file CbcObject.hpp.

7.102.2.13 int CbcStrongInfo::fix

Definition at line 64 of file CbcObject.hpp.

The documentation for this struct was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcObject.hpp

7.103 CbcThread Class Reference

A class to encapsulate thread stuff.

```
#include <CbcThread.hpp>
```

Public Member Functions

- CbcThread ()
- virtual ∼CbcThread ()

7.103.1 Detailed Description

A class to encapsulate thread stuff.

Definition at line 418 of file CbcThread.hpp.

7.103.2 Constructor & Destructor Documentation

```
7.103.2.1 CbcThread::CbcThread() [inline]
```

Definition at line 421 of file CbcThread.hpp.

```
7.103.2.2 virtual CbcThread::~CbcThread( ) [inline],[virtual]
```

Definition at line 423 of file CbcThread.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcThread.hpp

7.104 CbcTree Class Reference

Using MS heap implementation.

#include <CbcTree.hpp>

Inheritance diagram for CbcTree:



Public Member Functions

Constructors and related

• CbcTree ()

Default Constructor.

CbcTree (const CbcTree &rhs)

Copy constructor.

• CbcTree & operator= (const CbcTree &rhs)

= operator

virtual ∼CbcTree ()

Destructor.

virtual CbcTree * clone () const

Clone.

virtual void generateCpp (FILE *)

Create C++ lines to get to current state.

Heap access and maintenance methods

void setComparison (CbcCompareBase &compare)

Set comparison function and resort heap.

virtual CbcNode * top () const

Return the top node of the heap.

virtual void push (CbcNode *x)

Add a node to the heap.

• virtual void pop ()

Remove the top node from the heap.

virtual CbcNode * bestNode (double cutoff)

Gets best node and takes off heap.

virtual void rebuild ()

Rebuild the heap.

Direct node access methods

• virtual bool empty ()

Test for an empty tree.

• virtual int size () const

Return size.

• CbcNode * operator[] (int i) const

Return a node pointer.

CbcNode * nodePointer (int i) const

Return a node pointer.

- void realpop ()
- void fixTop ()

After changing data in the top node, fix the heap.

void realpush (CbcNode *node)

Search tree maintenance

virtual void cleanTree (CbcModel *model, double cutoff, double &bestPossibleObjective)

Prune the tree using an objective function cutoff.

CbcNode * bestAlternate ()

Get best on list using alternate method.

virtual void endSearch ()

We may have got an intelligent tree so give it one more chance.

virtual double getBestPossibleObjective ()

Get best possible objective function in the tree.

void resetNodeNumbers ()

Reset maximum node number.

• int maximumNodeNumber () const

Get maximum node number.

• void setNumberBranching (int value)

Set number of branches.

• int getNumberBranching () const

Get number of branches.

void setMaximumBranching (int value)

Set maximum branches.

• int getMaximumBranching () const

Get maximum branches.

unsigned int * branched () const

Get branched variables.

int * newBounds () const

Get bounds

· double lastObjective () const

Last objective in branch-and-cut search tree.

int lastDepth () const

Last depth in branch-and-cut search tree.

• int lastUnsatisfied () const

Last number of objects unsatisfied.

 void addBranchingInformation (const CbcModel *model, const CbcNodeInfo *nodeInfo, const double *current-Lower, const double *currentUpper)

Adds branching information to complete state.

void increaseSpace ()

Increase space for data.

Protected Attributes

std::vector< CbcNode * > nodes_

Storage vector for the heap.

CbcCompare comparison_

Sort predicate for heap ordering.

int maximumNodeNumber

Maximum "node" number so far to split ties.

· int numberBranching_

Size of variable list.

int maximumBranching

Maximum size of variable list.

double lastObjective

Objective of last node pushed on tree.

int lastDepth

Depth of last node pushed on tree.

int lastUnsatisfied_

Number unsatisfied of last node pushed on tree.

unsigned int * branched

Integer variables branched or bounded top bit set if new upper bound next bit set if a branch.

int * newBound

New bound.

7.104.1 Detailed Description

Using MS heap implementation.

It's unclear if this is needed any longer, or even if it should be allowed. Cbc occasionally tries to do things to the tree (typically tweaking the comparison predicate) that can cause a violation of the heap property (parent better than either child). In a debug build, Microsoft's heap implementation does checks that detect this and fail. This symbol switched to an alternate implementation of CbcTree, and there are clearly differences, but no explanation as to why or what for.

As of 100921, the code is cleaned up to make it through 'cbc -unitTest' without triggering 'Invalid heap' in an MSVS debug build. The method validateHeap() can be used for debugging if this turns up again.

Controls search tree debugging

In order to have validateHeap() available, set CBC_DEBUG_HEAP to 1 or higher.

- 1 calls validateHeap() after each change to the heap
- 2 will print a line for major operations (clean, set comparison, etc.)
- · 3 will print information about each push and pop

```
#define CBC_DEBUG_HEAP 1
```

Implementation of the live set as a heap.

This class is used to hold the set of live nodes in the search tree.

Definition at line 53 of file CbcTree.hpp.

7.104.2 Constructor & Destructor Documentation

```
7.104.2.1 CbcTree::CbcTree()
```

Default Constructor.

7.104.2.2 CbcTree::CbcTree (const CbcTree & rhs)

Copy constructor.

7.104.2.3 virtual CbcTree::~CbcTree() [virtual]

Destructor.

7.104.3 Member Function Documentation

Reimplemented in CbcTreeVariable, and CbcTreeLocal.

```
7.104.3.1 CbcTree& CbcTree::operator= ( const CbcTree & rhs )
= operator
7.104.3.2 virtual CbcTree* CbcTree::clone() const [virtual]
Clone.
Reimplemented in CbcTreeVariable, and CbcTreeLocal.
7.104.3.3 virtual void CbcTree::generateCpp(FILE * ) [inline], [virtual]
Create C++ lines to get to current state.
Reimplemented in CbcTreeVariable, and CbcTreeLocal.
Definition at line 74 of file CbcTree.hpp.
7.104.3.4 void CbcTree::setComparison ( CbcCompareBase & compare )
Set comparison function and resort heap.
7.104.3.5 virtual CbcNode* CbcTree::top( )const [virtual]
Return the top node of the heap.
Reimplemented in CbcTreeVariable, and CbcTreeLocal.
7.104.3.6 virtual void CbcTree::push ( CbcNode * x ) [virtual]
Add a node to the heap.
Reimplemented in CbcTreeVariable, and CbcTreeLocal.
7.104.3.7 virtual void CbcTree::pop() [virtual]
Remove the top node from the heap.
Reimplemented in CbcTreeVariable, and CbcTreeLocal.
7.104.3.8 virtual CbcNode* CbcTree::bestNode ( double cutoff ) [virtual]
Gets best node and takes off heap.
Before returning the node from the top of the heap, the node is offered an opportunity to reevaluate itself. Callers should
be prepared to check that the node returned is suitable for use.
7.104.3.9 virtual void CbcTree::rebuild( ) [virtual]
Rebuild the heap.
7.104.3.10 virtual bool CbcTree::empty() [virtual]
Test for an empty tree.
```

```
7.104.3.11 virtual int CbcTree::size ( ) const [inline], [virtual]
Return size.
Definition at line 109 of file CbcTree.hpp.
7.104.3.12 CbcNode* CbcTree::operator[]( int i) const [inline]
Return a node pointer.
Definition at line 112 of file CbcTree.hpp.
7.104.3.13 CbcNode* CbcTree::nodePointer(inti)const [inline]
Return a node pointer.
Definition at line 115 of file CbcTree.hpp.
7.104.3.14 void CbcTree::realpop()
7.104.3.15 void CbcTree::fixTop ( )
After changing data in the top node, fix the heap.
7.104.3.16 void CbcTree::realpush ( CbcNode * node )
7.104.3.17 virtual void CbcTree::cleanTree ( CbcModel * model, double cutoff, double & bestPossibleObjective ) [virtual]
Prune the tree using an objective function cutoff.
This routine removes all nodes with objective worse than the specified cutoff value. It also sets bestPossibleObjective
to the best objective over remaining nodes.
7.104.3.18 CbcNode* CbcTree::bestAlternate ( )
Get best on list using alternate method.
7.104.3.19 virtual void CbcTree::endSearch() [inline], [virtual]
We may have got an intelligent tree so give it one more chance.
Reimplemented in CbcTreeVariable, and CbcTreeLocal.
Definition at line 136 of file CbcTree.hpp.
7.104.3.20 virtual double CbcTree::getBestPossibleObjective() [virtual]
Get best possible objective function in the tree.
7.104.3.21 void CbcTree::resetNodeNumbers ( ) [inline]
Reset maximum node number.
Definition at line 142 of file CbcTree.hpp.
7.104.3.22 int CbcTree::maximumNodeNumber() const [inline]
Get maximum node number.
Definition at line 145 of file CbcTree.hpp.
```

```
7.104.3.23 void CbcTree::setNumberBranching (int value) [inline]
Set number of branches.
Definition at line 148 of file CbcTree.hpp.
7.104.3.24 int CbcTree::getNumberBranching ( ) const [inline]
Get number of branches.
Definition at line 151 of file CbcTree.hpp.
7.104.3.25 void CbcTree::setMaximumBranching (int value ) [inline]
Set maximum branches.
Definition at line 154 of file CbcTree.hpp.
7.104.3.26 int CbcTree::getMaximumBranching ( ) const [inline]
Get maximum branches.
Definition at line 157 of file CbcTree.hpp.
7.104.3.27 unsigned int* CbcTree::branched ( ) const [inline]
Get branched variables.
Definition at line 160 of file CbcTree.hpp.
7.104.3.28 int* CbcTree::newBounds() const [inline]
Get bounds.
Definition at line 163 of file CbcTree.hpp.
7.104.3.29 double CbcTree::lastObjective ( ) const [inline]
Last objective in branch-and-cut search tree.
Definition at line 166 of file CbcTree.hpp.
7.104.3.30 int CbcTree::lastDepth ( ) const [inline]
Last depth in branch-and-cut search tree.
Definition at line 170 of file CbcTree.hpp.
7.104.3.31 int CbcTree::lastUnsatisfied ( ) const [inline]
Last number of objects unsatisfied.
Definition at line 174 of file CbcTree.hpp.
7.104.3.32 void CbcTree::addBranchingInformation ( const CbcModel * model, const CbcNodeInfo * nodeInfo, const double *
           currentLower, const double * currentUpper )
Adds branching information to complete state.
7.104.3.33 void CbcTree::increaseSpace ( )
Increase space for data.
```

7.104.4 Member Data Documentation

7.104.4.1 std::vector < CbcNode *> CbcTree::nodes_ [protected]

Storage vector for the heap.

Definition at line 195 of file CbcTree.hpp.

7.104.4.2 CbcCompare CbcTree::comparison [protected]

Sort predicate for heap ordering.

Definition at line 197 of file CbcTree.hpp.

7.104.4.3 int CbcTree::maximumNodeNumber_ [protected]

Maximum "node" number so far to split ties.

Definition at line 199 of file CbcTree.hpp.

7.104.4.4 int CbcTree::numberBranching_ [protected]

Size of variable list.

Definition at line 201 of file CbcTree.hpp.

7.104.4.5 int CbcTree::maximumBranching [protected]

Maximum size of variable list.

Definition at line 203 of file CbcTree.hpp.

7.104.4.6 double CbcTree::lastObjective_ [protected]

Objective of last node pushed on tree.

Definition at line 205 of file CbcTree.hpp.

7.104.4.7 int CbcTree::lastDepth_ [protected]

Depth of last node pushed on tree.

Definition at line 207 of file CbcTree.hpp.

7.104.4.8 int CbcTree::lastUnsatisfied_ [protected]

Number unsatisfied of last node pushed on tree.

Definition at line 209 of file CbcTree.hpp.

7.104.4.9 unsigned int* CbcTree::branched [protected]

Integer variables branched or bounded top bit set if new upper bound next bit set if a branch.

Definition at line 214 of file CbcTree.hpp.

7.104.4.10 int* CbcTree::newBound_ [protected]

New bound.

Definition at line 216 of file CbcTree.hpp.


The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcTree.hpp

7.105 CbcTreeLocal Class Reference

#include <CbcTreeLocal.hpp>

Inheritance diagram for CbcTreeLocal:



Public Member Functions

- CbcTreeLocal ()
- CbcTreeLocal (CbcModel *model, const double *solution, int range=10, int typeCuts=0, int maxDiversification=0, int timeLimit=1000000, int nodeLimit=1000000, bool refine=true)
- CbcTreeLocal (const CbcTreeLocal &rhs)
- CbcTreeLocal & operator= (const CbcTreeLocal &rhs)
- virtual ∼CbcTreeLocal ()
- virtual CbcTree * clone () const

Clone.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

Heap access and maintenance methods

virtual CbcNode * top () const

Return the top node of the heap.

virtual void push (CbcNode *x)

Add a node to the heap.

• virtual void pop ()

Remove the top node from the heap.

Other stuff

• int createCut (const double *solution, OsiRowCut &cut)

Create cut - return -1 if bad, 0 if okay and 1 if cut is everything.

• virtual bool empty ()

Test if empty *** note may be overridden.

virtual void endSearch ()

We may have got an intelligent tree so give it one more chance.

void reverseCut (int state, double bias=0.0)

Other side of last cut branch (if bias==rhs_ will be weakest possible)

void deleteCut (OsiRowCut &cut)

Delete last cut branch.

void passInSolution (const double *solution, double solutionValue)

Pass in solution (so can be used after heuristic)

- int range () const
- void setRange (int value)
- int typeCuts () const
- void setTypeCuts (int value)
- int maxDiversification () const
- void setMaxDiversification (int value)
- int timeLimit () const
- void setTimeLimit (int value)
- int nodeLimit () const
- void setNodeLimit (int value)
- bool refine () const
- void setRefine (bool yesNo)

Additional Inherited Members

7.105.1 Detailed Description

Definition at line 40 of file CbcTreeLocal.hpp.

```
7.105.2 Constructor & Destructor Documentation
```

```
7.105.2.1 CbcTreeLocal::CbcTreeLocal()
```

7.105.2.2 CbcTreeLocal::CbcTreeLocal (CbcModel * model, const double * solution, int range = 10, int typeCuts = 0, int maxDiversification = 0, int timeLimit = 1000000, int nodeLimit = 1000000, bool refine = true)

7.105.2.3 CbcTreeLocal::CbcTreeLocal (const CbcTreeLocal & rhs)

7.105.2.4 virtual CbcTreeLocal:: ~ CbcTreeLocal() [virtual]

7.105.3 Member Function Documentation

7.105.3.1 CbcTreeLocal& CbcTreeLocal::operator= (const CbcTreeLocal & rhs)

7.105.3.2 virtual CbcTree* CbcTreeLocal::clone() const [virtual]

Clone.

Reimplemented from CbcTree.

7.105.3.3 virtual void CbcTreeLocal::generateCpp (FILE * fp) [virtual]

Create C++ lines to get to current state.

Reimplemented from CbcTree.

7.105.3.4 virtual CbcNode* CbcTreeLocal::top() const [virtual]

Return the top node of the heap.

Reimplemented from CbcTree.

7.105.3.5 virtual void CbcTreeLocal::push (CbcNode * x) [virtual]

Add a node to the heap.

Reimplemented from CbcTree.

```
7.105.3.6 virtual void CbcTreeLocal::pop() [virtual]
Remove the top node from the heap.
Reimplemented from CbcTree.
7.105.3.7 int CbcTreeLocal::createCut ( const double * solution, OsiRowCut & cut )
Create cut - return -1 if bad, 0 if okay and 1 if cut is everything.
7.105.3.8 virtual bool CbcTreeLocal::empty() [virtual]
Test if empty *** note may be overridden.
Reimplemented from CbcTree.
7.105.3.9 virtual void CbcTreeLocal::endSearch() [virtual]
We may have got an intelligent tree so give it one more chance.
Reimplemented from CbcTree.
7.105.3.10 void CbcTreeLocal::reverseCut ( int state, double bias = 0.0 )
Other side of last cut branch (if bias==rhs_ will be weakest possible)
7.105.3.11 void CbcTreeLocal::deleteCut ( OsiRowCut & cut )
Delete last cut branch.
7.105.3.12 void CbcTreeLocal::passInSolution ( const double * solution, double solutionValue )
Pass in solution (so can be used after heuristic)
7.105.3.13 int CbcTreeLocal::range ( ) const [inline]
Definition at line 107 of file CbcTreeLocal.hpp.
7.105.3.14 void CbcTreeLocal::setRange (int value) [inline]
Definition at line 111 of file CbcTreeLocal.hpp.
7.105.3.15 int CbcTreeLocal::typeCuts() const [inline]
Definition at line 115 of file CbcTreeLocal.hpp.
7.105.3.16 void CbcTreeLocal::setTypeCuts(int value) [inline]
Definition at line 119 of file CbcTreeLocal.hpp.
7.105.3.17 int CbcTreeLocal::maxDiversification ( ) const [inline]
Definition at line 123 of file CbcTreeLocal.hpp.
7.105.3.18 void CbcTreeLocal::setMaxDiversification (int value) [inline]
Definition at line 127 of file CbcTreeLocal.hpp.
```

7.105.3.19 int CbcTreeLocal::timeLimit() const [inline]

Definition at line 131 of file CbcTreeLocal.hpp.

7.105.3.20 void CbcTreeLocal::setTimeLimit(int value) [inline]

Definition at line 135 of file CbcTreeLocal.hpp.

7.105.3.21 int CbcTreeLocal::nodeLimit() const [inline]

Definition at line 139 of file CbcTreeLocal.hpp.

7.105.3.22 void CbcTreeLocal::setNodeLimit (int value) [inline]

Definition at line 143 of file CbcTreeLocal.hpp.

7.105.3.23 bool CbcTreeLocal::refine () const [inline]

Definition at line 147 of file CbcTreeLocal.hpp.

7.105.3.24 void CbcTreeLocal::setRefine (bool yesNo) [inline]

Definition at line 151 of file CbcTreeLocal.hpp.


The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcTreeLocal.hpp

7.106 CbcTreeVariable Class Reference

#include <CbcTreeLocal.hpp>

Inheritance diagram for CbcTreeVariable:



Public Member Functions

- CbcTreeVariable ()
- CbcTreeVariable (CbcModel *model, const double *solution, int range=10, int typeCuts=0, int max-Diversification=0, int timeLimit=1000000, int nodeLimit=1000000, bool refine=true)
- CbcTreeVariable (const CbcTreeVariable &rhs)
- CbcTreeVariable & operator= (const CbcTreeVariable &rhs)
- virtual ∼CbcTreeVariable ()
- virtual CbcTree * clone () const

Clone.

virtual void generateCpp (FILE *fp)

Create C++ lines to get to current state.

Heap access and maintenance methods

```
    virtual CbcNode * top () const
```

Return the top node of the heap.

virtual void push (CbcNode *x)

Add a node to the heap.

virtual void pop ()

Remove the top node from the heap.

Other stuff

• int createCut (const double *solution, OsiRowCut &cut)

Create cut - return -1 if bad, 0 if okay and 1 if cut is everything.

virtual bool empty ()

Test if empty *** note may be overridden.

virtual void endSearch ()

We may have got an intelligent tree so give it one more chance.

void reverseCut (int state, double bias=0.0)

Other side of last cut branch (if bias==rhs_ will be weakest possible)

void deleteCut (OsiRowCut &cut)

Delete last cut branch.

void passInSolution (const double *solution, double solutionValue)

Pass in solution (so can be used after heuristic)

- int range () const
- void setRange (int value)
- int typeCuts () const
- void setTypeCuts (int value)
- int maxDiversification () const
- void setMaxDiversification (int value)
- int timeLimit () const
- void setTimeLimit (int value)
- int nodeLimit () const
- void setNodeLimit (int value)
- bool refine () const
- · void setRefine (bool yesNo)

Additional Inherited Members

7.106.1 Detailed Description

Definition at line 206 of file CbcTreeLocal.hpp.

- 7.106.2 Constructor & Destructor Documentation
- 7.106.2.1 CbcTreeVariable::CbcTreeVariable ()
- 7.106.2.2 CbcTreeVariable::CbcTreeVariable (CbcModel * model, const double * solution, int range = 10, int typeCuts = 0, int maxDiversification = 0, int timeLimit = 1000000, int nodeLimit = 1000000, bool refine = true)
- 7.106.2.3 CbcTreeVariable::CbcTreeVariable (const CbcTreeVariable & rhs)
- **7.106.2.4** virtual CbcTreeVariable::~CbcTreeVariable() [virtual]
- 7.106.3 Member Function Documentation
- 7.106.3.1 CbcTreeVariable& CbcTreeVariable::operator=(const CbcTreeVariable & rhs)

```
7.106.3.2 virtual CbcTree* CbcTreeVariable::clone( )const [virtual]
Clone.
Reimplemented from CbcTree.
7.106.3.3 virtual void CbcTreeVariable::generateCpp (FILE * fp ) [virtual]
Create C++ lines to get to current state.
Reimplemented from CbcTree.
7.106.3.4 virtual CbcNode* CbcTreeVariable::top( )const [virtual]
Return the top node of the heap.
Reimplemented from CbcTree.
7.106.3.5 virtual void CbcTreeVariable::push ( CbcNode * x ) [virtual]
Add a node to the heap.
Reimplemented from CbcTree.
7.106.3.6 virtual void CbcTreeVariable::pop() [virtual]
Remove the top node from the heap.
Reimplemented from CbcTree.
7.106.3.7 int CbcTreeVariable::createCut ( const double * solution, OsiRowCut & cut )
Create cut - return -1 if bad, 0 if okay and 1 if cut is everything.
7.106.3.8 virtual bool CbcTreeVariable::empty() [virtual]
Test if empty *** note may be overridden.
Reimplemented from CbcTree.
7.106.3.9 virtual void CbcTreeVariable::endSearch() [virtual]
We may have got an intelligent tree so give it one more chance.
Reimplemented from CbcTree.
7.106.3.10 void CbcTreeVariable::reverseCut ( int state, double bias = 0.0 )
Other side of last cut branch (if bias==rhs will be weakest possible)
7.106.3.11 void CbcTreeVariable::deleteCut ( OsiRowCut & cut )
Delete last cut branch.
7.106.3.12 void CbcTreeVariable::passInSolution ( const double * solution, double solutionValue )
Pass in solution (so can be used after heuristic)
7.106.3.13 int CbcTreeVariable::range ( ) const [inline]
Definition at line 273 of file CbcTreeLocal.hpp.
```

```
7.106.3.14 void CbcTreeVariable::setRange (int value) [inline]
Definition at line 277 of file CbcTreeLocal.hpp.
7.106.3.15 int CbcTreeVariable::typeCuts()const [inline]
Definition at line 281 of file CbcTreeLocal.hpp.
7.106.3.16 void CbcTreeVariable::setTypeCuts (int value ) [inline]
Definition at line 285 of file CbcTreeLocal.hpp.
7.106.3.17 int CbcTreeVariable::maxDiversification ( ) const [inline]
Definition at line 289 of file CbcTreeLocal.hpp.
7.106.3.18 void CbcTreeVariable::setMaxDiversification (int value) [inline]
Definition at line 293 of file CbcTreeLocal.hpp.
7.106.3.19 int CbcTreeVariable::timeLimit() const [inline]
Definition at line 297 of file CbcTreeLocal.hpp.
7.106.3.20 void CbcTreeVariable::setTimeLimit(int value) [inline]
Definition at line 301 of file CbcTreeLocal.hpp.
7.106.3.21 int CbcTreeVariable::nodeLimit() const [inline]
Definition at line 305 of file CbcTreeLocal.hpp.
7.106.3.22 void CbcTreeVariable::setNodeLimit(int value) [inline]
Definition at line 309 of file CbcTreeLocal.hpp.
7.106.3.23 bool CbcTreeVariable::refine ( ) const [inline]
Definition at line 313 of file CbcTreeLocal.hpp.
7.106.3.24 void CbcTreeVariable::setRefine (bool yesNo) [inline]
Definition at line 317 of file CbcTreeLocal.hpp.
The documentation for this class was generated from the following file:

    /home/ted/COIN/trunk/Cbc/src/CbcTreeLocal.hpp
```

7.107 CbcUser Class Reference

A class to allow the use of unknown user functionality.

```
#include <CbcSolver.hpp>
```

Public Member Functions

import/export methods

virtual int importData (CbcSolver *, int &, char **)

Import - gets full command arguments.

virtual void exportSolution (CbcSolver *, int, const char *=NULL)

Export.

virtual void exportData (CbcSolver *)

Export Data (i.e. at very end)

virtual void fillInformation (CbcSolver *, CbcSolverUsefulData &)

Get useful stuff.

usage methods

• CoinModel * coinModel () const

CoinModel if valid.

virtual void * stuff ()

Other info - needs expanding.

• std::string name () const

Name.

virtual void solve (CbcSolver *model, const char *options)=0

Solve (whatever that means)

virtual bool canDo (const char *options)=0

Returns true if function knows about option.

Constructors and destructors etc

• CbcUser ()

Default Constructor.

CbcUser (const CbcUser &rhs)

Copy constructor.

CbcUser & operator= (const CbcUser &rhs)

Assignment operator.

virtual CbcUser * clone () const =0

Clone.

virtual ∼CbcUser ()

Destructor.

Protected Attributes

Private member data

• CoinModel * coinModel

CoinModel.

std::string userName_

Name of user function.

7.107.1 Detailed Description

A class to allow the use of unknown user functionality.

For example, access to a modelling language (CbcAmpl).

Definition at line 260 of file CbcSolver.hpp.

```
7.107.2 Constructor & Destructor Documentation
7.107.2.1 CbcUser::CbcUser()
Default Constructor.
7.107.2.2 CbcUser::CbcUser ( const CbcUser & rhs )
Copy constructor.
7.107.2.3 virtual CbcUser::~CbcUser() [virtual]
Destructor.
7.107.3 Member Function Documentation
7.107.3.1 virtual int CbcUser::importData ( CbcSolver *, int &, char ** ) [inline], [virtual]
Import - gets full command arguments.
Returns
         • -1 - no action
         • 0 - data read in without error
         • 1 - errors
Definition at line 272 of file CbcSolver.hpp.
7.107.3.2 virtual void CbcUser::exportSolution ( CbcSolver *, int, const char * = NULL ) [inline], [virtual]
Export.
Values for mode:
    • 1 OsiClpSolver
    • 2 CbcModel
    · add 10 if infeasible from odd situation
Definition at line 283 of file CbcSolver.hpp.
7.107.3.3 virtual void CbcUser::exportData ( CbcSolver * ) [inline], [virtual]
Export Data (i.e. at very end)
Definition at line 287 of file CbcSolver.hpp.
7.107.3.4 virtual void CbcUser::fillInformation ( CbcSolver *, CbcSolverUsefulData & ) [inline], [virtual]
Get useful stuff.
Definition at line 290 of file CbcSolver.hpp.
7.107.3.5 CoinModel* CbcUser::coinModel( ) const [inline]
CoinModel if valid.
Definition at line 297 of file CbcSolver.hpp.
```

```
7.107.3.6 virtual void* CbcUser::stuff() [inline], [virtual]
Other info - needs expanding.
Definition at line 301 of file CbcSolver.hpp.
7.107.3.7 std::string CbcUser::name ( ) const [inline]
Name.
Definition at line 305 of file CbcSolver.hpp.
7.107.3.8 virtual void CbcUser::solve ( CbcSolver * model, const char * options ) [pure virtual]
Solve (whatever that means)
7.107.3.9 virtual bool CbcUser::canDo ( const char * options ) [pure virtual]
Returns true if function knows about option.
7.107.3.10 CbcUser& CbcUser::operator= ( const CbcUser & rhs )
Assignment operator.
7.107.3.11 virtual CbcUser* CbcUser::clone( ) const [pure virtual]
Clone.
7.107.4 Member Data Documentation
7.107.4.1 CoinModel* CbcUser::coinModel_ [protected]
CoinModel.
Definition at line 337 of file CbcSolver.hpp.
7.107.4.2 std::string CbcUser::userName_ [protected]
Name of user function.
Definition at line 340 of file CbcSolver.hpp.
The documentation for this class was generated from the following file:
```


/home/ted/COIN/trunk/Cbc/src/CbcSolver.hpp

7.108 CglTemporary Class Reference

Stored Temporary Cut Generator Class - destroyed after first use.

```
#include <CbcLinked.hpp>
```

Inheritance diagram for CglTemporary:



Public Member Functions

Generate Cuts

virtual void generateCuts (const OsiSolverInterface &si, OsiCuts &cs, const CglTreeInfo info=CglTreeInfo())
 Generate Mixed Integer Stored cuts for the model of the solver interface, si.

Constructors and destructors

• CglTemporary ()

Default constructor.

CglTemporary (const CglTemporary &rhs)

Copy constructor.

virtual CglCutGenerator * clone () const

Clone

• CglTemporary & operator= (const CglTemporary &rhs)

Assignment operator.

virtual ∼CglTemporary ()

Destructor.

7.108.1 Detailed Description

Stored Temporary Cut Generator Class - destroyed after first use.

Definition at line 1266 of file CbcLinked.hpp.

7.108.2 Constructor & Destructor Documentation

7.108.2.1 CglTemporary::CglTemporary ()

Default constructor.

7.108.2.2 CglTemporary::CglTemporary (const CglTemporary & rhs)

Copy constructor.

7.108.2.3 virtual CglTemporary::~CglTemporary() [virtual]

Destructor.

7.108.3 Member Function Documentation

7.108.3.1 virtual void CglTemporary::generateCuts (const OsiSolverInterface & si, OsiCuts & cs, const CglTreeInfo info = CglTreeInfo()) [virtual]

Generate Mixed Integer Stored cuts for the model of the solver interface, si.

Insert the generated cuts into OsiCut, cs.

This generator just looks at previously stored cuts and inserts any that are violated by enough

7.108.3.2 virtual CglCutGenerator* CglTemporary::clone() const [virtual]

Clone.

7.108.3.3 CglTemporary& CglTemporary::operator= (const CglTemporary & rhs)

Assignment operator.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.109 CbcGenCtlBlk::chooseStrongCtl_struct Struct Reference

Control variables for a strong branching method.

```
#include <CbcGenCtlBlk.hpp>
```

Public Attributes

- int numBeforeTrust
- int numStrong_
- int shadowPriceMode

7.109.1 Detailed Description

Control variables for a strong branching method.

Consult OsiChooseVariable and CbcModel for details. An artifact of the changeover from CbcObjects to OsiObjects is that the number of uses before pseudo costs are trusted (numBeforeTrust_) and the number of variables evaluated with strong branching (numStrong_) are parameters of CbcModel.

Definition at line 765 of file CbcGenCtlBlk.hpp.

7.109.2 Member Data Documentation

7.109.2.1 int CbcGenCtlBlk::chooseStrongCtl_struct::numBeforeTrust_

Definition at line 766 of file CbcGenCtlBlk.hpp.

7.109.2.2 int CbcGenCtlBlk::chooseStrongCtl_struct::numStrong_

Definition at line 767 of file CbcGenCtlBlk.hpp.

7.109.2.3 int CbcGenCtlBlk::chooseStrongCtl_struct::shadowPriceMode_

Definition at line 768 of file CbcGenCtlBlk.hpp.

The documentation for this struct was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcGenCtlBlk.hpp

7.110 ClpAmplObjective Class Reference

Ampl Objective Class.

#include <ClpAmplObjective.hpp>

Inheritance diagram for ClpAmplObjective:



Public Member Functions

Stuff

 virtual double * gradient (const ClpSimplex *model, const double *solution, double &offset, bool refresh, int includeLinear=2)

Returns gradient.

- virtual double reducedGradient (ClpSimplex *model, double *region, bool useFeasibleCosts)
 Resize objective.
- virtual double stepLength (ClpSimplex *model, const double *solution, const double *change, double maximumTheta, double ¤tObj, double &predictedObj, double &thetaObj)

Returns step length which gives minimum of objective for solution + theta * change vector up to maximum theta.

• virtual double objective Value (const ClpSimplex *model, const double *solution) const

Return objective value (without any ClpModel offset) (model may be NULL)

- virtual void resize (int newNumberColumns)
- virtual void deleteSome (int numberToDelete, const int *which)

Delete columns in objective.

virtual void reallyScale (const double *columnScale)

Scale objective.

virtual int markNonlinear (char *which)

Given a zeroed array sets nonlinear columns to 1.

virtual void newXValues ()

Say we have new primal solution - so may need to recompute.

Constructors and destructors

ClpAmplObjective ()

Default Constructor.

ClpAmplObjective (void *amplInfo)

Constructor from ampl info.

ClpAmplObjective (const ClpAmplObjective &rhs)

Copy constructor.

ClpAmplObjective & operator= (const ClpAmplObjective &rhs)

Assignment operator.

• virtual ~ClpAmplObjective ()

Destructor.

virtual ClpObjective * clone () const

Clone.

Gets and sets

• double * linearObjective () const

Linear objective.

7.110.1 Detailed Description

Ampl Objective Class.

Definition at line 18 of file ClpAmplObjective.hpp.

7.110.2 Constructor & Destructor Documentation

7.110.2.1 ClpAmplObjective::ClpAmplObjective ()

Default Constructor.

7.110.2.2 ClpAmplObjective::ClpAmplObjective (void * amplInfo)

Constructor from ampl info.

7.110.2.3 ClpAmplObjective::ClpAmplObjective (const ClpAmplObjective & rhs)

Copy constructor.

7.110.2.4 virtual ClpAmplObjective::~ClpAmplObjective() [virtual]

Destructor.

7.110.3 Member Function Documentation

7.110.3.1 virtual double* ClpAmplObjective::gradient (const ClpSimplex * model, const double * solution, double & offset, bool refresh, int includeLinear = 2) [virtual]

Returns gradient.

If Ampl then solution may be NULL, also returns an offset (to be added to current one) If refresh is false then uses last solution Uses model for scaling includeLinear 0 - no, 1 as is, 2 as feasible

7.110.3.2 virtual double ClpAmplObjective::reducedGradient (ClpSimplex * model, double * region, bool useFeasibleCosts)

[virtual]

Resize objective.

Returns reduced gradient. Returns an offset (to be added to current one).

7.110.3.3 virtual double ClpAmplObjective::stepLength (ClpSimplex * model, const double * solution, const double * change, double maximumTheta, double & currentObj, double & predictedObj, double & thetaObj) [virtual]

Returns step length which gives minimum of objective for solution + theta * change vector up to maximum theta. arrays are numberColumns+numberRows Also sets current objective, predicted and at maximumTheta

7.110.3.4 virtual double ClpAmplObjective::objectiveValue (const ClpSimplex * model, const double * solution) const [virtual]

Return objective value (without any ClpModel offset) (model may be NULL)

7.110.3.5 virtual void ClpAmplObjective::resize (int newNumberColumns) [virtual]

7.110.3.6 virtual void ClpAmplObjective::deleteSome(int numberToDelete, const int * which) [virtual]

Delete columns in objective.

7.110.3.7 virtual void ClpAmplObjective::reallyScale (const double * columnScale) [virtual]

Scale objective.

7.110.3.8 virtual int ClpAmplObjective::markNonlinear (char * which) [virtual]

Given a zeroed array sets nonlinear columns to 1.

Returns number of nonlinear columns

7.110.3.9 virtual void ClpAmplObjective::newXValues() [virtual]

Say we have new primal solution - so may need to recompute.

7.110.3.10 ClpAmplObjective& ClpAmplObjective::operator= (const ClpAmplObjective & rhs)

Assignment operator.

7.110.3.11 virtual ClpObjective* ClpAmplObjective::clone () const [virtual]

Clone.

7.110.3.12 double* ClpAmplObjective::linearObjective () const

Linear objective.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/ClpAmplObjective.hpp

7.111 ClpConstraintAmpl Class Reference

Ampl Constraint Class.

#include <ClpConstraintAmpl.hpp>

Inheritance diagram for ClpConstraintAmpl:



Public Member Functions

Stuff

- virtual int gradient (const ClpSimplex *model, const double *solution, double *gradient, double &functionValue, double &offset, bool useScaling=false, bool refresh=true) const Fills gradient.
- virtual void resize (int newNumberColumns)

Resize constraint.

virtual void deleteSome (int numberToDelete, const int *which)

Delete columns in constraint.

virtual void reallyScale (const double *columnScale)

Scale constraint.

virtual int markNonlinear (char *which) const

Given a zeroed array sets nonampl columns to 1.

virtual int markNonzero (char *which) const

Given a zeroed array sets possible nonzero coefficients to 1.

virtual void newXValues ()

Say we have new primal solution - so may need to recompute.

Constructors and destructors

ClpConstraintAmpl ()

Default Constructor.

ClpConstraintAmpl (int row, void *amplInfo)

Constructor from ampl.

ClpConstraintAmpl (const ClpConstraintAmpl &rhs)

Copy constructor.

• ClpConstraintAmpl & operator= (const ClpConstraintAmpl &rhs)

Assignment operator.

virtual ∼ClpConstraintAmpl ()

Destructor.

• virtual ClpConstraint * clone () const

Clone.

Gets and sets

• virtual int numberCoefficients () const

Number of coefficients.

• const int * column () const

Columns.

• const double * coefficient () const

Coefficients.

7.111.1 Detailed Description

Ampl Constraint Class.

Definition at line 17 of file ClpConstraintAmpl.hpp.

7.111.2 Constructor & Destructor Documentation

7.111.2.1 ClpConstraintAmpl::ClpConstraintAmpl ()

Default Constructor.

7.111.2.2 ClpConstraintAmpl::ClpConstraintAmpl (int row, void * amplInfo)

Constructor from ampl.

7.111.2.3 ClpConstraintAmpl::ClpConstraintAmpl (const ClpConstraintAmpl & rhs)

Copy constructor.

```
7.111.2.4 virtual ClpConstraintAmpl::~ClpConstraintAmpl() [virtual]
Destructor.
7.111.3 Member Function Documentation
7.111.3.1 virtual int ClpConstraintAmpl::gradient ( const ClpSimplex * model, const double * solution, double * gradient, double
          & functionValue, double & offset, bool useScaling = false, bool refresh = true ) const [virtual]
Fills gradient.
If Ampl then solution may be NULL, also returns true value of function and offset so we can use x not deltaX in constraint
If refresh is false then uses last solution Uses model for scaling Returns non-zero if gradient udefined at current solution
7.111.3.2 virtual void ClpConstraintAmpl::resize (int newNumberColumns) [virtual]
Resize constraint.
7.111.3.3 virtual void ClpConstraintAmpl::deleteSome ( int numberToDelete, const int * which ) [virtual]
Delete columns in constraint.
7.111.3.4 virtual void ClpConstraintAmpl::reallyScale ( const double * columnScale ) [virtual]
Scale constraint.
7.111.3.5 virtual int ClpConstraintAmpl::markNonlinear ( char * which ) const [virtual]
Given a zeroed array sets nonampl columns to 1.
Returns number of nonampl columns
7.111.3.6 virtual int ClpConstraintAmpl::markNonzero ( char * which ) const [virtual]
Given a zeroed array sets possible nonzero coefficients to 1.
Returns number of nonzeros
7.111.3.7 virtual void ClpConstraintAmpl::newXValues() [virtual]
Say we have new primal solution - so may need to recompute.
7.111.3.8 ClpConstraintAmpl& ClpConstraintAmpl & rhs )
Assignment operator.
7.111.3.9 virtual ClpConstraint* ClpConstraintAmpl::clone() const [virtual]
Clone.
7.111.3.10 virtual int ClpConstraintAmpl::numberCoefficients() const [virtual]
Number of coefficients.
7.111.3.11 const int* ClpConstraintAmpl::column( ) const [inline]
```

Columns.

Definition at line 83 of file ClpConstraintAmpl.hpp.

7.111.3.12 const double* ClpConstraintAmpl::coefficient() const [inline]

Coefficients.

Definition at line 87 of file ClpConstraintAmpl.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/ClpConstraintAmpl.hpp

7.112 CoinHashLink Struct Reference

Really for Conflict cuts to - a) stop duplicates b) allow half baked cuts The whichRow_field in OsiRowCut2 is used for a type 0 - normal 1 - processed cut 2 - unprocessed cut i.e.

```
#include <CbcCountRowCut.hpp>
```

Public Attributes

- int index
- int next

7.112.1 Detailed Description

Really for Conflict cuts to - a) stop duplicates b) allow half baked cuts The whichRow_field in OsiRowCut2 is used for a type 0 - normal 1 - processed cut 2 - unprocessed cut i.e.

dual ray computation

Definition at line 131 of file CbcCountRowCut.hpp.

7.112.2 Member Data Documentation

7.112.2.1 int CoinHashLink::index

Definition at line 132 of file CbcCountRowCut.hpp.

7.112.2.2 int CoinHashLink::next

Definition at line 132 of file CbcCountRowCut.hpp.

The documentation for this struct was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcCountRowCut.hpp

7.113 CbcGenCtlBlk::debugSolInfo_struct Struct Reference

Array of primal variable values for debugging.

#include <CbcGenCtlBlk.hpp>

Public Attributes

- int numCols
- double * values

7.113.1 Detailed Description

Array of primal variable values for debugging.

Used to provide a known optimal solution to activateRowCutDebugger().

Definition at line 669 of file CbcGenCtlBlk.hpp.

7.113.2 Member Data Documentation

7.113.2.1 int CbcGenCtlBlk::debugSolInfo_struct::numCols_

Definition at line 670 of file CbcGenCtlBlk.hpp.

7.113.2.2 double* CbcGenCtlBlk::debugSolInfo_struct::values_

Definition at line 671 of file CbcGenCtlBlk.hpp.

The documentation for this struct was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcGenCtlBlk.hpp

7.114 CbcGenCtlBlk::djFixCtl_struct Struct Reference

Control use of reduced cost fixing prior to B&C.

```
#include <CbcGenCtlBlk.hpp>
```

Public Attributes

- · bool action_
- double threshold

7.114.1 Detailed Description

Control use of reduced cost fixing prior to B&C.

This heuristic fixes variables whose reduced cost for the root relaxtion exceeds the specified threshold. This is purely a heuristic, performed before there's any incumbent solution. It may well fix variables at the wrong bound!

Definition at line 739 of file CbcGenCtlBlk.hpp.

7.114.2 Member Data Documentation

7.114.2.1 bool CbcGenCtlBlk::djFixCtl_struct::action_

Definition at line 740 of file CbcGenCtlBlk.hpp.

7.114.2.2 double CbcGenCtlBlk::djFixCtl_struct::threshold_

Definition at line 741 of file CbcGenCtlBlk.hpp.

The documentation for this struct was generated from the following file:

• /home/ted/COIN/trunk/Cbc/src/CbcGenCtlBlk.hpp

7.115 CbcGenCtlBlk::genParamsInfo_struct Struct Reference

Start and end of cbc-generic parameters in parameter vector.

```
#include <CbcGenCtlBlk.hpp>
```

Public Attributes

- int first
- int last

7.115.1 Detailed Description

Start and end of cbc-generic parameters in parameter vector.

Definition at line 598 of file CbcGenCtlBlk.hpp.

7.115.2 Member Data Documentation

7.115.2.1 int CbcGenCtlBlk::genParamsInfo_struct::first_

Definition at line 599 of file CbcGenCtlBlk.hpp.

7.115.2.2 int CbcGenCtlBlk::genParamsInfo_struct::last_

Definition at line 600 of file CbcGenCtlBlk.hpp.

The documentation for this struct was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcGenCtlBlk.hpp

7.116 OsiBiLinear Class Reference

Define BiLinear objects.

#include <CbcLinked.hpp>

Inheritance diagram for OsiBiLinear:



Public Member Functions

- OsiBiLinear ()
- OsiBiLinear (OsiSolverInterface *solver, int xColumn, int yColumn, int xyRow, double coefficient, double xMesh, double yMesh, int numberExistingObjects=0, const OsiObject **objects=NULL)

Useful constructor - This Adds in rows and variables to construct valid Linked Ordered Set Adds extra constraints to match other x/y So note not const solver.

• OsiBiLinear (CoinModel *coinModel, int xColumn, int yColumn, int xyRow, double coefficient, double xMesh, double yMesh, int numberExistingObjects=0, const OsiObject **objects=NULL)

Useful constructor - This Adds in rows and variables to construct valid Linked Ordered Set Adds extra constraints to match other x/y So note not const model.

- OsiBiLinear (const OsiBiLinear &)
- virtual OsiObject * clone () const

Clone.

- OsiBiLinear & operator= (const OsiBiLinear &rhs)
- virtual ∼OsiBiLinear ()
- virtual double infeasibility (const OsiBranchingInformation *info, int &whichWay) const

Infeasibility - large is 0.5.

 $\bullet \ \ virtual \ double \ feasible Region \ (OsiSolverInterface \ *solver, \ const \ OsiBranchingInformation \ *info) \ const$

Set bounds to fix the variable at the current (integer) value.

• virtual OsiBranchingObject * createBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way) const

Creates a branching object.

virtual void resetSequenceEtc (int numberColumns, const int *originalColumns)

Redoes data when sequence numbers change.

- virtual double checkInfeasibility (const OsiBranchingInformation *info) const
- virtual bool canDoHeuristics () const

Return true if object can take part in normal heuristics.

· virtual bool boundBranch () const

Return true if branch should only bound variables.

• int xColumn () const

X column.

• int yColumn () const

Y column.

· int xRow () const

X row.

• int yRow () const

Y row.

• int xyRow () const

XY row.

· double coefficient () const

Coefficient.

void setCoefficient (double value)

Set coefficient.

int firstLambda () const

First lambda (of 4)

· double xSatisfied () const

X satisfied if less than this away from mesh.

- void setXSatisfied (double value)
- · double ySatisfied () const

Y satisfied if less than this away from mesh.

- void setYSatisfied (double value)
- · double xOtherSatisfied () const

X other satisfied if less than this away from mesh.

- void setXOtherSatisfied (double value)
- double yOtherSatisfied () const

Y other satisfied if less than this away from mesh.

- void setYOtherSatisfied (double value)
- double xMeshSize () const

X meshSize.

- void setXMeshSize (double value)
- double yMeshSize () const

Y meshSize.

- void setYMeshSize (double value)
- · double xySatisfied () const

XY satisfied if two version differ by less than this.

- void setXYSatisfied (double value)
- void setMeshSizes (const OsiSolverInterface *solver, double x, double y)

Set sizes and other stuff.

· int branchingStrategy () const

branching strategy etc bottom 2 bits 0 branch on either, 1 branch on x, 2 branch on y next bit 4 set to say don't update coefficients next bit 8 set to say don't use in feasible region next bit 16 set to say - Always satisfied!!

- void setBranchingStrategy (int value)
- int boundType () const

Simple quadratic bound marker.

- void setBoundType (int value)
- void newBounds (OsiSolverInterface *solver, int way, short xOrY, double separator) const

Does work of branching.

 int updateCoefficients (const double *lower, const double *upper, double *objective, CoinPackedMatrix *matrix, CoinWarmStartBasis *basis) const

Updates coefficients - returns number updated.

double xyCoefficient (const double *solution) const

Returns true value of single xyRow coefficient.

- void getCoefficients (const OsiSolverInterface *solver, double xB[2], double yB[2], double xybar[4]) const
 Get LU coefficients from matrix.
- double computeLambdas (const double xB[3], const double yB[3], const double xybar[4], double lambda[4]) const Compute lambdas (third entry in each .B is current value) (nonzero if bad)
- void addExtraRow (int row, double multiplier)

Adds in data for extra row with variable coefficients.

void getPseudoShadow (const OsiBranchingInformation *info)

Sets infeasibility and other when pseudo shadow prices.

double getMovement (const OsiBranchingInformation *info)

Gets sum of movements to correct value.

Protected Member Functions

 void computeLambdas (const OsiSolverInterface *solver, double lambda[4]) const Compute lambdas if coefficients not changing.

Protected Attributes

```
    double coefficient
```

data

double xMeshSize

x mesh

double yMeshSize

y mesh

double xSatisfied_

x satisfied if less than this away from mesh

double vSatisfied

y satisfied if less than this away from mesh

double xOtherSatisfied

X other satisfied if less than this away from mesh.

· double yOtherSatisfied_

Y other satisfied if less than this away from mesh.

double xySatisfied_

xy satisfied if less than this away from true

• double xyBranchValue_

value of x or y to branch about

• int xColumn_

x column

• int yColumn_

y column

int firstLambda_

First lambda (of 4)

int branchingStrategy_

branching strategy etc bottom 2 bits 0 branch on either, 1 branch on x, 2 branch on y next bit 4 set to say don't update coefficients next bit 8 set to say don't use in feasible region next bit 16 set to say - Always satisfied!!

int boundType_

Simple quadratic bound marker.

int xRow

x row

int yRow

y row (-1 if x*x)

int xyRow

Output row.

int convexity

Convexity row.

int numberExtraRows_

Number of extra rows (coefficients to be modified)

double * multiplier

Multiplier for coefficient on row.

int * extraRow_

Row number.

short chosen

Which chosen -1 none, 0 x, 1 y.

7.116.1 Detailed Description

Define BiLinear objects.

This models x*y where one or both are integer

Definition at line 720 of file CbcLinked.hpp.

7.116.2 Constructor & Destructor Documentation

```
7.116.2.1 OsiBiLinear::OsiBiLinear ( )
```

7.116.2.2 OsiBiLinear::OsiBiLinear (OsiSolverInterface * solver, int xColumn, int yColumn, int xyRow, double coefficient, double xMesh, double yMesh, int numberExistingObjects = 0, const OsiObject ** objects = NULL)

Useful constructor - This Adds in rows and variables to construct valid Linked Ordered Set Adds extra constraints to match other x/y So note not const solver.

7.116.2.3 OsiBiLinear::OsiBiLinear (CoinModel * coinModel, int xColumn, int yColumn, int xyRow, double coefficient, double xMesh, double yMesh, int numberExistingObjects = 0, const OsiObject ** objects = NULL)

Useful constructor - This Adds in rows and variables to construct valid Linked Ordered Set Adds extra constraints to match other x/y So note not const model.

```
7.116.2.4 OsiBiLinear::OsiBiLinear ( const OsiBiLinear & )
```

```
7.116.2.5 virtual OsiBiLinear::~OsiBiLinear() [virtual]
```

7.116.3 Member Function Documentation

7.116.3.1 virtual OsiObject* OsiBiLinear::clone() const [virtual]

Clone.

Reimplemented in OsiBiLinearEquality.

```
7.116.3.2 OsiBiLinear & OsiBiLinear::operator= ( const OsiBiLinear & rhs )
```

7.116.3.3 virtual double OsiBiLinear::infeasibility (const OsiBranchingInformation * info, int & whichWay) const [virtual]

Infeasibility - large is 0.5.

```
7.116.3.4 virtual double OsiBiLinear::feasibleRegion ( OsiSolverInterface * solver, const OsiBranchingInformation * info ) const
          [virtual]
Set bounds to fix the variable at the current (integer) value.
Given an integer value, set the lower and upper bounds to fix the variable. Returns amount it had to move variable.
7.116.3.5 virtual OsiBranchingObject* OsiBiLinear::createBranch ( OsiSolverInterface * solver, const OsiBranchingInformation *
          info, int way ) const [virtual]
Creates a branching object.
The preferred direction is set by way, 0 for down, 1 for up.
7.116.3.6 virtual void OsiBiLinear::resetSequenceEtc (int numberColumns, const int * originalColumns) [virtual]
Redoes data when sequence numbers change.
7.116.3.7 virtual double OsiBiLinear::checkInfeasibility ( const OsiBranchingInformation * info ) const [virtual]
7.116.3.8 virtual bool OsiBiLinear::canDoHeuristics ( ) const [inline], [virtual]
Return true if object can take part in normal heuristics.
Definition at line 785 of file CbcLinked.hpp.
7.116.3.9 virtual bool OsiBiLinear::boundBranch() const [inline], [virtual]
Return true if branch should only bound variables.
Definition at line 790 of file CbcLinked.hpp.
7.116.3.10 int OsiBiLinear::xColumn ( ) const [inline]
X column.
Definition at line 794 of file CbcLinked.hpp.
7.116.3.11 int OsiBiLinear::yColumn ( ) const [inline]
Y column.
Definition at line 798 of file CbcLinked.hpp.
7.116.3.12 int OsiBiLinear::xRow() const [inline]
X row.
Definition at line 802 of file CbcLinked.hpp.
7.116.3.13 int OsiBiLinear::yRow() const [inline]
Y row.
Definition at line 806 of file CbcLinked.hpp.
7.116.3.14 int OsiBiLinear::xyRow() const [inline]
XY row.
```

Definition at line 810 of file CbcLinked.hpp.

```
7.116.3.15 double OsiBiLinear::coefficient ( ) const [inline]
Coefficient.
Definition at line 814 of file CbcLinked.hpp.
7.116.3.16 void OsiBiLinear::setCoefficient ( double value ) [inline]
Set coefficient.
Definition at line 818 of file CbcLinked.hpp.
7.116.3.17 int OsiBiLinear::firstLambda ( ) const [inline]
First lambda (of 4)
Definition at line 822 of file CbcLinked.hpp.
7.116.3.18 double OsiBiLinear::xSatisfied ( ) const [inline]
X satisfied if less than this away from mesh.
Definition at line 826 of file CbcLinked.hpp.
7.116.3.19 void OsiBiLinear::setXSatisfied ( double value ) [inline]
Definition at line 829 of file CbcLinked.hpp.
7.116.3.20 double OsiBiLinear::ySatisfied ( ) const [inline]
Y satisfied if less than this away from mesh.
Definition at line 833 of file CbcLinked.hpp.
7.116.3.21 void OsiBiLinear::setYSatisfied ( double value ) [inline]
Definition at line 836 of file CbcLinked.hpp.
7.116.3.22 double OsiBiLinear::xOtherSatisfied ( ) const [inline]
X other satisfied if less than this away from mesh.
Definition at line 840 of file CbcLinked.hpp.
7.116.3.23 void OsiBiLinear::setXOtherSatisfied ( double value ) [inline]
Definition at line 843 of file CbcLinked.hpp.
7.116.3.24 double OsiBiLinear::yOtherSatisfied ( ) const [inline]
Y other satisfied if less than this away from mesh.
Definition at line 847 of file CbcLinked.hpp.
7.116.3.25 void OsiBiLinear::setYOtherSatisfied ( double value ) [inline]
Definition at line 850 of file CbcLinked.hpp.
7.116.3.26 double OsiBiLinear::xMeshSize ( ) const [inline]
X meshSize.
```

Definition at line 854 of file CbcLinked.hpp.

7.116.3.27 void OsiBiLinear::setXMeshSize (double value) [inline]

Definition at line 857 of file CbcLinked.hpp.

7.116.3.28 double OsiBiLinear::yMeshSize () const [inline]

Y meshSize.

Definition at line 861 of file CbcLinked.hpp.

7.116.3.29 void OsiBiLinear::setYMeshSize (double value) [inline]

Definition at line 864 of file CbcLinked.hpp.

7.116.3.30 double OsiBiLinear::xySatisfied () const [inline]

XY satisfied if two version differ by less than this.

Definition at line 868 of file CbcLinked.hpp.

7.116.3.31 void OsiBiLinear::setXYSatisfied (double value) [inline]

Definition at line 871 of file CbcLinked.hpp.

7.116.3.32 void OsiBiLinear::setMeshSizes (const OsiSolverInterface * solver, double x, double y)

Set sizes and other stuff.

7.116.3.33 int OsiBiLinear::branchingStrategy () const [inline]

branching strategy etc bottom 2 bits 0 branch on either, 1 branch on x, 2 branch on y next bit 4 set to say don't update coefficients next bit 8 set to say don't use in feasible region next bit 16 set to say - Always satisfied!!

Definition at line 886 of file CbcLinked.hpp.

7.116.3.34 void OsiBiLinear::setBranchingStrategy (int value) [inline]

Definition at line 889 of file CbcLinked.hpp.

7.116.3.35 int OsiBiLinear::boundType() const [inline]

Simple quadratic bound marker.

0 no 1 L if coefficient pos, G if negative i.e. value is ub on xy 2 G if coefficient pos, L if negative i.e. value is lb on xy 3 E If bound then real coefficient is 1.0 and coefficient_ is bound

Definition at line 899 of file CbcLinked.hpp.

7.116.3.36 void OsiBiLinear::setBoundType (int value) [inline]

Definition at line 902 of file CbcLinked.hpp.

7.116.3.37 void OsiBiLinear::newBounds (OsiSolverInterface * solver, int way, short xOrY, double separator) const

Does work of branching.

7.116.3.38 int OsiBiLinear::updateCoefficients (const double * lower, const double * upper, double * objective, CoinPackedMatrix * matrix. CoinWarmStartBasis * basis) const

Updates coefficients - returns number updated.

7.116.3.39 double OsiBiLinear::xyCoefficient (const double * solution) const

Returns true value of single xyRow coefficient.

7.116.3.40 void OsiBiLinear::getCoefficients (const OsiSolverInterface * solver, double xB[2], double yB[2], double xybar[4]) const

Get LU coefficients from matrix.

7.116.3.41 double OsiBiLinear::computeLambdas (const double xB[3], const double yB[3], const double xybar[4], double lambda[4]) const

Compute lambdas (third entry in each .B is current value) (nonzero if bad)

7.116.3.42 void OsiBiLinear::addExtraRow (int row, double multiplier)

Adds in data for extra row with variable coefficients.

7.116.3.43 void OsiBiLinear::getPseudoShadow (const OsiBranchingInformation * info)

Sets infeasibility and other when pseudo shadow prices.

7.116.3.44 double OsiBiLinear::getMovement (const OsiBranchingInformation * info)

Gets sum of movements to correct value.

7.116.3.45 void OsiBiLinear::computeLambdas (const OsiSolverInterface * solver, double lambda[4]) const [protected]

Compute lambdas if coefficients not changing.

7.116.4 Member Data Documentation

7.116.4.1 double OsiBiLinear::coefficient [protected]

data

Coefficient

Definition at line 929 of file CbcLinked.hpp.

7.116.4.2 double OsiBiLinear::xMeshSize [protected]

x mesh

Definition at line 931 of file CbcLinked.hpp.

7.116.4.3 double OsiBiLinear::yMeshSize_ [protected]

y mesh

Definition at line 933 of file CbcLinked.hpp.

```
7.116.4.4 double OsiBiLinear::xSatisfied [protected]
x satisfied if less than this away from mesh
Definition at line 935 of file CbcLinked.hpp.
7.116.4.5 double OsiBiLinear::ySatisfied_ [protected]
y satisfied if less than this away from mesh
Definition at line 937 of file CbcLinked.hpp.
7.116.4.6 double OsiBiLinear::xOtherSatisfied_ [protected]
X other satisfied if less than this away from mesh.
Definition at line 939 of file CbcLinked.hpp.
7.116.4.7 double OsiBiLinear::yOtherSatisfied_ [protected]
Y other satisfied if less than this away from mesh.
Definition at line 941 of file CbcLinked.hpp.
7.116.4.8 double OsiBiLinear::xySatisfied [protected]
xy satisfied if less than this away from true
Definition at line 943 of file CbcLinked.hpp.
7.116.4.9 double OsiBiLinear::xyBranchValue_ [mutable], [protected]
value of x or y to branch about
Definition at line 945 of file CbcLinked.hpp.
7.116.4.10 int OsiBiLinear::xColumn_ [protected]
x column
Definition at line 947 of file CbcLinked.hpp.
7.116.4.11 int OsiBiLinear::yColumn_ [protected]
y column
Definition at line 949 of file CbcLinked.hpp.
7.116.4.12 int OsiBiLinear::firstLambda_ [protected]
First lambda (of 4)
Definition at line 951 of file CbcLinked.hpp.
7.116.4.13 int OsiBiLinear::branchingStrategy_ [protected]
branching strategy etc bottom 2 bits 0 branch on either, 1 branch on x, 2 branch on y next bit 4 set to say don't update
coefficients next bit 8 set to say don't use in feasible region next bit 16 set to say - Always satisfied !!
```

Definition at line 962 of file CbcLinked.hpp.

Generated on Mon Oct 21 2013 19:03:07 for Cbc by Doxygen

```
7.116.4.14 int OsiBiLinear::boundType_ [protected]
Simple quadratic bound marker.
0 no 1 L if coefficient pos, G if negative i.e. value is ub on xy 2 G if coefficient pos, L if negative i.e. value is lb on xy 3 E
If bound then real coefficient is 1.0 and coefficient is bound
Definition at line 970 of file CbcLinked.hpp.
7.116.4.15 int OsiBiLinear::xRow_ [protected]
x row
Definition at line 972 of file CbcLinked.hpp.
7.116.4.16 int OsiBiLinear::yRow_ [protected]
y row (-1 \text{ if } x*x)
Definition at line 974 of file CbcLinked.hpp.
7.116.4.17 int OsiBiLinear::xyRow_ [protected]
Output row.
Definition at line 976 of file CbcLinked.hpp.
7.116.4.18 int OsiBiLinear::convexity_ [protected]
Convexity row.
Definition at line 978 of file CbcLinked.hpp.
7.116.4.19 int OsiBiLinear::numberExtraRows_ [protected]
Number of extra rows (coefficients to be modified)
Definition at line 980 of file CbcLinked.hpp.
7.116.4.20 double* OsiBiLinear::multiplier_ [protected]
Multiplier for coefficient on row.
Definition at line 982 of file CbcLinked.hpp.
7.116.4.21 int* OsiBiLinear::extraRow_ [protected]
Row number.
Definition at line 984 of file CbcLinked.hpp.
7.116.4.22 short OsiBiLinear::chosen_ [mutable], [protected]
```

Which chosen -1 none, 0 x, 1 y.

Definition at line 986 of file CbcLinked.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.117 OsiBiLinearBranchingObject Class Reference

Branching object for BiLinear objects.

#include <CbcLinked.hpp>

Inheritance diagram for OsiBiLinearBranchingObject:



Public Member Functions

- OsiBiLinearBranchingObject ()
- OsiBiLinearBranchingObject (OsiSolverInterface *solver, const OsiBiLinear *originalObject, int way, double separator, int chosen)
- OsiBiLinearBranchingObject (const OsiBiLinearBranchingObject &)
- OsiBiLinearBranchingObject & operator= (const OsiBiLinearBranchingObject &rhs)
- virtual OsiBranchingObject * clone () const

Clone.

- virtual ~OsiBiLinearBranchingObject ()
- virtual double branch (OsiSolverInterface *solver)

Does next branch and updates state.

virtual void print (const OsiSolverInterface *solver=NULL)

Print something about branch - only if log level high.

· virtual bool boundBranch () const

Return true if branch should only bound variables.

7.117.1 Detailed Description

Branching object for BiLinear objects.

Definition at line 991 of file CbcLinked.hpp.

- 7.117.2 Constructor & Destructor Documentation
- 7.117.2.1 OsiBiLinearBranchingObject::OsiBiLinearBranchingObject ()
- 7.117.2.2 OsiBiLinearBranchingObject::OsiBiLinearBranchingObject (OsiSolverInterface * solver, const OsiBiLinear * originalObject, int way, double separator, int chosen)
- 7.117.2.3 OsiBiLinearBranchingObject::OsiBiLinearBranchingObject (const OsiBiLinearBranchingObject &)
- 7.117.2.4 virtual OsiBiLinearBranchingObject:: ~OsiBiLinearBranchingObject() [virtual]
- 7.117.3 Member Function Documentation
- 7.117.3.1 OsiBiLinearBranchingObject& OsiBiLinearBranchingObject::operator= (const OsiBiLinearBranchingObject & rhs)

7.117.3.2 virtual OsiBranchingObject* OsiBiLinearBranchingObject::clone () const [virtual]

Clone.

7.117.3.3 virtual double OsiBiLinearBranchingObject::branch (OsiSolverInterface * solver) [virtual]

Does next branch and updates state.

7.117.3.4 virtual void OsiBiLinearBranchingObject::print (const OsiSolverInterface * solver = NULL) [virtual]

Print something about branch - only if log level high.

7.117.3.5 virtual bool OsiBiLinearBranchingObject::boundBranch () const [virtual]

Return true if branch should only bound variables.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.118 OsiBiLinearEquality Class Reference

Define Continuous BiLinear objects for an == bound.

#include <CbcLinked.hpp>

Inheritance diagram for OsiBiLinearEquality:



Public Member Functions

- OsiBiLinearEquality ()
- OsiBiLinearEquality (OsiSolverInterface *solver, int xColumn, int yColumn, int xyRow, double rhs, double xMesh)
 Useful constructor This Adds in rows and variables to construct Ordered Set for x*y = b So note not const solver.
- OsiBiLinearEquality (const OsiBiLinearEquality &)
- virtual OsiObject * clone () const

Clone.

- OsiBiLinearEquality & operator= (const OsiBiLinearEquality &rhs)
- virtual ∼OsiBiLinearEquality ()
- virtual double improvement (const OsiSolverInterface *solver) const

Possible improvement.

double newGrid (OsiSolverInterface *solver, int type) const

change grid if type 0 then use solution and make finer if 1 then back to original returns mesh size

· int numberPoints () const

Number of points.

void setNumberPoints (int value)

```
Additional Inherited Members
7.118.1 Detailed Description
Define Continuous BiLinear objects for an == bound.
This models x*y = b where both are continuous
Definition at line 1038 of file CbcLinked.hpp.
7.118.2 Constructor & Destructor Documentation
7.118.2.1 OsiBiLinearEquality::OsiBiLinearEquality ( )
7.118.2.2 OsiBiLinearEquality::OsiBiLinearEquality (OsiSolverInterface * solver, int xColumn, int yColumn, int xyRow, double rhs,
          double xMesh )
Useful constructor - This Adds in rows and variables to construct Ordered Set for x*y = b So note not const solver.
7.118.2.3 OsiBiLinearEquality::OsiBiLinearEquality ( const OsiBiLinearEquality & )
7.118.2.4 virtual OsiBiLinearEquality::~OsiBiLinearEquality() [virtual]
7.118.3 Member Function Documentation
7.118.3.1 virtual OsiObject* OsiBiLinearEquality::clone( ) const [virtual]
Clone.
Reimplemented from OsiBiLinear.
7.118.3.2 OsiBiLinearEquality & OsiBiLinearEquality::operator= ( const OsiBiLinearEquality & rhs )
7.118.3.3 virtual double OsiBiLinearEquality::improvement ( const OsiSolverInterface * solver ) const [virtual]
Possible improvement.
7.118.3.4 double OsiBiLinearEquality::newGrid ( OsiSolverInterface * solver, int type ) const
change grid if type 0 then use solution and make finer if 1 then back to original returns mesh size
```

7.118.3.5 int OsiBiLinearEquality::numberPoints () const [inline]

Number of points.

Definition at line 1075 of file CbcLinked.hpp.

7.118.3.6 void OsiBiLinearEquality::setNumberPoints (int value) [inline]

Definition at line 1078 of file CbcLinked.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.119 OsiCbcSolverInterface Class Reference

Cbc Solver Interface.

#include <OsiCbcSolverInterface.hpp>

Inheritance diagram for OsiCbcSolverInterface:



Public Member Functions

virtual void setObjSense (double s)

Set objective function sense (1 for min (default), -1 for max,)

virtual void setColSolution (const double *colsol)

Set the primal solution column values.

virtual void setRowPrice (const double *rowprice)

Set dual solution vector.

Solve methods

virtual void initialSolve ()

Solve initial LP relaxation.

virtual void resolve ()

Resolve an LP relaxation after problem modification.

virtual void branchAndBound ()

Invoke solver's built-in enumeration algorithm.

Parameter set/get methods

The set methods return true if the parameter was set to the given value, false otherwise.

There can be various reasons for failure: the given parameter is not applicable for the solver (e.g., refactorization frequency for the cbc algorithm), the parameter is not yet implemented for the solver or simply the value of the parameter is out of the range the solver accepts. If a parameter setting call returns false check the details of your solver.

The get methods return true if the given parameter is applicable for the solver and is implemented. In this case the value of the parameter is returned in the second argument. Otherwise they return false.

- bool setIntParam (OsiIntParam key, int value)
- bool setDblParam (OsiDblParam key, double value)
- bool setStrParam (OsiStrParam key, const std::string &value)
- bool getIntParam (OsiIntParam key, int &value) const
- bool getDblParam (OsiDblParam key, double &value) const
- bool getStrParam (OsiStrParam key, std::string &value) const
- virtual bool setHintParam (OsiHintParam key, bool yesNo=true, OsiHintStrength strength=OsiHintTry, void *otherInformation=NULL)
- virtual bool getHintParam (OsiHintParam key, bool &yesNo, OsiHintStrength &strength, void *&other-Information) const

Get a hint parameter.

virtual bool getHintParam (OsiHintParam key, bool &yesNo, OsiHintStrength &strength) const

Get a hint parameter.

Methods returning info on how the solution process terminated

· virtual bool isAbandoned () const

Are there a numerical difficulties?

virtual bool isProvenOptimal () const

Is optimality proven?

· virtual bool isProvenPrimalInfeasible () const

Is primal infeasiblity proven?

· virtual bool isProvenDualInfeasible () const

Is dual infeasiblity proven?

· virtual bool isPrimalObjectiveLimitReached () const

Is the given primal objective limit reached?

· virtual bool isDualObjectiveLimitReached () const

Is the given dual objective limit reached?

· virtual bool isIterationLimitReached () const

Iteration limit reached?

WarmStart related methods

virtual CoinWarmStart * getEmptyWarmStart () const

Get an empty warm start object.

virtual CoinWarmStart * getWarmStart () const

Get warmstarting information.

virtual bool setWarmStart (const CoinWarmStart *warmstart)

Set warmstarting information.

Hotstart related methods (primarily used in strong branching).

 tr>

The user can create a hotstart (a snapshot) of the optimization process then reoptimize over and over again always starting from there.

NOTE: between hotstarted optimizations only bound changes are allowed.

virtual void markHotStart ()

Create a hotstart point of the optimization process.

virtual void solveFromHotStart ()

Optimize starting from the hotstart.

virtual void unmarkHotStart ()

Delete the snapshot.

Methods related to querying the input data

• virtual int getNumCols () const

Get number of columns.

virtual int getNumRows () const

Get number of rows.

• virtual int getNumElements () const

Get number of nonzero elements.

• virtual const double * getColLower () const

Get pointer to array[getNumCols()] of column lower bounds.

• virtual const double * getColUpper () const

Get pointer to array[getNumCols()] of column upper bounds.

virtual const char * getRowSense () const

Get pointer to array[getNumRows()] of row constraint senses.

virtual const double * getRightHandSide () const

Get pointer to array[getNumRows()] of rows right-hand sides.

virtual const double * getRowRange () const

Get pointer to array[getNumRows()] of row ranges.

virtual const double * getRowLower () const

Get pointer to array[getNumRows()] of row lower bounds.

virtual const double * getRowUpper () const

Get pointer to array[getNumRows()] of row upper bounds.

virtual const double * getObjCoefficients () const

Get pointer to array[getNumCols()] of objective function coefficients.

virtual double getObjSense () const

Get objective function sense (1 for min (default), -1 for max)

virtual bool isContinuous (int colNumber) const

Return true if column is continuous.

virtual const CoinPackedMatrix * getMatrixByRow () const

Get pointer to row-wise copy of matrix.

virtual const CoinPackedMatrix * getMatrixByCol () const

Get pointer to column-wise copy of matrix.

virtual double getInfinity () const

Get solver's value for infinity.

Methods related to querying the solution

virtual const double * getColSolution () const

Get pointer to array[getNumCols()] of primal solution vector.

virtual const double * getRowPrice () const

Get pointer to array[getNumRows()] of dual prices.

virtual const double * getReducedCost () const

Get a pointer to array[getNumCols()] of reduced costs.

virtual const double * getRowActivity () const

Get pointer to array[getNumRows()] of row activity levels (constraint matrix times the solution vector.

virtual double getObjValue () const

Get objective function value.

virtual int getIterationCount () const

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

 $\bullet \ \ \text{virtual std::vector} < \ \ \text{double} \ * > \ \ \ \text{getDualRays} \ \ (\text{int maxNumRays, bool fullRay=false}) \ \ \text{const}$

Get as many dual rays as the solver can provide.

virtual std::vector< double * > getPrimalRays (int maxNumRays) const

Get as many primal rays as the solver can provide.

Methods for row and column names.

Because OsiCbc is a pass-through class, it's necessary to override any virtual method in order to be sure we catch an override by the underlying solver.

See the OsiSolverInterface class documentation for detailed descriptions.

• virtual std::string dfltRowColName (char rc, int ndx, unsigned digits=7) const

Generate a standard name of the form Rnnnnnnn or Cnnnnnnn.

virtual std::string getObjName (unsigned maxLen=std::string::npos) const

Return the name of the objective function.

virtual void setObjName (std::string name)

Set the name of the objective function.

virtual std::string getRowName (int rowIndex, unsigned maxLen=std::string::npos) const

Return the name of the row.

• virtual const OsiNameVec & getRowNames ()

Return a pointer to a vector of row names.

virtual void setRowName (int ndx, std::string name)

Set a row name.

virtual void setRowNames (OsiNameVec &srcNames, int srcStart, int len, int tgtStart)

Set multiple row names.

virtual void deleteRowNames (int tgtStart, int len)

Delete len row names starting at index tgtStart.

• virtual std::string getColName (int colIndex, unsigned maxLen=std::string::npos) const

Return the name of the column.

virtual const OsiNameVec & getColNames ()

Return a pointer to a vector of column names.

virtual void setColName (int ndx, std::string name)

Set a column name.

virtual void setColNames (OsiNameVec &srcNames, int srcStart, int len, int tgtStart)

Set multiple column names.

virtual void deleteColNames (int tgtStart, int len)

Delete len column names starting at index tgtStart.

Changing bounds on variables and constraints

virtual void setObiCoeff (int elementIndex, double elementValue)

Set an objective function coefficient.

virtual void setColLower (int elementIndex, double elementValue)

Set a single column lower bound

Use -DBL MAX for -infinity.

virtual void setColUpper (int elementIndex, double elementValue)

Set a single column upper bound

Use DBL MAX for infinity.

virtual void setColBounds (int elementIndex, double lower, double upper)

Set a single column lower and upper bound.

virtual void setColSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a number of columns simultaneously

The default implementation just invokes setColLower() and setColUpper() over and over again.

virtual void setRowLower (int elementIndex, double elementValue)

Set a single row lower bound

Use -DBL_MAX for -infinity.

virtual void setRowUpper (int elementIndex, double elementValue)

Set a single row upper bound

Use DBL_MAX for infinity.

virtual void setRowBounds (int elementIndex, double lower, double upper)

Set a single row lower and upper bound.

virtual void setRowType (int index, char sense, double rightHandSide, double range)

Set the type of a single row

virtual void setRowSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a number of rows simultaneously

The default implementation just invokes setRowLower() and setRowUpper() over and over again.

 virtual void setRowSetTypes (const int *indexFirst, const int *indexLast, const char *senseList, const double *rhsList, const double *rangeList)

Set the type of a number of rows simultaneously

The default implementation just invokes setRowType() over and over again.

Integrality related changing methods

virtual void setContinuous (int index)

Set the index-th variable to be a continuous variable.

virtual void setInteger (int index)

Set the index-th variable to be an integer variable.

virtual void setContinuous (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be continuous variables.

virtual void setInteger (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be integer variables.

Methods to expand a problem.

Note that if a column is added then by default it will correspond to a continuous variable.

- virtual void addCol (const CoinPackedVectorBase &vec, const double collb, const double colub, const double obj)
- virtual void addCol (int numberElements, const int *rows, const double *elements, const double collb, const double collb, const double collb, const double obj)

Add a column (primal variable) to the problem.

- virtual void addCols (const int numcols, const CoinPackedVectorBase *const *cols, const double *collb, const double *collb
- virtual void deleteCols (const int num, const int *colIndices)
- virtual void addRow (const CoinPackedVectorBase &vec, const double rowlb, const double rowlb)
- virtual void addRow (const CoinPackedVectorBase &vec, const char rowsen, const double rowrhs, const double rowrng)
- virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const double *rowlb, const double *rowub)
- virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const char *rowsen, const double *rowrhs, const double *rowrng)
- virtual void deleteRows (const int num, const int *rowIndices)
- virtual void applyRowCuts (int numberCuts, const OsiRowCut *cuts)

Apply a collection of row cuts which are all effective.

virtual void applyRowCuts (int numberCuts, const OsiRowCut **cuts)

Apply a collection of row cuts which are all effective.

Methods to input a problem

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *rowub, const double *rowub)

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds).

virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&obj, double *&rowlb, double *&rowlb

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *rowrng)

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets).

 virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&obj, char *&rowsen, double *&rowrhs, double *&rowrng)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

virtual void loadProblem (const int numcols, const int numrows, const CoinBigIndex *start, const int *index, const double *value, const double *collb, const double *collb, const double *rowlb, const double *rowlb)

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

virtual void loadProblem (const int numcols, const int numrows, const CoinBigIndex *start, const int *index, const double *value, const double *collb, const double *collb, const double *rowrhs, const double *rowrng)

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

virtual int readMps (const char *filename, const char *extension="mps")

Read an mps file from the given filename (defaults to Osi reader) - returns number of errors (see OsiMpsReader class)

virtual void writeMps (const char *filename, const char *extension="mps", double objSense=0.0) const

Write the problem into an mps file of the given filename.

 virtual int writeMpsNative (const char *filename, const char **rowNames, const char **columnNames, int formatType=0, int numberAcross=2, double objSense=0.0) const

Write the problem into an mps file of the given filename, names may be null.

Message handling (extra for Cbc messages).

Normally I presume you would want the same language.

If not then you could use underlying model pointer

- void newLanguage (CoinMessages::Language language)
 Set language.
- void setLanguage (CoinMessages::Language language)

Cbc specific public interfaces

CbcModel * getModelPtr () const

Get pointer to Cbc model.

OsiSolverInterface * getRealSolverPtr () const

Get pointer to underlying solver.

void setCutoff (double value)

Set cutoff bound on the objective function.

double getCutoff () const

Get the cutoff bound on the objective function - always as minimize.

void setMaximumNodes (int value)

Set the CbcModel::CbcMaxNumNode maximum node limit.

int getMaximumNodes () const

Get the CbcModel::CbcMaxNumNode maximum node limit.

void setMaximumSolutions (int value)

Set the CbcModel::CbcMaxNumSol maximum number of solutions.

• int getMaximumSolutions () const

Get the CbcModel::CbcMaxNumSol maximum number of solutions.

void setMaximumSeconds (double value)

Set the CbcModel::CbcMaximumSeconds maximum number of seconds.

• double getMaximumSeconds () const

Get the CbcModel::CbcMaximumSeconds maximum number of seconds.

bool isNodeLimitReached () const

Node limit reached?

bool isSolutionLimitReached () const

Solution limit reached?

int getNodeCount () const

Get how many Nodes it took to solve the problem.

• int status () const

Final status of problem - 0 finished, 1 stopped, 2 difficulties.

virtual void passInMessageHandler (CoinMessageHandler *handler)

Pass in a message handler.

Constructors and destructors

OsiCbcSolverInterface (OsiSolverInterface *solver=NULL, CbcStrategy *strategy=NULL)

Default Constructor.

• virtual OsiSolverInterface * clone (bool copyData=true) const

OsiCbcSolverInterface (const OsiCbcSolverInterface &)

Copy constructor.

OsiCbcSolverInterface & operator= (const OsiCbcSolverInterface &rhs)

Assignment operator.

virtual ∼OsiCbcSolverInterface ()

Destructor.

Protected Member Functions

Protected methods

virtual void applyRowCut (const OsiRowCut &rc)

Apply a row cut (append to constraint matrix).

virtual void applyColCut (const OsiColCut &cc)

Apply a column cut (adjust one or more bounds).

Protected Attributes

Protected member data

• CbcModel * modelPtr

Cbc model represented by this class instance.

Friends

void OsiCbcSolverInterfaceUnitTest (const std::string &mpsDir, const std::string &netlibDir)

A function that tests the methods in the OsiCbcSolverInterface class.

7.119.1 Detailed Description

Cbc Solver Interface.

Instantiation of OsiCbcSolverInterface for the Model Algorithm.

Definition at line 30 of file OsiCbcSolverInterface.hpp.

```
7.119.2 Constructor & Destructor Documentation
```

```
7.119.2.1 OsiCbcSolverInterface::OsiCbcSolverInterface ( OsiSolverInterface * solver = NULL, CbcStrategy * strategy = NULL )
```

Default Constructor.

7.119.2.2 OsiCbcSolverInterface::OsiCbcSolverInterface (const OsiCbcSolverInterface &)

Copy constructor.

7.119.2.3 virtual OsiCbcSolverInterface::~OsiCbcSolverInterface() [virtual]

Destructor.

7.119.3 Member Function Documentation

```
7.119.3.1 virtual void OsiCbcSolverInterface::initialSolve() [virtual]
Solve initial LP relaxation.
7.119.3.2 virtual void OsiCbcSolverInterface::resolve() [virtual]
Resolve an LP relaxation after problem modification.
7.119.3.3 virtual void OsiCbcSolverInterface::branchAndBound() [virtual]
Invoke solver's built-in enumeration algorithm.
7.119.3.4 bool OsiCbcSolverInterface::setIntParam ( OsiIntParam key, int value )
7.119.3.5 bool OsiCbcSolverInterface::setDblParam ( OsiDblParam key, double value )
7.119.3.6 bool OsiCbcSolverInterface::setStrParam ( OsiStrParam key, const std::string & value )
7.119.3.7 bool OsiCbcSolverInterface::getIntParam ( OsiIntParam key, int & value ) const
7.119.3.8 bool OsiCbcSolverInterface::getDblParam ( OsiDblParam key, double & value ) const
7.119.3.9 bool OsiCbcSolverInterface::getStrParam ( OsiStrParam key, std::string & value ) const
7.119.3.10 virtual bool OsiCbcSolverInterface::setHintParam ( OsiHintParam key, bool yesNo = true, OsiHintStrength strength =
           OsiHintTry, void * otherInformation = NULL ) [virtual]
7.119.3.11 virtual bool OsiCbcSolverInterface::getHintParam ( OsiHintParam key, bool & yesNo, OsiHintStrength & strength, void
           *& otherInformation ) const [virtual]
Get a hint parameter.
7.119.3.12 virtual bool OsiCbcSolverInterface::getHintParam ( OsiHintParam key, bool & yesNo, OsiHintStrength & strength ) const
            [virtual]
Get a hint parameter.
7.119.3.13 virtual bool OsiCbcSolverInterface::isAbandoned ( ) const [virtual]
Are there a numerical difficulties?
7.119.3.14 virtual bool OsiCbcSolverInterface::isProvenOptimal() const [virtual]
Is optimality proven?
7.119.3.15 virtual bool OsiCbcSolverInterface::isProvenPrimalInfeasible ( ) const [virtual]
Is primal infeasibility proven?
7.119.3.16 virtual bool OsiCbcSolverInterface::isProvenDualInfeasible ( ) const [virtual]
Is dual infeasiblity proven?
```

```
7.119.3.17 virtual bool OsiCbcSolverInterface::isPrimalObjectiveLimitReached ( ) const [virtual]
Is the given primal objective limit reached?
7.119.3.18 virtual bool OsiCbcSolverInterface::isDualObjectiveLimitReached( ) const [virtual]
Is the given dual objective limit reached?
7.119.3.19 virtual bool OsiCbcSolverInterface::isIterationLimitReached( ) const [virtual]
Iteration limit reached?
7.119.3.20 virtual CoinWarmStart* OsiCbcSolverInterface::getEmptyWarmStart() const [virtual]
Get an empty warm start object.
This routine returns an empty CoinWarmStartBasis object. Its purpose is to provide a way to give a client a warm start
basis object of the appropriate type, which can resized and modified as desired.
7.119.3.21 virtual CoinWarmStart* OsiCbcSolverInterface::getWarmStart( ) const [virtual]
Get warmstarting information.
7.119.3.22 virtual bool OsiCbcSolverInterface::setWarmStart ( const CoinWarmStart * warmstart ) [virtual]
Set warmstarting information.
Return true/false depending on whether the warmstart information was accepted or not.
7.119.3.23 virtual void OsiCbcSolverInterface::markHotStart() [virtual]
Create a hotstart point of the optimization process.
7.119.3.24 virtual void OsiCbcSolverInterface::solveFromHotStart() [virtual]
Optimize starting from the hotstart.
7.119.3.25 virtual void OsiCbcSolverInterface::unmarkHotStart() [virtual]
Delete the snapshot.
7.119.3.26 virtual int OsiCbcSolverInterface::getNumCols() const [virtual]
Get number of columns.
7.119.3.27 virtual int OsiCbcSolverInterface::getNumRows ( ) const [virtual]
Get number of rows.
7.119.3.28 virtual int OsiCbcSolverInterface::getNumElements ( ) const [virtual]
Get number of nonzero elements.
7.119.3.29 virtual const double* OsiCbcSolverInterface::getColLower( ) const [virtual]
Get pointer to array[getNumCols()] of column lower bounds.
```

```
7.119.3.30 virtual const double* OsiCbcSolverInterface::getColUpper( ) const [virtual]
Get pointer to array[getNumCols()] of column upper bounds.
7.119.3.31 virtual const char* OsiCbcSolverInterface::getRowSense() const [virtual]
Get pointer to array[getNumRows()] of row constraint senses.
    • 'L' <= constraint

    'E' = constraint

    • 'G' >= constraint
    · 'R' ranged constraint
    · 'N' free constraint
7.119.3.32 virtual const double* OsiCbcSolverInterface::getRightHandSide ( ) const [virtual]
Get pointer to array[getNumRows()] of rows right-hand sides.
    • if rowsense()[i] == 'L' then rhs()[i] == rowupper()[i]
    • if rowsense()[i] == 'G' then rhs()[i] == rowlower()[i]

    if rowsense()[i] == 'R' then rhs()[i] == rowupper()[i]

    • if rowsense()[i] == 'N' then rhs()[i] == 0.0
7.119.3.33 virtual const double* OsiCbcSolverInterface::getRowRange() const [virtual]
Get pointer to array[getNumRows()] of row ranges.
    • if rowsense()[i] == 'R' then rowrange()[i] == rowupper()[i] - rowlower()[i]

    if rowsense()[i] != 'R' then rowrange()[i] is undefined

7.119.3.34 virtual const double* OsiCbcSolverInterface::getRowLower( ) const [virtual]
Get pointer to array[getNumRows()] of row lower bounds.
7.119.3.35 virtual const double* OsiCbcSolverInterface::getRowUpper( ) const [virtual]
Get pointer to array[getNumRows()] of row upper bounds.
7.119.3.36 virtual const double* OsiCbcSolverInterface::getObjCoefficients() const [virtual]
Get pointer to array[getNumCols()] of objective function coefficients.
7.119.3.37 virtual double OsiCbcSolverInterface::getObjSense() const [virtual]
Get objective function sense (1 for min (default), -1 for max)
7.119.3.38 virtual bool OsiCbcSolverInterface::isContinuous ( int colNumber ) const [virtual]
Return true if column is continuous.
```

```
7.119.3.39 virtual const CoinPackedMatrix* OsiCbcSolverInterface::getMatrixByRow() const [virtual]
Get pointer to row-wise copy of matrix.
7.119.3.40 virtual const CoinPackedMatrix* OsiCbcSolverInterface::getMatrixByCol( ) const [virtual]
Get pointer to column-wise copy of matrix.
7.119.3.41 virtual double OsiCbcSolverInterface::getInfinity() const [virtual]
Get solver's value for infinity.
7.119.3.42 virtual const double* OsiCbcSolverInterface::getColSolution() const [virtual]
Get pointer to array[getNumCols()] of primal solution vector.
7.119.3.43 virtual const double* OsiCbcSolverInterface::getRowPrice ( ) const [virtual]
Get pointer to array[getNumRows()] of dual prices.
7.119.3.44 virtual const double* OsiCbcSolverInterface::getReducedCost() const [virtual]
Get a pointer to array[getNumCols()] of reduced costs.
7.119.3.45 virtual const double* OsiCbcSolverInterface::getRowActivity( ) const [virtual]
Get pointer to array[getNumRows()] of row activity levels (constraint matrix times the solution vector.
7.119.3.46 virtual double OsiCbcSolverInterface::getObjValue() const [virtual]
Get objective function value.
7.119.3.47 virtual int OsiCbcSolverInterface::getIterationCount() const [virtual]
Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.
7.119.3.48 virtual std::vector<double*> OsiCbcSolverInterface::getDualRays ( int maxNumRays, bool fullRay = false ) const
           [virtual]
```

Get as many dual rays as the solver can provide.

(In case of proven primal infeasibility there should be at least one.)

The first getNumRows() ray components will always be associated with the row duals (as returned by getRowPrice()). If fullRay is true, the final getNumCols() entries will correspond to the ray components associated with the nonbasic variables. If the full ray is requested and the method cannot provide it, it will throw an exception.

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumRows() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

7.119.3.49 virtual std::vector<double*> OsiCbcSolverInterface::getPrimalRays (int maxNumRays) const [virtual]

Get as many primal rays as the solver can provide.

(In case of proven dual infeasibility there should be at least one.)

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumCols() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

```
7.119.3.50 virtual std::string OsiCbcSolverInterface::dfltRowColName ( char rc, int ndx, unsigned digits = 7 ) const [virtual]
```

Generate a standard name of the form Rnnnnnnn or Cnnnnnnn.

```
7.119.3.51 virtual std::string OsiCbcSolverInterface::getObjName ( unsigned maxLen = std::string::npos ) const [virtual]
```

Return the name of the objective function.

```
7.119.3.52 virtual void OsiCbcSolverInterface::setObjName ( std::string name ) [virtual]
```

Set the name of the objective function.

```
7.119.3.53 virtual std::string OsiCbcSolverInterface::getRowName (int rowIndex, unsigned maxLen = std::string::npos ) const [virtual]
```

Return the name of the row.

```
7.119.3.54 virtual const OsiNameVec& OsiCbcSolverInterface::getRowNames() [virtual]
```

Return a pointer to a vector of row names.

```
7.119.3.55 virtual void OsiCbcSolverInterface::setRowName(int ndx, std::string name) [virtual]
```

Set a row name.

```
7.119.3.56 virtual void OsiCbcSolverInterface::setRowNames ( OsiNameVec & srcNames, int srcStart, int len, int tgtStart )

[virtual]
```

Set multiple row names.

```
7.119.3.57 virtual void OsiCbcSolverInterface::deleteRowNames (int tgtStart, int len ) [virtual]
```

Delete len row names starting at index tgtStart.

```
7.119.3.58 virtual std::string OsiCbcSolverInterface::getColName (int collndex, unsigned maxLen = std::string::npos)
const [virtual]
```

Return the name of the column.

```
7.119.3.59 virtual const OsiNameVec& OsiCbcSolverInterface::getColNames() [virtual]
```

Return a pointer to a vector of column names.

```
7.119.3.60 virtual void OsiCbcSolverInterface::setColName (int ndx, std::string name ) [virtual]
```

Set a column name.

7.119.3.61 virtual void OsiCbcSolverInterface::setColNames (OsiNameVec & srcNames, int srcStart, int len, int tgtStart)

[virtual]

Set multiple column names.

7.119.3.62 virtual void OsiCbcSolverInterface::deleteColNames (int tgtStart, int len) [virtual]

Delete len column names starting at index tgtStart.

7.119.3.63 virtual void OsiCbcSolverInterface::setObjCoeff (int elementIndex, double elementValue) [virtual]

Set an objective function coefficient.

7.119.3.64 virtual void OsiCbcSolverInterface::setColLower (int elementIndex, double elementValue) [virtual]

Set a single column lower bound

Use -DBL MAX for -infinity.

7.119.3.65 virtual void OsiCbcSolverInterface::setColUpper(int elementIndex, double elementValue) [virtual]

Set a single column upper bound

Use DBL MAX for infinity.

7.119.3.66 virtual void OsiCbcSolverInterface::setColBounds (int elementIndex, double lower, double upper) [virtual]

Set a single column lower and upper bound.

7.119.3.67 virtual void OsiCbcSolverInterface::setColSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a number of columns simultaneously

The default implementation just invokes setColLower() and setColUpper() over and over again.

Parameters

indexFirst,index-	pointers to the beginning and after the end of the array of the indices of the variables whose
Last	either bound changes
boundList	the new lower/upper bound pairs for the variables

7.119.3.68 virtual void OsiCbcSolverInterface::setRowLower (int elementIndex, double elementValue) [virtual]

Set a single row lower bound

Use -DBL_MAX for -infinity.

7.119.3.69 virtual void OsiCbcSolverInterface::setRowUpper (int elementIndex, double elementValue) [virtual]

Set a single row upper bound

Use DBL_MAX for infinity.

7.119.3.70 virtual void OsiCbcSolverInterface::setRowBounds (int elementIndex, double lower, double upper) [virtual]

Set a single row lower and upper bound.

7.119.3.71 virtual void OsiCbcSolverInterface::setRowType (int index, char sense, double rightHandSide, double range)
[virtual]

Set the type of a single row

7.119.3.72 virtual void OsiCbcSolverInterface::setRowSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a number of rows simultaneously

The default implementation just invokes setRowLower() and setRowUpper() over and over again.

Parameters

indexFirst,index-	pointers to the beginning and after the end of the array of the indices of the constraints whose
Last	either bound changes
boundList	the new lower/upper bound pairs for the constraints

7.119.3.73 virtual void OsiCbcSolverInterface::setRowSetTypes (const int * indexFirst, const int * indexLast, const char * senseList, const double * rhsList, const double * rangeList) [virtual]

Set the type of a number of rows simultaneously

The default implementation just invokes setRowType() over and over again.

Parameters

indexFirst,index-	pointers to the beginning and after the end of the array of the indices of the constraints whose
Last	any characteristics changes
senseList	the new senses
rhsList	the new right hand sides
rangeList	the new ranges

7.119.3.74 virtual void OsiCbcSolverInterface::setContinuous (int index) [virtual]

Set the index-th variable to be a continuous variable.

7.119.3.75 virtual void OsiCbcSolverInterface::setInteger (int index) [virtual]

Set the index-th variable to be an integer variable.

7.119.3.76 virtual void OsiCbcSolverInterface::setContinuous (const int * indices, int len) [virtual]

Set the variables listed in indices (which is of length len) to be continuous variables.

7.119.3.77 virtual void OsiCbcSolverInterface::setInteger (const int * indices, int len) [virtual]

Set the variables listed in indices (which is of length len) to be integer variables.

7.119.3.78 virtual void OsiCbcSolverInterface::setObjSense (double s) [virtual]

Set objective function sense (1 for min (default), -1 for max,)

7.119.3.79 virtual void OsiCbcSolverInterface::setColSolution (const double * colsol) [virtual]

Set the primal solution column values.

colsol[numcols()] is an array of values of the problem column variables. These values are copied to memory owned by

the solver object or the solver. They will be returned as the result of colsol() until changed by another call to setColsol() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

7.119.3.80 virtual void OsiCbcSolverInterface::setRowPrice (const double * rowprice) [virtual]

Set dual solution vector.

rowprice[numrows()] is an array of values of the problem row dual variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of rowprice() until changed by another call to setRowprice() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

- 7.119.3.81 virtual void OsiCbcSolverInterface::addCol (const CoinPackedVectorBase & vec, const double collb, const double collb, const double obj) [virtual]
- 7.119.3.82 virtual void OsiCbcSolverInterface::addCol (int numberElements, const int * rows, const double * elements, const double collb, const double collb, const double collb, const double obj) [virtual]

Add a column (primal variable) to the problem.

- 7.119.3.83 virtual void OsiCbcSolverInterface::addCols (const int *numcols*, const CoinPackedVectorBase *const * cols, const double * collb, const double
- 7.119.3.84 virtual void OsiCbcSolverInterface::deleteCols (const int num, const int * collndices) [virtual]
- 7.119.3.85 virtual void OsiCbcSolverInterface::addRow (const CoinPackedVectorBase & *vec*, const double *rowlb*, const double *rowub*) [virtual]
- 7.119.3.86 virtual void OsiCbcSolverInterface::addRow (const CoinPackedVectorBase & vec, const char rowsen, const double rowrns, const double rowrng) [virtual]
- 7.119.3.87 virtual void OsiCbcSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * *rows*, const double * *rowlb*, const double * *rowub*) [virtual]
- 7.119.3.88 virtual void OsiCbcSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * rows, const char * rowsen, const double * rowrns, const double * rowrng) [virtual]
- 7.119.3.89 virtual void OsiCbcSolverInterface::deleteRows (const int num, const int * rowIndices) [virtual]
- 7.119.3.90 virtual void OsiCbcSolverInterface::applyRowCuts (int numberCuts, const OsiRowCut * cuts) [virtual]

Apply a collection of row cuts which are all effective.

applyCuts seems to do one at a time which seems inefficient.

7.119.3.91 virtual void OsiCbcSolverInterface::applyRowCuts (int numberCuts, const OsiRowCut ** cuts) [virtual]

Apply a collection of row cuts which are all effective.

applyCuts seems to do one at a time which seems inefficient. This uses array of pointers

7.119.3.92 virtual void OsiCbcSolverInterface::loadProblem (const CoinPackedMatrix & matrix, const double * collb, const double * collb, const double * rowlb, const double * rowlb) [virtual]

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds). If a pointer is 0 then the following values are the default:

colub: all columns have upper bound infinity

- collb: all columns have lower bound 0
- rowub: all rows have upper bound infinity
- rowlb: all rows have lower bound -infinity
- obj: all variables have 0 objective coefficient

```
7.119.3.93 virtual void OsiCbcSolverInterface::assignProblem ( CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& rowlb, double *& rowlb ) [virtual]
```

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions.

```
7.119.3.94 virtual void OsiCbcSolverInterface::loadProblem ( const CoinPackedMatrix & matrix, const double * collb, const double * collb, const double * rowrng) [virtual]
```

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets).

If a pointer is 0 then the following values are the default:

- colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- obj: all variables have 0 objective coefficient
- rowsen: all rows are >=
- rowrhs: all right hand sides are 0
- rowrng: 0 for the ranged rows

```
7.119.3.95 virtual void OsiCbcSolverInterface::assignProblem ( CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& rowrng ) [virtual]
```

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions.

```
7.119.3.96 virtual void OsiCbcSolverInterface::loadProblem ( const int numcols, const int numrows, const CoinBigIndex * start, const int * index, const double * value, const double * collb, const double * colub, const double * obj, const double * rowlb, const double * rowub ) [virtual]
```

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

```
7.119.3.97 virtual void OsiCbcSolverInterface::loadProblem ( const int numcols, const int numrows, const CoinBigIndex * start, const int * index, const double * value, const double * collb, const double * colub, const double * obj, const char * rowsen, const double * rowrhs, const double * rowrng ) [virtual]
```

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

```
7.119.3.98 virtual int OsiCbcSolverInterface::readMps( const char * filename, const char * extension = "mps") [virtual]
Read an mps file from the given filename (defaults to Osi reader) - returns number of errors (see OsiMpsReader class)
7.119.3.99 virtual void OsiCbcSolverInterface::writeMps ( const char * filename, const char * extension = "mps", double
           objSense = 0.0 ) const [virtual]
Write the problem into an mps file of the given filename.
If objSense is non zero then -1.0 forces the code to write a maximization objective and +1.0 to write a minimization one.
If 0.0 then solver can do what it wants
7.119.3.100 virtual int OsiCbcSolverInterface::writeMpsNative (const char * filename, const char ** rowNames, const char **
            columnNames, int formatType = 0, int numberAcross = 2, double objSense = 0.0 ) const [virtual]
Write the problem into an mps file of the given filename, names may be null.
formatType is 0 - normal 1 - extra accuracy 2 - IEEE hex (later)
Returns non-zero on I/O error
7.119.3.101 void OsiCbcSolverInterface::newLanguage ( CoinMessages::Language language )
Set language.
7.119.3.102 void OsiCbcSolverInterface::setLanguage ( CoinMessages::Language language ) [inline]
Definition at line 655 of file OsiCbcSolverInterface.hpp.
7.119.3.103 CbcModel* OsiCbcSolverInterface::getModelPtr() const [inline]
Get pointer to Cbc model.
Definition at line 663 of file OsiCbcSolverInterface.hpp.
7.119.3.104 OsiSolverInterface* OsiCbcSolverInterface::getRealSolverPtr( ) const [inline]
Get pointer to underlying solver.
Definition at line 666 of file OsiCbcSolverInterface.hpp.
7.119.3.105 void OsiCbcSolverInterface::setCutoff ( double value ) [inline]
Set cutoff bound on the objective function.
Definition at line 669 of file OsiCbcSolverInterface.hpp.
7.119.3.106 double OsiCbcSolverInterface::getCutoff( ) const [inline]
Get the cutoff bound on the objective function - always as minimize.
Definition at line 672 of file OsiCbcSolverInterface.hpp.
7.119.3.107 void OsiCbcSolverInterface::setMaximumNodes (int value) [inline]
```

Set the CbcModel::CbcMaxNumNode maximum node limit.

Definition at line 675 of file OsiCbcSolverInterface.hpp.

```
7.119.3.108 int OsiCbcSolverInterface::getMaximumNodes ( ) const [inline]
Get the CbcModel::CbcMaxNumNode maximum node limit.
Definition at line 678 of file OsiCbcSolverInterface.hpp.
7.119.3.109 void OsiCbcSolverInterface::setMaximumSolutions (int value) [inline]
Set the CbcModel::CbcMaxNumSol maximum number of solutions.
Definition at line 681 of file OsiCbcSolverInterface.hpp.
7.119.3.110 int OsiCbcSolverInterface::getMaximumSolutions ( ) const [inline]
Get the CbcModel::CbcMaxNumSol maximum number of solutions.
Definition at line 684 of file OsiCbcSolverInterface.hpp.
7.119.3.111 void OsiCbcSolverInterface::setMaximumSeconds ( double value ) [inline]
Set the CbcModel::CbcMaximumSeconds maximum number of seconds.
Definition at line 687 of file OsiCbcSolverInterface.hpp.
7.119.3.112 double OsiCbcSolverInterface::getMaximumSeconds()const [inline]
Get the CbcModel::CbcMaximumSeconds maximum number of seconds.
Definition at line 690 of file OsiCbcSolverInterface.hpp.
7.119.3.113 bool OsiCbcSolverInterface::isNodeLimitReached ( ) const [inline]
Node limit reached?
Definition at line 693 of file OsiCbcSolverInterface.hpp.
7.119.3.114 bool OsiCbcSolverInterface::isSolutionLimitReached ( ) const [inline]
Solution limit reached?
Definition at line 696 of file OsiCbcSolverInterface.hpp.
7.119.3.115 int OsiCbcSolverInterface::getNodeCount() const [inline]
Get how many Nodes it took to solve the problem.
Definition at line 699 of file OsiCbcSolverInterface.hpp.
7.119.3.116 int OsiCbcSolverInterface::status ( ) const [inline]
Final status of problem - 0 finished, 1 stopped, 2 difficulties.
Definition at line 702 of file OsiCbcSolverInterface.hpp.
7.119.3.117 virtual void OsiCbcSolverInterface::passInMessageHandler ( CoinMessageHandler * handler ) [virtual]
Pass in a message handler.
```

It is the client's responsibility to destroy a message handler installed by this routine; it will not be destroyed when the

solver interface is destroyed.

Generated on Mon Oct 21 2013 19:03:07 for Cbc by Doxygen

7.119.3.118 virtual OsiSolverInterface* OsiCbcSolverInterface::clone (bool copyData = true) const [virtual]

Clone.

7.119.3.119 OsiCbcSolverInterface & OsiCbcSolverInterface::operator= (const OsiCbcSolverInterface & rhs)
Assignment operator.

7.119.3.120 virtual void OsiCbcSolverInterface::applyRowCut (const OsiRowCut & rc) [protected], [virtual]

Apply a row cut (append to constraint matrix).

7.119.3.121 virtual void OsiCbcSolverInterface::applyColCut (const OsiColCut & cc) [protected], [virtual]

Apply a column cut (adjust one or more bounds).

7.119.4 Friends And Related Function Documentation

7.119.4.1 void OsiCbcSolverInterfaceUnitTest (const std::string & mpsDir, const std::string & netlibDir) [friend]

A function that tests the methods in the OsiCbcSolverInterface class.

7.119.5 Member Data Documentation

7.119.5.1 CbcModel* OsiCbcSolverInterface::modelPtr_ [mutable], [protected]

Cbc model represented by this class instance.

Definition at line 754 of file OsiCbcSolverInterface.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/OsiCbc/OsiCbcSolverInterface.hpp

7.120 OsiChooseStrongSubset Class Reference

This class chooses a variable to branch on.

#include <CbcLinked.hpp>

Inheritance diagram for OsiChooseStrongSubset:



Public Member Functions

• OsiChooseStrongSubset ()

Default Constructor.

OsiChooseStrongSubset (const OsiSolverInterface *solver)

Constructor from solver (so we can set up arrays etc)

OsiChooseStrongSubset (const OsiChooseStrongSubset &)

Copy constructor.

OsiChooseStrongSubset & operator= (const OsiChooseStrongSubset &rhs)

Assignment operator.

• virtual OsiChooseVariable * clone () const

Clone.

virtual ~OsiChooseStrongSubset ()

Destructor.

virtual int setupList (OsiBranchingInformation *info, bool initialize)

Sets up strong list and clears all if initialize is true.

virtual int chooseVariable (OsiSolverInterface *solver, OsiBranchingInformation *info, bool fixVariables)

Choose a variable Returns - -1 Node is infeasible 0 Normal termination - we have a candidate 1 All looks satisfied - no candidate 2 We can change the bound on a variable - but we also have a strong branching candidate 3 We can change the bound on a variable - but we have a non-strong branching candidate 4 We can change the bound on a variable - no other candidates We can pick up branch from bestObjectIndex() and bestWhichWay() We can pick up a forced branch (can change bound) from firstForcedObjectIndex() and firstForcedWhichWay() If we have a solution then we can pick up from goodObjectiveValue() and goodSolution() If fixVariables is true then 2,3,4 are all really same as problem changed.

• int numberObjectsToUse () const

Number of objects to use.

void setNumberObjectsToUse (int value)

Set number of objects to use.

Protected Attributes

• int numberObjectsToUse_

Number of objects to be used (and set in solver)

7.120.1 Detailed Description

This class chooses a variable to branch on.

This is just as OsiChooseStrong but it fakes it so only first so many are looked at in this phase

Definition at line 1203 of file CbcLinked.hpp.

7.120.2 Constructor & Destructor Documentation

7.120.2.1 OsiChooseStrongSubset::OsiChooseStrongSubset()

Default Constructor.

7.120.2.2 OsiChooseStrongSubset::OsiChooseStrongSubset (const OsiSolverInterface * solver)

Constructor from solver (so we can set up arrays etc)

7.120.2.3 OsiChooseStrongSubset::OsiChooseStrongSubset (const OsiChooseStrongSubset &)

Copy constructor.

7.120.2.4 virtual OsiChooseStrongSubset::~OsiChooseStrongSubset() [virtual]

Destructor.

7.120.3 Member Function Documentation

7.120.3.1 OsiChooseStrongSubset& OsiChooseStrongSubset::operator=(const OsiChooseStrongSubset & rhs)

Assignment operator.

7.120.3.2 virtual OsiChooseVariable* OsiChooseStrongSubset::clone() const [virtual]

Clone.

7.120.3.3 virtual int OsiChooseStrongSubset::setupList (OsiBranchingInformation * info, bool initialize) [virtual]

Sets up strong list and clears all if initialize is true.

Returns number of infeasibilities. If returns -1 then has worked out node is infeasible!

7.120.3.4 virtual int OsiChooseStrongSubset::chooseVariable (OsiSolverInterface * solver, OsiBranchingInformation * info, bool fixVariables) [virtual]

Choose a variable Returns - -1 Node is infeasible 0 Normal termination - we have a candidate 1 All looks satisfied - no candidate 2 We can change the bound on a variable - but we also have a strong branching candidate 3 We can change the bound on a variable - but we have a non-strong branching candidate 4 We can change the bound on a variable - no other candidates We can pick up branch from bestObjectIndex() and bestWhichWay() We can pick up a forced branch (can change bound) from firstForcedObjectIndex() and firstForcedWhichWay() If we have a solution then we can pick up from goodObjectiveValue() and goodSolution() If fixVariables is true then 2,3,4 are all really same as problem changed.

7.120.3.5 int OsiChooseStrongSubset::numberObjectsToUse() const [inline]

Number of objects to use.

Definition at line 1246 of file CbcLinked.hpp.

7.120.3.6 void OsiChooseStrongSubset::setNumberObjectsToUse(int value) [inline]

Set number of objects to use.

Definition at line 1250 of file CbcLinked.hpp.

7.120.4 Member Data Documentation

7.120.4.1 int OsiChooseStrongSubset::numberObjectsToUse_ [protected]

Number of objects to be used (and set in solver)

Definition at line 1257 of file CbcLinked.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.121 OsiLink Class Reference

Define Special Linked Ordered Sets.

#include <CbcLinked.hpp>

Inheritance diagram for OsiLink:



Public Member Functions

- OsiLink ()
- OsiLink (const OsiSolverInterface *solver, int yRow, int yColumn, double meshSize)

Useful constructor -.

- OsiLink (const OsiLink &)
- virtual OsiObject * clone () const

Clone.

- OsiLink & operator= (const OsiLink &rhs)
- virtual ~OsiLink ()
- virtual double infeasibility (const OsiBranchingInformation *info, int &whichWay) const

Infeasibility - large is 0.5.

 $\bullet \ \ virtual \ double \ feasible Region \ (OsiSolverInterface \ *solver, \ const \ OsiBranchingInformation \ *info) \ const$

Set bounds to fix the variable at the current (integer) value.

• virtual OsiBranchingObject * createBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way) const

Creates a branching object.

• virtual void resetSequenceEtc (int numberColumns, const int *originalColumns)

Redoes data when sequence numbers change.

• int numberLinks () const

Number of links for each member.

· virtual bool canDoHeuristics () const

Return true if object can take part in normal heuristics.

• virtual bool boundBranch () const

Return true if branch should only bound variables.

7.121.1 Detailed Description

Define Special Linked Ordered Sets.

New style

members and weights may be stored in SOS object

This is for y and x*f(y) and z*g(y) etc

Definition at line 600 of file CbcLinked.hpp.

```
7.121.2 Constructor & Destructor Documentation
7.121.2.1 OsiLink::OsiLink()
7.121.2.2 OsiLink::OsiLink ( const OsiSolverInterface * solver, int yRow, int yColumn, double meshSize )
Useful constructor -.
7.121.2.3 OsiLink::OsiLink (const OsiLink &)
7.121.2.4 virtual OsiLink::~OsiLink() [virtual]
7.121.3 Member Function Documentation
7.121.3.1 virtual OsiObject* OsiLink::clone( ) const [virtual]
Clone.
7.121.3.2 OsiLink& OsiLink::operator= ( const OsiLink & rhs )
7.121.3.3 virtual double OsiLink::infeasibility ( const OsiBranchingInformation * info, int & whichWay ) const [virtual]
Infeasibility - large is 0.5.
7.121.3.4 virtual double OsiLink::feasibleRegion (OsiSolverInterface * solver, const OsiBranchingInformation * info ) const
          [virtual]
Set bounds to fix the variable at the current (integer) value.
Given an integer value, set the lower and upper bounds to fix the variable. Returns amount it had to move variable.
7.121.3.5 virtual OsiBranchingObject * OsiLink::createBranch ( OsiSolverInterface * solver, const OsiBranchingInformation * info,
          int way ) const [virtual]
Creates a branching object.
The preferred direction is set by way, 0 for down, 1 for up.
7.121.3.6 virtual void OsiLink::resetSequenceEtc (int numberColumns, const int * originalColumns ) [virtual]
Redoes data when sequence numbers change.
7.121.3.7 int OsiLink::numberLinks ( ) const [inline]
Number of links for each member.
Definition at line 647 of file CbcLinked.hpp.
7.121.3.8 virtual bool OsiLink::canDoHeuristics ( ) const [inline], [virtual]
Return true if object can take part in normal heuristics.
Definition at line 653 of file CbcLinked.hpp.
7.121.3.9 virtual bool OsiLink::boundBranch ( ) const [inline], [virtual]
Return true if branch should only bound variables.
```

Definition at line 658 of file CbcLinked.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.122 OsiLinkBranchingObject Class Reference

Branching object for Linked ordered sets.

```
#include <CbcLinked.hpp>
```

Inheritance diagram for OsiLinkBranchingObject:



Public Member Functions

- OsiLinkBranchingObject ()
- OsiLinkBranchingObject (OsiSolverInterface *solver, const OsiLink *originalObject, int way, double separator)
- OsiLinkBranchingObject (const OsiLinkBranchingObject &)
- OsiLinkBranchingObject & operator= (const OsiLinkBranchingObject &rhs)
- virtual OsiBranchingObject * clone () const

Clone.

- virtual ~OsiLinkBranchingObject ()
- virtual double branch (OsiSolverInterface *solver)

Does next branch and updates state.

virtual void print (const OsiSolverInterface *solver=NULL)

Print something about branch - only if log level high.

7.122.1 Detailed Description

Branching object for Linked ordered sets.

Definition at line 678 of file CbcLinked.hpp.

- 7.122.2 Constructor & Destructor Documentation
- 7.122.2.1 OsiLinkBranchingObject::OsiLinkBranchingObject ()
- 7.122.2.2 OsiLinkBranchingObject::OsiLinkBranchingObject (OsiSolverInterface * solver, const OsiLink * originalObject, int way, double separator)
- 7.122.2.3 OsiLinkBranchingObject::OsiLinkBranchingObject (const OsiLinkBranchingObject &)
- **7.122.2.4** virtual OsiLinkBranchingObject::~OsiLinkBranchingObject() [virtual]
- 7.122.3 Member Function Documentation

7.122.3.1 OsiLinkBranchingObject& OsiLinkBranchingObject::operator=(const OsiLinkBranchingObject & rhs)

7.122.3.2 virtual OsiBranchingObject* OsiLinkBranchingObject::clone () const [virtual]

Clone.

7.122.3.3 virtual double OsiLinkBranchingObject::branch (OsiSolverInterface * solver) [virtual]

Does next branch and updates state.

7.122.3.4 virtual void OsiLinkBranchingObject::print (const OsiSolverInterface * solver = NULL) [virtual]

Print something about branch - only if log level high.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.123 OsiLinkedBound Class Reference

List of bounds which depend on other bounds.

```
#include <CbcLinked.hpp>
```

Public Member Functions

Action methods

void updateBounds (ClpSimplex *solver)

Update other bounds.

Constructors and destructors

• OsiLinkedBound ()

Default Constructor.

• OsiLinkedBound (OsiSolverInterface *model, int variable, int numberAffected, const int *positionL, const int *positionU, const double *multiplier)

Useful Constructor.

• OsiLinkedBound (const OsiLinkedBound &)

Copy constructor.

OsiLinkedBound & operator= (const OsiLinkedBound &rhs)

Assignment operator.

∼OsiLinkedBound ()

Destructor.

Sets and Gets

• int variable () const

Get variable.

 void addBoundModifier (bool upperBoundAffected, bool useUpperBound, int whichVariable, double multiplier=1.0)

Add a bound modifier.

7.123.1 Detailed Description List of bounds which depend on other bounds. Definition at line 300 of file CbcLinked.hpp. 7.123.2 Constructor & Destructor Documentation 7.123.2.1 OsiLinkedBound::OsiLinkedBound () Default Constructor. 7.123.2.2 OsiLinkedBound::OsiLinkedBound (OsiSolverInterface * model, int variable, int numberAffected, const int * positionL, const int * positionU, const double * multiplier) Useful Constructor. 7.123.2.3 OsiLinkedBound::OsiLinkedBound (const OsiLinkedBound &) Copy constructor. 7.123.2.4 OsiLinkedBound:: ~OsiLinkedBound () Destructor. 7.123.3 Member Function Documentation 7.123.3.1 void OsiLinkedBound::updateBounds (ClpSimplex * solver) Update other bounds. 7.123.3.2 OsiLinkedBound& OsiLinkedBound::operator=(const OsiLinkedBound & rhs) Assignment operator. 7.123.3.3 int OsiLinkedBound::variable () const [inline] Get variable. Definition at line 334 of file CbcLinked.hpp. 7.123.3.4 void OsiLinkedBound::addBoundModifier (bool upperBoundAffected, bool useUpperBound, int whichVariable, double multiplier = 1.0) Add a bound modifier. The documentation for this class was generated from the following file:

7.124 OsiOldLink Class Reference

/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

#include <CbcLinked.hpp>

Inheritance diagram for OsiOldLink:



Public Member Functions

- OsiOldLink ()
- OsiOldLink (const OsiSolverInterface *solver, int numberMembers, int numberLinks, int first, const double *weights, int setNumber)

Useful constructor - A valid solution is if all variables are zero apart from k*numberLink to (k+1)*numberLink-1 where k is 0 through numberInSet-1.

 OsiOldLink (const OsiSolverInterface *solver, int numberMembers, int numberLinks, int typeSOS, const int *which, const double *weights, int setNumber)

Useful constructor - A valid solution is if all variables are zero apart from k*numberLink to (k+1)*numberLink-1 where k is 0 through numberInSet-1.

- OsiOldLink (const OsiOldLink &)
- virtual OsiObject * clone () const

Clone.

- OsiOldLink & operator= (const OsiOldLink &rhs)
- virtual ∼OsiOldLink ()
- virtual double infeasibility (const OsiBranchingInformation *info, int &whichWay) const

Infeasibility - large is 0.5.

virtual double feasibleRegion (OsiSolverInterface *solver, const OsiBranchingInformation *info) const

Set bounds to fix the variable at the current (integer) value.

• virtual OsiBranchingObject * createBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way) const

Creates a branching object.

virtual void resetSequenceEtc (int numberColumns, const int *originalColumns)

Redoes data when sequence numbers change.

• int numberLinks () const

Number of links for each member.

• virtual bool canDoHeuristics () const

Return true if object can take part in normal heuristics.

virtual bool boundBranch () const

Return true if branch should only bound variables.

7.124.1 Detailed Description

Definition at line 434 of file CbcLinked.hpp.

7.124.2 Constructor & Destructor Documentation

7.124.2.1 OsiOldLink::OsiOldLink()

7.124.2.2 OsiOldLink::OsiOldLink (const OsiSolverInterface * solver, int numberMembers, int numberLinks, int first, const double * weights, int setNumber)

Useful constructor - A valid solution is if all variables are zero apart from k*numberLink to (k+1)*numberLink-1 where k is 0 through numberInSet-1.

The length of weights array is numberInSet. For this constructor the variables in matrix are the numberInSet*numberLink starting at first. If weights null then 0,1,2..

7.124.2.3 OsiOldLink::OsiOldLink (const OsiSolverInterface * solver, int numberMembers, int numberLinks, int typeSOS, const int * which, const double * weights, int setNumber)

Useful constructor - A valid solution is if all variables are zero apart from k*numberLink to (k+1)*numberLink-1 where k is 0 through numberInSet-1.

The length of weights array is numberInSet. For this constructor the variables are given by list - grouped. If weights null then 0.1.2..

```
7.124.2.4 OsiOldLink::OsiOldLink ( const OsiOldLink & )
```

```
7.124.2.5 virtual OsiOldLink::~OsiOldLink( ) [virtual]
```

7.124.3 Member Function Documentation

```
7.124.3.1 virtual OsiObject* OsiOldLink::clone() const [virtual]
```

Clone.

7.124.3.2 OsiOldLink& OsiOldLink::operator= (const OsiOldLink & rhs)

7.124.3.3 virtual double OsiOldLink::infeasibility (const OsiBranchingInformation * info, int & whichWay) const [virtual]

Infeasibility - large is 0.5.

7.124.3.4 virtual double OsiOldLink::feasibleRegion (OsiSolverInterface * solver, const OsiBranchingInformation * info) const [virtual]

Set bounds to fix the variable at the current (integer) value.

Given an integer value, set the lower and upper bounds to fix the variable. Returns amount it had to move variable.

7.124.3.5 virtual OsiBranchingObject* OsiOldLink::createBranch (OsiSolverInterface * solver, const OsiBranchingInformation * info, int way) const [virtual]

Creates a branching object.

The preferred direction is set by way, 0 for down, 1 for up.

7.124.3.6 virtual void OsiOldLink::resetSequenceEtc (int numberColumns, const int * originalColumns) [virtual]

Redoes data when sequence numbers change.

7.124.3.7 int OsiOldLink::numberLinks () const [inline]

Number of links for each member.

Definition at line 494 of file CbcLinked.hpp.

7.124.3.8 virtual bool OsiOldLink::canDoHeuristics () const [inline], [virtual]

Return true if object can take part in normal heuristics.

Definition at line 500 of file CbcLinked.hpp.

7.124.3.9 virtual bool OsiOldLink::boundBranch() const [inline], [virtual]

Return true if branch should only bound variables.

Definition at line 505 of file CbcLinked.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.125 OsiOldLinkBranchingObject Class Reference

Branching object for Linked ordered sets.

#include <CbcLinked.hpp>

Inheritance diagram for OsiOldLinkBranchingObject:



Public Member Functions

- OsiOldLinkBranchingObject ()
- OsiOldLinkBranchingObject (OsiSolverInterface *solver, const OsiOldLink *originalObject, int way, double separator)
- OsiOldLinkBranchingObject (const OsiOldLinkBranchingObject &)
- OsiOldLinkBranchingObject & operator= (const OsiOldLinkBranchingObject &rhs)
- virtual OsiBranchingObject * clone () const

Clone.

- virtual ~OsiOldLinkBranchingObject ()
- virtual double branch (OsiSolverInterface *solver)

Does next branch and updates state.

virtual void print (const OsiSolverInterface *solver=NULL)

Print something about branch - only if log level high.

7.125.1 Detailed Description

Branching object for Linked ordered sets.

Definition at line 518 of file CbcLinked.hpp.

```
7.125.2.1 OsiOldLinkBranchingObject::OsiOldLinkBranchingObject ( )
7.125.2.2 OsiOldLinkBranchingObject::OsiOldLinkBranchingObject ( OsiSolverInterface * solver, const OsiOldLink *
          originalObject, int way, double separator )
7.125.2.3 OsiOldLinkBranchingObject::OsiOldLinkBranchingObject ( const OsiOldLinkBranchingObject & )
7.125.2.4 virtual OsiOldLinkBranchingObject:: ~OsiOldLinkBranchingObject( ) [virtual]
7.125.3 Member Function Documentation
7.125.3.1 OsiOldLinkBranchingObject& OsiOldLinkBranchingObject & const OsiOldLinkBranchingObject &
7.125.3.2 virtual OsiBranchingObject* OsiOldLinkBranchingObject::clone ( ) const [virtual]
```

Clone.

7.125.3.3 virtual double OsiOldLinkBranchingObject::branch (OsiSolverInterface * solver) [virtual]

Does next branch and updates state.

7.125.2 Constructor & Destructor Documentation

7.125.3.4 virtual void OsiOldLinkBranchingObject::print (const OsiSolverInterface * solver = NULL) [virtual]

Print something about branch - only if log level high.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.126 OsiOneLink Class Reference

Define data for one link.

#include <CbcLinked.hpp>

Public Member Functions

- OsiOneLink ()
- OsiOneLink (const OsiSolverInterface *solver, int xRow, int xColumn, int xyRow, const char *functionString) Useful constructor -.
- OsiOneLink (const OsiOneLink &)
- OsiOneLink & operator= (const OsiOneLink &rhs)
- virtual ∼OsiOneLink ()

Public Attributes

int xRow

data

int xColumn

Column which defines x.

```
    int xyRow

          Output row.

    std::string function_

          Function.
7.126.1 Detailed Description
Define data for one link.
Definition at line 558 of file CbcLinked.hpp.
7.126.2 Constructor & Destructor Documentation
7.126.2.1 OsiOneLink::OsiOneLink()
7.126.2.2 OsiOneLink::OsiOneLink ( const OsiSolverInterface * solver, int xRow, int xColumn, int xyRow, const char *
          functionString )
Useful constructor -.
7.126.2.3 OsiOneLink::OsiOneLink ( const OsiOneLink & )
7.126.2.4 virtual OsiOneLink::~OsiOneLink() [virtual]
7.126.3 Member Function Documentation
7.126.3.1 OsiOneLink& OsiOneLink::operator= ( const OsiOneLink & rhs )
7.126.4 Member Data Documentation
7.126.4.1 int OsiOneLink::xRow_
data
Row which defines x (if -1 then no x)
Definition at line 583 of file CbcLinked.hpp.
7.126.4.2 int OsiOneLink::xColumn_
Column which defines x.
Definition at line 585 of file CbcLinked.hpp.
7.126.4.3 int OsiOneLink::xyRow
Output row.
Definition at line 587 of file CbcLinked.hpp.
7.126.4.4 std::string OsiOneLink::function_
Function.
Definition at line 589 of file CbcLinked.hpp.
```

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.127 CbcGenCtlBlk::osiParamsInfo_struct Struct Reference

Start and end of OsiSolverInterface parameters in parameter vector.

```
#include <CbcGenCtlBlk.hpp>
```

Public Attributes

- int first
- int last_

7.127.1 Detailed Description

Start and end of OsiSolverInterface parameters in parameter vector.

Definition at line 614 of file CbcGenCtlBlk.hpp.

7.127.2 Member Data Documentation

7.127.2.1 int CbcGenCtlBlk::osiParamsInfo_struct::first_

Definition at line 615 of file CbcGenCtlBlk.hpp.

7.127.2.2 int CbcGenCtlBlk::osiParamsInfo_struct::last_

Definition at line 616 of file CbcGenCtlBlk.hpp.

The documentation for this struct was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcGenCtlBlk.hpp

7.128 OsiSimpleFixedInteger Class Reference

Define a single integer class - but one where you keep branching until fixed even if satisfied.

```
#include <CbcLinked.hpp>
```

Inheritance diagram for OsiSimpleFixedInteger:



Public Member Functions

OsiSimpleFixedInteger ()

Default Constructor.

• OsiSimpleFixedInteger (const OsiSolverInterface *solver, int iColumn)

Useful constructor - passed solver index.

OsiSimpleFixedInteger (int iColumn, double lower, double upper)

Useful constructor - passed solver index and original bounds.

OsiSimpleFixedInteger (const OsiSimpleInteger &)

Useful constructor - passed simple integer.

• OsiSimpleFixedInteger (const OsiSimpleFixedInteger &)

Copy constructor.

virtual OsiObject * clone () const

Clone.

OsiSimpleFixedInteger & operator= (const OsiSimpleFixedInteger &rhs)

Assignment operator.

virtual ∼OsiSimpleFixedInteger ()

Destructor.

• virtual double infeasibility (const OsiBranchingInformation ∗info, int &whichWay) const

Infeasibility - large is 0.5.

virtual OsiBranchingObject * createBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way) const

Creates a branching object.

7.128.1 Detailed Description

Define a single integer class - but one where you keep branching until fixed even if satisfied.

Definition at line 1089 of file CbcLinked.hpp.

7.128.2 Constructor & Destructor Documentation

7.128.2.1 OsiSimpleFixedInteger::OsiSimpleFixedInteger ()

Default Constructor.

7.128.2.2 OsiSimpleFixedInteger::OsiSimpleFixedInteger (const OsiSolverInterface * solver, int iColumn)

Useful constructor - passed solver index.

7.128.2.3 OsiSimpleFixedInteger::OsiSimpleFixedInteger (int iColumn, double lower, double upper)

Useful constructor - passed solver index and original bounds.

7.128.2.4 OsiSimpleFixedInteger::OsiSimpleFixedInteger (const OsiSimpleInteger &)

Useful constructor - passed simple integer.

7.128.2.5 OsiSimpleFixedInteger::OsiSimpleFixedInteger (const OsiSimpleFixedInteger &)

Copy constructor.

7.128.2.6 virtual OsiSimpleFixedInteger::~OsiSimpleFixedInteger() [virtual]

Destructor.

7.128.3 Member Function Documentation

7.128.3.1 virtual OsiObject* OsiSimpleFixedInteger::clone () const [virtual]

Clone.

7.128.3.2 OsiSimpleFixedInteger & OsiSimpleFixedInteger::operator= (const OsiSimpleFixedInteger & rhs)

Assignment operator.

7.128.3.3 virtual double OsiSimpleFixedInteger::infeasibility (const OsiBranchingInformation * info, int & whichWay) const [virtual]

Infeasibility - large is 0.5.

7.128.3.4 virtual OsiBranchingObject* OsiSimpleFixedInteger::createBranch (OsiSolverInterface * solver, const OsiBranchingInformation * info, int way) const [virtual]

Creates a branching object.

The preferred direction is set by way, 0 for down, 1 for up.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.129 OsiSolverLinearizedQuadratic Class Reference

This is to allow the user to replace initialSolve and resolve.

#include <CbcLinked.hpp>

Inheritance diagram for OsiSolverLinearizedQuadratic:



Public Member Functions

Solve methods

• virtual void initialSolve () Solve initial LP relaxation.

Constructors and destructors

OsiSolverLinearizedQuadratic ()

Default Constructor.

• OsiSolverLinearizedQuadratic (ClpSimplex *quadraticModel)

Useful constructor (solution should be good)

 virtual OsiSolverInterface * clone (bool copyData=true) const Clone. OsiSolverLinearizedQuadratic (const OsiSolverLinearizedQuadratic &)

Copy constructor.

OsiSolverLinearizedQuadratic & operator= (const OsiSolverLinearizedQuadratic &rhs)

Assignment operator.

virtual ~OsiSolverLinearizedQuadratic ()

Destructor.

Sets and Gets

double bestObjectiveValue () const

Objective value of best solution found internally.

const double * bestSolution () const

Best solution found internally.

void setSpecialOptions3 (int value)

Set special options.

• int specialOptions3 () const

Get special options.

ClpSimplex * quadraticModel () const

Copy of quadratic model if one.

Protected Attributes

Private member data

double bestObjectiveValue_

Objective value of best solution found internally.

ClpSimplex * quadraticModel_

Copy of quadratic model if one.

double * bestSolution

Best solution found internally.

int specialOptions3_

0 bit (1) - don't do mini B&B 1 bit (2) - quadratic only in objective

7.129.1 Detailed Description

This is to allow the user to replace initialSolve and resolve.

Definition at line 1318 of file CbcLinked.hpp.

7.129.2 Constructor & Destructor Documentation

7.129.2.1 OsiSolverLinearizedQuadratic::OsiSolverLinearizedQuadratic ()

Default Constructor.

7.129.2.2 OsiSolverLinearizedQuadratic::OsiSolverLinearizedQuadratic (CIpSimplex * quadraticModel)

Useful constructor (solution should be good)

7.129.2.3 OsiSolverLinearizedQuadratic::OsiSolverLinearizedQuadratic (const OsiSolverLinearizedQuadratic &)

Copy constructor.

```
7.129.2.4 virtual OsiSolverLinearizedQuadratic::~OsiSolverLinearizedQuadratic() [virtual]
Destructor.
7.129.3 Member Function Documentation
7.129.3.1 virtual void OsiSolverLinearizedQuadratic::initialSolve() [virtual]
Solve initial LP relaxation.
7.129.3.2 virtual OsiSolverInterface* OsiSolverLinearizedQuadratic::clone ( bool copyData = true ) const [virtual]
Clone.
7.129.3.3 OsiSolverLinearizedQuadratic& OsiSolverLinearizedQuadratic::operator= ( const
          OsiSolverLinearizedQuadratic & rhs )
Assignment operator.
7.129.3.4 double OsiSolverLinearizedQuadratic::bestObjectiveValue() const [inline]
Objective value of best solution found internally.
Definition at line 1353 of file CbcLinked.hpp.
7.129.3.5 const double* OsiSolverLinearizedQuadratic::bestSolution ( ) const [inline]
Best solution found internally.
Definition at line 1357 of file CbcLinked.hpp.
7.129.3.6 void OsiSolverLinearizedQuadratic::setSpecialOptions3 (int value) [inline]
Set special options.
Definition at line 1361 of file CbcLinked.hpp.
7.129.3.7 int OsiSolverLinearizedQuadratic::specialOptions3 ( ) const [inline]
Get special options.
Definition at line 1365 of file CbcLinked.hpp.
7.129.3.8 ClpSimplex* OsiSolverLinearizedQuadratic::quadraticModel( ) const [inline]
Copy of quadratic model if one.
Definition at line 1369 of file CbcLinked.hpp.
7.129.4 Member Data Documentation
7.129.4.1 double OsiSolverLinearizedQuadratic::bestObjectiveValue_ [protected]
Objective value of best solution found internally.
Definition at line 1385 of file CbcLinked.hpp.
```

7.129.4.2 ClpSimplex* OsiSolverLinearizedQuadratic::quadraticModel_ [protected]

Copy of quadratic model if one.

Definition at line 1387 of file CbcLinked.hpp.

7.129.4.3 double* OsiSolverLinearizedQuadratic::bestSolution_ [protected]

Best solution found internally.

Definition at line 1389 of file CbcLinked.hpp.

7.129.4.4 int OsiSolverLinearizedQuadratic::specialOptions3_ [protected]

0 bit (1) - don't do mini B&B 1 bit (2) - quadratic only in objective

Definition at line 1394 of file CbcLinked.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.130 OsiSolverLink Class Reference

This is to allow the user to replace initialSolve and resolve This version changes coefficients.

#include <CbcLinked.hpp>

Inheritance diagram for OsiSolverLink:



Public Member Functions

Solve methods

virtual void initialSolve ()

Solve initial LP relaxation.

virtual void resolve ()

Resolve an LP relaxation after problem modification.

virtual int fathom (bool allFixed)

Problem specific Returns -1 if node fathomed and no solution 0 if did nothing 1 if node fathomed and solution allFixed is true if all LinkedBound variables are fixed.

• double * nonlinearSLP (int numberPasses, double deltaTolerance)

Solves nonlinear problem from CoinModel using SLP - may be used as crash for other algorithms when number of iterations small.

double linearizedBAB (CglStored *cut)

Solve linearized quadratic objective branch and bound.

double * heuristicSolution (int numberPasses, double deltaTolerance, int mode)

Solves nonlinear problem from CoinModel using SLP - and then tries to get heuristic solution Returns solution array mode - 0 just get continuous 1 round and try normal bab 2 use defaultBound_ to bound integer variables near current solution.

• int doAOCuts (CglTemporary *cutGen, const double *solution, const double *solution2)

Do OA cuts.

Constructors and destructors

OsiSolverLink ()

Default Constructor.

OsiSolverLink (CoinModel &modelObject)

This creates from a coinModel object.

- void load (CoinModel &modelObject, bool tightenBounds=false, int logLevel=1)
- virtual OsiSolverInterface * clone (bool copyData=true) const

Clone

OsiSolverLink (const OsiSolverLink &)

Copy constructor.

OsiSolverLink & operator= (const OsiSolverLink &rhs)

Assignment operator.

virtual ∼OsiSolverLink ()

Destructor.

Sets and Gets

 void addBoundModifier (bool upperBoundAffected, bool useUpperBound, int whichVariable, int whichVariable-Affected, double multiplier=1.0)

Add a bound modifier.

int updateCoefficients (ClpSimplex *solver, CoinPackedMatrix *matrix)

Update coefficients - returns number updated if in updating mode.

void analyzeObjects ()

Analyze constraints to see which are convex (quadratic)

• void addTighterConstraints ()

Add reformulated bilinear constraints.

double bestObjectiveValue () const

Objective value of best solution found internally.

void setBestObjectiveValue (double value)

Set objective value of best solution found internally.

• const double * bestSolution () const

Best solution found internally.

void setBestSolution (const double *solution, int numberColumns)

Set best solution found internally.

void setSpecialOptions2 (int value)

Set special options.

void sayConvex (bool convex)

Say convex (should work it out) - if convex false then strictly concave.

• int specialOptions2 () const

Get special options.

CoinPackedMatrix * cleanMatrix () const

Clean copy of matrix So we can add rows.

CoinPackedMatrix * originalRowCopy () const

Row copy of matrix Just genuine columns and rows Linear part.

ClpSimplex * quadraticModel () const

Copy of quadratic model if one.

• CoinPackedMatrix * quadraticRow (int rowNumber, double *linear) const

Gets correct form for a quadratic row - user to delete.

• double defaultMeshSize () const

Default meshSize.

- void setDefaultMeshSize (double value)
- double defaultBound () const

Default maximumbound.

- void setDefaultBound (double value)
- void setIntegerPriority (int value)

Set integer priority.

• int integerPriority () const

Get integer priority.

• int objective Variable () const

Objective transfer variable if one.

• void setBiLinearPriority (int value)

Set biLinear priority.

int biLinearPriority () const

Get biLinear priority.

const CoinModel * coinModel () const

Return CoinModel.

void setBiLinearPriorities (int value, double meshSize=1.0)

Set all biLinear priorities on x-x variables.

• void setBranchingStrategyOnVariables (int strategyValue, int priorityValue=-1, int mode=7)

Set options and priority on all or some biLinear variables 1 - on I-I 2 - on I-x 4 - on x-x or combinations.

void setMeshSizes (double value)

Set all mesh sizes on x-x variables.

void setFixedPriority (int priorityValue)

Two tier integer problem where when set of variables with priority less than this are fixed the problem becomes an easier integer problem.

Protected Member Functions

functions

void gutsOfDestructor (bool justNullify=false)

Do real work of initialize.

void gutsOfCopy (const OsiSolverLink &rhs)

Do real work of copy.

Protected Attributes

Private member data

CoinPackedMatrix * matrix

Clean copy of matrix Marked coefficients will be multiplied by L or U.

CoinPackedMatrix * originalRowCopy_

Row copy of matrix Just genuine columns and rows.

ClpSimplex * quadraticModel_

Copy of quadratic model if one.

int numberNonLinearRows_

Number of rows with nonLinearities.

int * startNonLinear_

Starts of lists.

int * rowNonLinear_

Row number for a list.

int * convex

Indicator whether is convex, concave or neither -1 concave, 0 neither, +1 convex.

int * whichNonLinear

Indices in a list/row.

CoinModel coinModel

Model in CoinModel format.

int numberVariables

Number of variables in tightening phase.

• OsiLinkedBound * info_

Information.

int specialOptions2

0 bit (1) - call fathom (may do mini B&B) 1 bit (2) - quadratic only in objective (add OA cuts) 2 bit (4) - convex 3 bit (8) - try adding OA cuts 4 bit (16) - add linearized constraints

int objectiveRow

Objective transfer row if one.

int objectiveVariable

Objective transfer variable if one.

double bestObjectiveValue_

Objective value of best solution found internally.

· double defaultMeshSize_

Default mesh.

double defaultBound

Default maximum bound.

double * bestSolution_

Best solution found internally.

· int integerPriority_

Priority for integers.

int biLinearPriority_

Priority for bilinear.

int numberFix_

Number of variables which when fixed help.

int * fixVariables_

list of fixed variables

7.130.1 Detailed Description

This is to allow the user to replace initialSolve and resolve This version changes coefficients.

Definition at line 29 of file CbcLinked.hpp.

7.130.2 Constructor & Destructor Documentation

7.130.2.1 OsiSolverLink::OsiSolverLink()

Default Constructor.

7.130.2.2 OsiSolverLink::OsiSolverLink (CoinModel & modelObject)

This creates from a coinModel object.

if errors.then number of sets is -1

This creates linked ordered sets information. It assumes -

for product terms syntax is yy*f(zz) also just f(zz) is allowed and even a constant

modelObject not const as may be changed as part of process.

7.130.2.3 OsiSolverLink::OsiSolverLink (const OsiSolverLink &) Copy constructor. 7.130.2.4 virtual OsiSolverLink::~OsiSolverLink() [virtual] Destructor. 7.130.3 Member Function Documentation 7.130.3.1 virtual void OsiSolverLink::initialSolve() [virtual] Solve initial LP relaxation. 7.130.3.2 virtual void OsiSolverLink::resolve() [virtual] Resolve an LP relaxation after problem modification. 7.130.3.3 virtual int OsiSolverLink::fathom (bool allFixed) [virtual] Problem specific Returns -1 if node fathomed and no solution 0 if did nothing 1 if node fathomed and solution allFixed is true if all LinkedBound variables are fixed. 7.130.3.4 double * OsiSolverLink::nonlinearSLP (int numberPasses, double deltaTolerance) Solves nonlinear problem from CoinModel using SLP - may be used as crash for other algorithms when number of iterations small. Also exits if all problematical variables are changing less than deltaTolerance Returns solution array 7.130.3.5 double OsiSolverLink::linearizedBAB (CglStored * cut) Solve linearized quadratic objective branch and bound. Return cutoff and OA cut 7.130.3.6 double * OsiSolverLink::heuristicSolution (int numberPasses, double deltaTolerance, int mode) Solves nonlinear problem from CoinModel using SLP - and then tries to get heuristic solution Returns solution array mode - 0 just get continuous 1 round and try normal bab 2 use defaultBound to bound integer variables near current solution. 7.130.3.7 int OsiSolverLink::doAOCuts (CgITemporary * cutGen, const double * solution, const double * solution2) Do OA cuts. 7.130.3.8 void OsiSolverLink::load (CoinModel & modelObject, bool tightenBounds = false, int logLevel = 1) 7.130.3.9 virtual OsiSolverInterface* OsiSolverLink::clone (bool copyData = true) const [virtual] Clone. Reimplemented from CbcOsiSolver.

Assignment operator.

7.130.3.10 OsiSolverLink& OsiSolverLink::operator= (const OsiSolverLink & rhs)

```
7.130.3.11 void OsiSolverLink::addBoundModifier ( bool upperBoundAffected, bool useUpperBound, int whichVariable, int
           which Variable Affected, double multiplier = 1.0)
Add a bound modifier.
7.130.3.12 int OsiSolverLink::updateCoefficients ( ClpSimplex * solver, CoinPackedMatrix * matrix )
Update coefficients - returns number updated if in updating mode.
7.130.3.13 void OsiSolverLink::analyzeObjects ( )
Analyze constraints to see which are convex (quadratic)
7.130.3.14 void OsiSolverLink::addTighterConstraints ( )
Add reformulated bilinear constraints.
7.130.3.15 double OsiSolverLink::bestObjectiveValue() const [inline]
Objective value of best solution found internally.
Definition at line 122 of file CbcLinked.hpp.
7.130.3.16 void OsiSolverLink::setBestObjectiveValue ( double value ) [inline]
Set objective value of best solution found internally.
Definition at line 126 of file CbcLinked.hpp.
7.130.3.17 const double* OsiSolverLink::bestSolution ( ) const [inline]
Best solution found internally.
Definition at line 130 of file CbcLinked.hpp.
7.130.3.18 void OsiSolverLink::setBestSolution ( const double * solution, int numberColumns )
Set best solution found internally.
7.130.3.19 void OsiSolverLink::setSpecialOptions2(int value) [inline]
Set special options.
Definition at line 136 of file CbcLinked.hpp.
7.130.3.20 void OsiSolverLink::sayConvex ( bool convex )
Say convex (should work it out) - if convex false then strictly concave.
7.130.3.21 int OsiSolverLink::specialOptions2( ) const [inline]
Get special options.
Definition at line 142 of file CbcLinked.hpp.
7.130.3.22 CoinPackedMatrix* OsiSolverLink::cleanMatrix ( ) const [inline]
Clean copy of matrix So we can add rows.
```

Definition at line 148 of file CbcLinked.hpp.

```
7.130.3.23 CoinPackedMatrix* OsiSolverLink::originalRowCopy() const [inline]
Row copy of matrix Just genuine columns and rows Linear part.
Definition at line 155 of file CbcLinked.hpp.
7.130.3.24 ClpSimplex* OsiSolverLink::quadraticModel() const [inline]
Copy of quadratic model if one.
Definition at line 159 of file CbcLinked.hpp.
7.130.3.25 CoinPackedMatrix* OsiSolverLink::quadraticRow ( int rowNumber, double * linear ) const
Gets correct form for a quadratic row - user to delete.
7.130.3.26 double OsiSolverLink::defaultMeshSize ( ) const [inline]
Default meshSize.
Definition at line 165 of file CbcLinked.hpp.
7.130.3.27 void OsiSolverLink::setDefaultMeshSize ( double value ) [inline]
Definition at line 168 of file CbcLinked.hpp.
7.130.3.28 double OsiSolverLink::defaultBound ( ) const [inline]
Default maximumbound.
Definition at line 172 of file CbcLinked.hpp.
7.130.3.29 void OsiSolverLink::setDefaultBound ( double value ) [inline]
Definition at line 175 of file CbcLinked.hpp.
7.130.3.30 void OsiSolverLink::setIntegerPriority (int value) [inline]
Set integer priority.
Definition at line 179 of file CbcLinked.hpp.
7.130.3.31 int OsiSolverLink::integerPriority ( ) const [inline]
Get integer priority.
Definition at line 183 of file CbcLinked.hpp.
7.130.3.32 int OsiSolverLink::objectiveVariable ( ) const [inline]
Objective transfer variable if one.
Definition at line 187 of file CbcLinked.hpp.
7.130.3.33 void OsiSolverLink::setBiLinearPriority (int value) [inline]
Set biLinear priority.
Definition at line 191 of file CbcLinked.hpp.
```

```
7.130.3.34 int OsiSolverLink::biLinearPriority ( ) const [inline]
Get biLinear priority.
Definition at line 195 of file CbcLinked.hpp.
7.130.3.35 const CoinModel* OsiSolverLink::coinModel() const [inline]
Return CoinModel.
Definition at line 199 of file CbcLinked.hpp.
7.130.3.36 void OsiSolverLink::setBiLinearPriorities (int value, double meshSize = 1.0)
Set all biLinear priorities on x-x variables.
7.130.3.37 void OsiSolverLink::setBranchingStrategyOnVariables ( int strategyValue, int priorityValue = -1, int mode = 7)
Set options and priority on all or some biLinear variables 1 - on I-I 2 - on I-x 4 - on x-x or combinations.
-1 means leave (for priority value and strategy value)
7.130.3.38 void OsiSolverLink::setMeshSizes ( double value )
Set all mesh sizes on x-x variables.
7.130.3.39 void OsiSolverLink::setFixedPriority ( int priorityValue )
Two tier integer problem where when set of variables with priority less than this are fixed the problem becomes an easier
integer problem.
7.130.3.40 void OsiSolverLink::gutsOfDestructor(bool justNullify = false) [protected]
Do real work of initialize.
Do real work of delete
7.130.3.41 void OsiSolverLink::gutsOfCopy (const OsiSolverLink & rhs) [protected]
Do real work of copy.
7.130.4 Member Data Documentation
7.130.4.1 CoinPackedMatrix* OsiSolverLink::matrix_ [protected]
Clean copy of matrix Marked coefficients will be multiplied by L or U.
Definition at line 241 of file CbcLinked.hpp.
7.130.4.2 CoinPackedMatrix* OsiSolverLink::originalRowCopy [protected]
Row copy of matrix Just genuine columns and rows.
Definition at line 245 of file CbcLinked.hpp.
7.130.4.3 ClpSimplex* OsiSolverLink::quadraticModel_ [protected]
Copy of quadratic model if one.
```

Definition at line 247 of file CbcLinked.hpp.

7.130.4.4 int OsiSolverLink::numberNonLinearRows_ [protected] Number of rows with nonLinearities. Definition at line 249 of file CbcLinked.hpp. 7.130.4.5 int* OsiSolverLink::startNonLinear_ [protected] Starts of lists. Definition at line 251 of file CbcLinked.hpp. 7.130.4.6 int* OsiSolverLink::rowNonLinear_ [protected] Row number for a list. Definition at line 253 of file CbcLinked.hpp. 7.130.4.7 int* OsiSolverLink::convex_ [protected] Indicator whether is convex, concave or neither -1 concave, 0 neither, +1 convex. Definition at line 257 of file CbcLinked.hpp. 7.130.4.8 int* OsiSolverLink::whichNonLinear_ [protected] Indices in a list/row. Definition at line 259 of file CbcLinked.hpp. **7.130.4.9 CoinModel OsiSolverLink::coinModel** [protected] Model in CoinModel format. Definition at line 261 of file CbcLinked.hpp. 7.130.4.10 int OsiSolverLink::numberVariables_ [protected] Number of variables in tightening phase. Definition at line 263 of file CbcLinked.hpp. 7.130.4.11 OsiLinkedBound* OsiSolverLink::info_ [protected] Information. Definition at line 265 of file CbcLinked.hpp. **7.130.4.12** int OsiSolverLink::specialOptions2_ [protected] 0 bit (1) - call fathom (may do mini B&B) 1 bit (2) - quadratic only in objective (add OA cuts) 2 bit (4) - convex 3 bit (8) try adding OA cuts 4 bit (16) - add linearized constraints Definition at line 273 of file CbcLinked.hpp. 7.130.4.13 int OsiSolverLink::objectiveRow_ [protected]

Definition at line 275 of file CbcLinked.hpp.

Objective transfer row if one.

7.130.4.14 int OsiSolverLink::objectiveVariable_ [protected]

Objective transfer variable if one.

Definition at line 277 of file CbcLinked.hpp.

7.130.4.15 double OsiSolverLink::bestObjectiveValue_ [protected]

Objective value of best solution found internally.

Definition at line 279 of file CbcLinked.hpp.

7.130.4.16 double OsiSolverLink::defaultMeshSize_ [protected]

Default mesh.

Definition at line 281 of file CbcLinked.hpp.

7.130.4.17 double OsiSolverLink::defaultBound_ [protected]

Default maximum bound.

Definition at line 283 of file CbcLinked.hpp.

7.130.4.18 double* OsiSolverLink::bestSolution [protected]

Best solution found internally.

Definition at line 285 of file CbcLinked.hpp.

7.130.4.19 int OsiSolverLink::integerPriority_ [protected]

Priority for integers.

Definition at line 287 of file CbcLinked.hpp.

7.130.4.20 int OsiSolverLink::biLinearPriority_ [protected]

Priority for bilinear.

Definition at line 289 of file CbcLinked.hpp.

7.130.4.21 int OsiSolverLink::numberFix_ [protected]

Number of variables which when fixed help.

Definition at line 291 of file CbcLinked.hpp.

7.130.4.22 int* OsiSolverLink::fixVariables_ [protected]

list of fixed variables

Definition at line 293 of file CbcLinked.hpp.

The documentation for this class was generated from the following file:


/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.131 OsiUsesBiLinear Class Reference

Define a single variable class which is involved with OsiBiLinear objects.

#include <CbcLinked.hpp>

Inheritance diagram for OsiUsesBiLinear:



Public Member Functions

• OsiUsesBiLinear ()

Default Constructor.

• OsiUsesBiLinear (const OsiSolverInterface *solver, int iColumn, int type)

Useful constructor - passed solver index.

OsiUsesBiLinear (int iColumn, double lower, double upper, int type)

Useful constructor - passed solver index and original bounds.

• OsiUsesBiLinear (const OsiSimpleInteger &rhs, int type)

Useful constructor - passed simple integer.

OsiUsesBiLinear (const OsiUsesBiLinear &rhs)

Copy constructor.

• virtual OsiObject * clone () const

Clone.

OsiUsesBiLinear & operator= (const OsiUsesBiLinear &rhs)

Assignment operator.

virtual ∼OsiUsesBiLinear ()

Destructor.

• virtual double infeasibility (const OsiBranchingInformation *info, int &whichWay) const

Infeasibility - large is 0.5.

 virtual OsiBranchingObject * createBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way) const

Creates a branching object.

 $\bullet \ \ virtual \ double \ \textbf{feasible} \textbf{Region} \ (OsiSolverInterface \ *solver, \ const \ OsiBranchingInformation \ *info) \ const$

Set bounds to fix the variable at the current value.

• void addBiLinearObjects (OsiSolverLink *solver)

Add all bi-linear objects.

Protected Attributes

• int numberBiLinear_

data Number of bilinear objects (maybe could be more general)

int type_

Type of variable - 0 continuous, 1 integer.

OsiObject ** objects_

Objects.

7.131.1 Detailed Description

Define a single variable class which is involved with OsiBiLinear objects.

This is used so can make better decision on where to branch as it can look at all objects.

This version sees if it can re-use code from OsiSimpleInteger even if not an integer variable. If not then need to duplicate code.

Definition at line 1139 of file CbcLinked.hpp.

```
7.131.2 Constructor & Destructor Documentation
```

```
7.131.2.1 OsiUsesBiLinear::OsiUsesBiLinear ( )
```

Default Constructor.

```
7.131.2.2 OsiUsesBiLinear::OsiUsesBiLinear ( const OsiSolverInterface * solver, int iColumn, int type )
```

Useful constructor - passed solver index.

```
7.131.2.3 OsiUsesBiLinear::OsiUsesBiLinear ( int iColumn, double lower, double upper, int type )
```

Useful constructor - passed solver index and original bounds.

```
7.131.2.4 OsiUsesBiLinear::OsiUsesBiLinear ( const OsiSimpleInteger & rhs, int type )
```

Useful constructor - passed simple integer.

7.131.2.5 OsiUsesBiLinear::OsiUsesBiLinear (const OsiUsesBiLinear & rhs)

Copy constructor.

```
7.131.2.6 virtual OsiUsesBiLinear::~OsiUsesBiLinear() [virtual]
```

Destructor.

7.131.3 Member Function Documentation

```
7.131.3.1 virtual OsiObject* OsiUsesBiLinear::clone( ) const [virtual]
```

Clone.

7.131.3.2 OsiUsesBiLinear & OsiUsesBiLinear::operator= (const OsiUsesBiLinear & rhs)

Assignment operator.

7.131.3.3 virtual double OsiUsesBiLinear::infeasibility (const OsiBranchingInformation * info, int & whichWay) const [virtual]

Infeasibility - large is 0.5.

7.131.3.4 virtual OsiBranchingObject* OsiUsesBiLinear::createBranch (OsiSolverInterface * solver, const OsiBranchingInformation * info, int way) const [virtual]

Creates a branching object.

The preferred direction is set by way, 0 for down, 1 for up.

7.131.3.5 virtual double OsiUsesBiLinear::feasibleRegion (OsiSolverInterface * solver, const OsiBranchingInformation * info) const [virtual]

Set bounds to fix the variable at the current value.

Given an current value, set the lower and upper bounds to fix the variable. Returns amount it had to move variable.

7.131.3.6 void OsiUsesBiLinear::addBiLinearObjects (OsiSolverLink * solver)

Add all bi-linear objects.

7.131.4 Member Data Documentation

7.131.4.1 int OsiUsesBiLinear::numberBiLinear_ [protected]

data Number of bilinear objects (maybe could be more general)

Definition at line 1190 of file CbcLinked.hpp.

7.131.4.2 int OsiUsesBiLinear::type_ [protected]

Type of variable - 0 continuous, 1 integer.

Definition at line 1192 of file CbcLinked.hpp.

7.131.4.3 OsiObject** **OsiUsesBiLinear::objects** [protected]

Objects.

Definition at line 1194 of file CbcLinked.hpp.

The documentation for this class was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp

7.132 PseudoReducedCost Struct Reference

#include <CbcHeuristicDive.hpp>

Public Attributes

- int var
- · double pseudoRedCost

7.132.1 Detailed Description

Definition at line 12 of file CbcHeuristicDive.hpp.

7.132.2 Member Data Documentation

7.132.2.1 int PseudoReducedCost::var

Definition at line 13 of file CbcHeuristicDive.hpp.

7.132.2.2 double PseudoReducedCost::pseudoRedCost

Definition at line 14 of file CbcHeuristicDive.hpp.

The documentation for this struct was generated from the following file:

/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDive.hpp

8 File Documentation

8.1 /home/ted/COIN/trunk/Cbc/src/Cbc_ampl.h File Reference

Classes

· struct ampl_info

Functions

- int readAmpl (ampl_info *info, int argc, char **argv, void **coinModel)
- void freeArrays1 (ampl info *info)
- void freeArrays2 (ampl info *info)
- void freeArgs (ampl_info *info)
- void writeAmpl (ampl info *info)
- int ampl_obj_prec ()

8.1.1 Function Documentation

```
8.1.1.1 int readAmpl ( ampl_info * info, int argc, char ** argv, void ** coinModel )
```

- 8.1.1.2 void freeArrays1 (ampl_info * info)
- 8.1.1.3 void freeArrays2 (ampl_info * info)
- 8.1.1.4 void freeArgs (ampl_info * info)
- 8.1.1.5 void writeAmpl (ampl_info * info)
- 8.1.1.6 int ampl_obj_prec ()

8.2 /home/ted/COIN/trunk/Cbc/src/Cbc_C_Interface.h File Reference

```
#include "Coin_C_defines.h"
```

Functions

Load model - loads some stuff and initializes others

COINLIBAPI void COINLINKAGE Cbc_loadProblem (Cbc_Model *model, const int numcols, const int numcols, const int numcols, const double *collb, const double *collb, const double *collb, const double *collb, const double *rowlb, const double *rowlb)

- COINLIBAPI void COINLINKAGE Cbc_addRows (Cbc_Model *model, const int number, const double *row-Lower, const double *rowUpper, const int *rowStarts, const int *columns, const double *elements)
- COINLIBAPI void COINLINKAGE Cbc_addColumns (Cbc_Model *model, int number, const double *column-Lower, const double *columnUpper, const double *objective, const int *columnStarts, const int *rows, const double *elements)

Add columns.

COINLIBAPI void COINLINKAGE Cbc_copyNames (Cbc_Model *model, const char *const *rowNamesIn, const char *const *columnNamesIn)

Copies in names.

Message handling. Call backs are handled by ONE function

COINLIBAPI void COINLINKAGE Cbc_registerCallBack (Cbc_Model *model, cbc_callback userCallBack)
 Pass in Callback function.

gets and sets - some synonyms

• COINLIBAPI void COINLINKAGE Cbc_addSOS_Dense (Cbc_Model *model, int numObjects, const int *len, const int *const *which, const double *weights, const int type)

Add SOS constraints to the model using dense matrix.

COINLIBAPI void COINLINKAGE Cbc_addSOS_Sparse (Cbc_Model *model, const int *rowStarts, const int *rowIndices, const double *weights, const int type)

Add SOS constraints to the model using row-order matrix.

Constructors and destructor

This is a first "C" interface to Cbc.

It is mostly similar to the "C" interface to Clp and was contributed by Bob Entriken. These do not have an exact analogue in C++. The user does not need to know structure of Cbc_Model.

For all functions outside this group there is an exact C++ analogue created by taking the first parameter out, removing the Cbc_ from name and applying the method to an object of type ClpSimplex.

COINLIBAPI Cbc_Model * COINLINKAGE

Default Cbc Model constructor.

COINLIBAPI double COINLINKAGE Cbc_getVersion ()

Version.

- 8.2.1 Function Documentation
- 8.2.1.1 COINLIBAPI double COINLINKAGE Cbc_getVersion ()

Version.

- 8.2.1.2 COINLIBAPI void COINLINKAGE Cbc_loadProblem (Cbc_Model * model, const int numcols, const int numrows, const CoinBigIndex * start, const int * index, const double * value, const double * collb, const double * colub, const double * obj, const double * rowlb, const double * rowub)
- 8.2.1.3 COINLIBAPI void COINLINKAGE Cbc_addRows (Cbc_Model * model, const int number, const double * rowLower, const double * rowUpper, const int * rowStarts, const int * columns, const double * elements)

Add rows.

8.2.1.4 COINLIBAPI void COINLINKAGE Cbc_addColumns (Cbc_Model * model, int number, const double * columnLower, const double * columnUpper, const double * objective, const int * columnStarts, const int * rows, const double * elements)

Add columns.

8.2.1.5 COINLIBAPI void COINLINKAGE Cbc_copyNames (Cbc_Model * model, const char *const * rowNamesIn, const char *const * columnNamesIn)

Copies in names.

8.2.1.6 COINLIBAPI void COINLINKAGE Cbc_registerCallBack (Cbc_Model * model, cbc_callback userCallBack)

Pass in Callback function.

Message numbers up to 1000000 are Clp, Coin ones have 1000000 added

8.2.1.7 COINLIBAPI void COINLINKAGE Cbc_addSOS_Dense (Cbc_Model * model, int numObjects, const int * len, const int * ronst * which, const double * weights, const int type)

Add SOS constraints to the model using dense matrix.

8.2.1.8 COINLIBAPI void COINLINKAGE Cbc_addSOS_Sparse (Cbc_Model * model, const int * rowStarts, const int * rowIndices, const double * weights, const int type)

Add SOS constraints to the model using row-order matrix.

8.2.2 Variable Documentation

8.2.2.1 COINLIBAPI int COINLINKAGE

Default Cbc Model constructor.

Primal algorithm - see ClpSimplexPrimal.hpp for method.

Dual algorithm - see ClpSimplexDual.hpp for method.

Primal initial solve.

Dual initial solve.

Print the solution.

Delete all object information.

Set this the variable to be continuous.

Return a copy of this model.

Number of nodes explored in B&B tree.

Return CPU time.

Determine whether the variable at location i is integer restricted.

Print the model.

Iteration limit reached?

Is the given dual objective limit reached?

Is the given primal objective limit reached?

Is dual infeasiblity proven?

Is primal infeasiblity proven?

Is optimality proven?

Are there a numerical difficulties?

Just check solution (for external use) - sets sum of infeasibilities etc.

Restore model from file, returns 0 if success, deletes current model.

Save model to file, returns 0 if success.

Number of primal infeasibilities.

Sum of primal infeasibilities.

Number of dual infeasibilities.

Sum of dual infeasibilities.

Set algorithm.

Current (or last) algorithm.

Perturbation: 50 - switch on perturbation 100 - auto perturb if takes too long (1.0e-6 largest nonzero) 101 - we are perturbed 102 - don't try perturbing again default is 100 others are for playing.

Infeasibility cost.

Dual bound.

If problem is dual feasible.

If problem is primal feasible.

Crash - at present just aimed at dual, returns -2 if dual preferred and crash basis created -1 if dual preferred and all slack basis preferred 0 if basis going in was not all slack 1 if primal preferred and all slack basis preferred 2 if primal preferred and crash basis created.

Gets scalingFlag.

Sets or unsets scaling, 0 -off, 1 equilibrium, 2 geometric, 3, auto, 4 dynamic(later)

General solve algorithm which can do presolve.

Fill in array (at least lengthNames+1 long) with a column name.

Fill in array (at least lengthNames+1 long) with a row name.

length of names (0 means no names0

Amount of print out: 0 - none 1 - just final 2 - just factorizations 3 - as 2 plus a bit more 4 - verbose above that 8,16,32 etc just for selective debug.

Unset Callback function.

User pointer for whatever reason.

Copy in status vector.

Return address of status array (char[numberRows+numberColumns])

See if status array exists (partly for OsiClp)

Infeasibility/unbounded ray (NULL returned if none/wrong) Up to user to use delete [] on these arrays.

Objective value.

Element values in matrix.

Column vector lengths in matrix.

Row indices in matrix.
Column starts in matrix.
Number of elements in matrix.
Column Upper.
Column Lower.
Objective.
Row upper.
Row lower.
Reduced costs.
Dual row solution.
Primal column solution.
Primal row solution.
Direction of optimization (1 - minimize, -1 - maximize, 0 - ignore.
Secondary status of problem - may get extended 0 - none 1 - primal infeasible because dual limit reached 2 - scaled problem optimal - unscaled has primal infeasibilities 3 - scaled problem optimal - unscaled has dual infeasibilities 4 - scaled problem optimal - unscaled has both dual and primal infeasibilities.
Set problem status.
Status of problem: 0 - optimal 1 - primal infeasible 2 - dual infeasible 3 - stopped on iterations etc 4 - stopped due to errors.
Returns true if hit maximum iterations (or time)
Maximum time in seconds (from when set called)
Maximum number of nodes.
Maximum number of iterations.
Number of iterations.
Sets problem name.
Fills in array with problem name.
Objective offset.
Dual objective limit.
Dual tolerance to use.
Primal tolerance to use.
Number of columns.
Number of rows.
Drops names - makes lengthnames 0 and names empty.
Deletes columns.
Deletes rows.
Resizes rim part of model.
Drop integer informations.
Copy in integer information.

Integer information.

Write an mps file from the given filename.

Read an mps file from the given filename.

Cbc Model Destructor.

array must be a null-terminated string.

See ClpSolve.hpp for options

if gap between bounds <= "gap" variables can be flipped

If "pivot" is 0 No pivoting (so will just be choice of algorithm) 1 Simple pivoting e.g. gub 2 Mini iterations

This is designed for use outside algorithms so does not save iterating arrays etc. It does not save any messaging information. Does not save scaling values. It does not know about all types of virtual functions.

Definition at line 39 of file Cbc_C_Interface.h.

8.3 /home/ted/COIN/trunk/Cbc/src/CbcBranchActual.hpp File Reference

```
#include "CbcBranchBase.hpp"
#include "CoinPackedMatrix.hpp"
#include "CbcClique.hpp"
#include "CbcSOS.hpp"
#include "CbcSimpleInteger.hpp"
#include "CbcNWay.hpp"
#include "CbcSimpleIntegerPseudoCost.hpp"
#include "CbcBranchDefaultDecision.hpp"
#include "CbcFollowOn.hpp"
#include "CbcFixVariable.hpp"
#include "CbcDummyBranchingObject.hpp"
#include "CbcGeneral.hpp"
#include "CbcGeneralDepth.hpp"
#include "CbcSubProblem.hpp"
```

8.4 /home/ted/COIN/trunk/Cbc/src/CbcBranchAllDifferent.hpp File Reference

```
#include "CbcBranchBase.hpp"
#include "OsiRowCut.hpp"
#include "CoinPackedMatrix.hpp"
#include "CbcBranchCut.hpp"
```

Classes

· class CbcBranchAllDifferent

Define a branch class that branches so that it is only satsified if all members have different values So cut is $x \le y-1$ or $x \ge y+1$.

8.5 /home/ted/COIN/trunk/Cbc/src/CbcBranchBase.hpp File Reference

```
#include <string>
#include <vector>
#include "OsiBranchingObject.hpp"
#include "CbcObject.hpp"
#include "CbcBranchingObject.hpp"
#include "CbcBranchDecision.hpp"
#include "CbcConsequence.hpp"
#include "CbcObjectUpdateData.hpp"
```

Enumerations

enum CbcRangeCompare {
 CbcRangeSame, CbcRangeDisjoint, CbcRangeSubset, CbcRangeSuperset,
 CbcRangeOverlap }

Functions

 static CbcRangeCompare CbcCompareRanges (double *thisBd, const double *otherBd, const bool replaceIf-Overlap)

Compare two ranges.

- 8.5.1 Enumeration Type Documentation
- 8.5.1.1 enum CbcRangeCompare

Enumerator

CbcRangeSame

CbcRangeDisjoint

CbcRangeSubset

CbcRangeSuperset

CbcRangeOverlap

Definition at line 13 of file CbcBranchBase.hpp.

8.5.2 Function Documentation

8.5.2.1 static CbcRangeCompare CbcCompareRanges (double * thisBd, const double * otherBd, const bool replacelfOverlap) [inline], [static]

Compare two ranges.

The two bounds arrays are both of size two and describe closed intervals. Return the appropriate CbcRangeCompare value (first argument being the sub/superset if that's the case). In case of overlap (and if replaceIfOverlap is true) replace the content of thisBd with the intersection of the ranges.

Definition at line 36 of file CbcBranchBase.hpp.

8.6 /home/ted/COIN/trunk/Cbc/src/CbcBranchCut.hpp File Reference

```
#include "CbcBranchBase.hpp"
#include "OsiRowCut.hpp"
#include "CoinPackedMatrix.hpp"
```

Classes

class CbcBranchCut

Define a cut branching class.

• class CbcCutBranchingObject

Cut branching object.

8.7 /home/ted/COIN/trunk/Cbc/src/CbcBranchDecision.hpp File Reference

```
#include "CbcBranchBase.hpp"
```

Classes

class CbcBranchDecision

8.8 /home/ted/COIN/trunk/Cbc/src/CbcBranchDefaultDecision.hpp File Reference

```
#include "CbcBranchBase.hpp"
```

Classes

• class CbcBranchDefaultDecision

Branching decision default class.

8.9 /home/ted/COIN/trunk/Cbc/src/CbcBranchDynamic.hpp File Reference

```
#include "CoinPackedMatrix.hpp"
#include "CbcSimpleIntegerDynamicPseudoCost.hpp"
#include "CbcBranchActual.hpp"
```

Classes

· class CbcBranchDynamicDecision

Branching decision dynamic class.

class CbcDynamicPseudoCostBranchingObject

Simple branching object for an integer variable with pseudo costs.

8.10 /home/ted/COIN/trunk/Cbc/src/CbcBranchingObject.hpp File Reference

```
#include <string>
#include <vector>
#include "CbcBranchBase.hpp"
#include "OsiBranchingObject.hpp"
```

Classes

class CbcBranchingObject

Abstract branching object base class Now just difference with OsiBranchingObject.

Enumerations

```
    enum CbcBranchObjType {
    SimpleIntegerBranchObj = 100, SimpleIntegerDynamicPseudoCostBranchObj = 101, CliqueBranchObj = 102, LongCliqueBranchObj = 103,
    SoSBranchObj = 104, NWayBranchObj = 105, FollowOnBranchObj = 106, DummyBranchObj = 107,
    GeneralDepthBranchObj = 108, OneGeneralBranchingObj = 110, CutBranchingObj = 200, LotsizeBranchObj = 300,
    DynamicPseudoCostBranchObj = 400 }
```

8.10.1 Enumeration Type Documentation

8.10.1.1 enum CbcBranchObjType

Enumerator

SimpleIntegerBranchObj

SimpleIntegerDynamicPseudoCostBranchObj

CliqueBranchObj

LongCliqueBranchObj

SoSBranchObj

NWayBranchObj

FollowOnBranchObj

DummyBranchObj

GeneralDepthBranchObj

OneGeneralBranchingObj

CutBranchingObj

LotsizeBranchObj

DynamicPseudoCostBranchObj

Definition at line 18 of file CbcBranchingObject.hpp.

8.11 /home/ted/COIN/trunk/Cbc/src/CbcBranchLotsize.hpp File Reference

```
#include "CbcBranchBase.hpp"
```

Classes

· class CbcLotsize

Lotsize class.

class CbcLotsizeBranchingObject

Lotsize branching object.

8.12 /home/ted/COIN/trunk/Cbc/src/CbcBranchToFixLots.hpp File Reference

```
#include "CbcBranchCut.hpp"
#include "CbcBranchBase.hpp"
#include "OsiRowCut.hpp"
#include "CoinPackedMatrix.hpp"
```

Classes

class CbcBranchToFixLots

Define a branch class that branches so that one way variables are fixed while the other way cuts off that solution.

8.13 /home/ted/COIN/trunk/Cbc/src/CbcClique.hpp File Reference

Classes

· class CbcClique

Branching object for cliques.

• class CbcCliqueBranchingObject

Branching object for unordered cliques.

class CbcLongCliqueBranchingObject

Unordered Clique Branching Object class.

8.14 /home/ted/COIN/trunk/Cbc/src/CbcCompare.hpp File Reference

Classes

· class CbcCompare

8.15 /home/ted/COIN/trunk/Cbc/src/CbcCompareActual.hpp File Reference

```
#include "CbcNode.hpp"
#include "CbcCompareBase.hpp"
#include "CbcCompare.hpp"
#include "CbcCompareDepth.hpp"
#include "CbcCompareDefault.hpp"
```

8.16 /home/ted/COIN/trunk/Cbc/src/CbcCompareBase.hpp File Reference

```
#include "CbcNode.hpp"
#include "CbcConfig.h"
```

Classes

class CbcCompareBase

8.17 /home/ted/COIN/trunk/Cbc/src/CbcCompareDefault.hpp File Reference

```
#include "CbcNode.hpp"
#include "CbcCompareBase.hpp"
#include "CbcCompare.hpp"
```

Classes

· class CbcCompareDefault

8.18 /home/ted/COIN/trunk/Cbc/src/CbcCompareDepth.hpp File Reference

```
#include "CbcNode.hpp"
#include "CbcCompareBase.hpp"
#include "CbcCompare.hpp"
```

Classes

• class CbcCompareDepth

8.19 /home/ted/COIN/trunk/Cbc/src/CbcCompareEstimate.hpp File Reference

```
#include "CbcNode.hpp"
#include "CbcCompareBase.hpp"
#include "CbcCompare.hpp"
```

Classes

class CbcCompareEstimate

8.20 /home/ted/COIN/trunk/Cbc/src/CbcCompareObjective.hpp File Reference

```
#include "CbcNode.hpp"
#include "CbcCompareBase.hpp"
#include "CbcCompare.hpp"
```

Classes

class CbcCompareObjective

8.21 /home/ted/COIN/trunk/Cbc/src/CbcConfig.h File Reference

```
#include "config_cbc_default.h"
```

8.22 /home/ted/COIN/trunk/Cbc/src/CbcConsequence.hpp File Reference

Classes

class CbcConsequence

Abstract base class for consequent bounds.

8.23 /home/ted/COIN/trunk/Cbc/src/CbcCountRowCut.hpp File Reference

Classes

· class CbcCountRowCut

OsiRowCut augmented with bookkeeping.

struct CoinHashLink

Really for Conflict cuts to - a) stop duplicates b) allow half baked cuts The whichRow_ field in OsiRowCut2 is used for a type 0 - normal 1 - processed cut 2 - unprocessed cut i.e.

class CbcRowCuts

8.24 /home/ted/COIN/trunk/Cbc/src/CbcCutGenerator.hpp File Reference

```
#include "OsiSolverInterface.hpp"
#include "OsiCuts.hpp"
#include "CglCutGenerator.hpp"
#include "CbcCutModifier.hpp"
```

Classes

class CbcCutGenerator

Interface between Cbc and Cut Generation Library.

Macros

- #define SCANCUTS 1000
- #define SCANCUTS_PROBING 1000

8.24.1 Macro Definition Documentation

8.24.1.1 #define SCANCUTS 1000

Definition at line 464 of file CbcCutGenerator.hpp.

8.24.1.2 #define SCANCUTS_PROBING 1000

Definition at line 466 of file CbcCutGenerator.hpp.

8.25 /home/ted/COIN/trunk/Cbc/src/CbcCutModifier.hpp File Reference

```
#include "OsiSolverInterface.hpp"
#include "OsiCuts.hpp"
#include "CglCutGenerator.hpp"
```

Classes

class CbcCutModifier

Abstract cut modifier base class.

8.26 /home/ted/COIN/trunk/Cbc/src/CbcCutSubsetModifier.hpp File Reference

```
#include "OsiSolverInterface.hpp"
#include "OsiCuts.hpp"
#include "CglCutGenerator.hpp"
#include "CbcCutModifier.hpp"
```

Classes

· class CbcCutSubsetModifier

Simple cut modifier base class.

8.27 /home/ted/COIN/trunk/Cbc/src/CbcDummyBranchingObject.hpp File Reference

```
#include "CbcBranchBase.hpp"
```

Classes

· class CbcDummyBranchingObject

Dummy branching object.

8.28 /home/ted/COIN/trunk/Cbc/src/CbcEventHandler.hpp File Reference

Event handling for cbc.

```
#include <map>
```

Classes

· class CbcEventHandler

Base class for Cbc event handling.

8.28.1 Detailed Description

Event handling for cbc. This file contains the declaration of CbcEventHandler, used for event handling in cbc.

The central method is CbcEventHandler::event(). The default semantics of this call are 'ask for the action to take in reponse to this event'. The call is made at the point in the code where the event occurs (*e.g.*, when a solution is found, or when a node is added to or removed from the search tree). The return value specifies the action to perform in response to the event (*e.g.*, continue, or stop).

This is a lazy class. Initially, it knows nothing about specific events, and returns dfltAction_ for any event. This makes for a trivial constructor and fast startup. The only place where the list of known events or actions is hardwired is in the enum definitions for CbcEvent and CbcAction, respectively.

At the first call to setAction, a map is created to hold (Event,Action) pairs, and this map will be consulted ever after. Events not in the map will still return the default value.

For serious extensions, derive a subclass and replace event() with a function that suits you better. The function has access to the CbcModel via a pointer held in the CbcEventHandler object, and can do as much thinking as it likes before returning an answer. You can also print as much information as you want. The model is held as a const, however, so you can't alter reality.

The design of the class deliberately matches ClpEventHandler, so that other solvers can participate in cbc without breaking the patterns set by clp-specific code.

Definition in file CbcEventHandler.hpp.

8.29 /home/ted/COIN/trunk/Cbc/src/CbcFathom.hpp File Reference

```
#include "CbcConfig.h"
#include "OsiClpSolverInterface.hpp"
```

Classes

· class CbcFathom

Fathom base class.

· class CbcOsiSolver

This is for codes where solver needs to know about CbcModel Seems to provide only one value-added feature, a CbcModel object.

8.30 /home/ted/COIN/trunk/Cbc/src/CbcFathomDynamicProgramming.hpp File Reference

```
#include "CbcFathom.hpp"
```

Classes

class CbcFathomDynamicProgramming

FathomDynamicProgramming class.

8.31 /home/ted/COIN/trunk/Cbc/src/CbcFeasibilityBase.hpp File Reference

Classes

· class CbcFeasibilityBase

8.32 /home/ted/COIN/trunk/Cbc/src/CbcFixVariable.hpp File Reference

```
#include "CbcBranchBase.hpp"
```

Classes

• class CbcFixVariable

Class for consequent bounds.

8.33 /home/ted/COIN/trunk/Cbc/src/CbcFollowOn.hpp File Reference

```
#include "CbcBranchBase.hpp"
#include "OsiRowCut.hpp"
#include "CoinHelperFunctions.hpp"
#include "CoinPackedMatrix.hpp"
```

Classes

· class CbcFollowOn

Define a follow on class.

class CbcFixingBranchingObject

General Branching Object class.

· class CbcldiotBranch

Define an idiotic idea class.

8.34 /home/ted/COIN/trunk/Cbc/src/CbcFullNodeInfo.hpp File Reference

```
#include <string>
#include <vector>
#include "CoinWarmStartBasis.hpp"
#include "CoinSearchTree.hpp"
#include "CbcBranchBase.hpp"
#include "CbcNodeInfo.hpp"
```

Classes

class CbcFullNodeInfo

Information required to recreate the subproblem at this node.

8.35 /home/ted/COIN/trunk/Cbc/src/CbcGenCbcParam.hpp File Reference

Classes

• class CbcCbcParam

Class for control parameters that act on a CbcModel object.

Namespaces

CbcCbcParamUtils

Functions

- void CbcCbcParamUtils::addCbcCbcParams (int &numParams, CoinParamVec ¶mVec, CbcModel *model)
- void CbcCbcParamUtils::loadCbcParamObj (const CoinParamVec paramVec, int first, int last, CbcModel *model)
- void CbcCbcParamUtils::setCbcModelDefaults (CbcModel *model)
- int CbcCbcParamUtils::pushCbcCbcDbl (CoinParam *param)
- int CbcCbcParamUtils::pushCbcCbcInt (CoinParam *param)

8.36 /home/ted/COIN/trunk/Cbc/src/CbcGenCtlBlk.hpp File Reference

```
#include "CoinParam.hpp"
```

```
#include "CoinMessageHandler.hpp"
#include "CglCutGenerator.hpp"
#include "CglProbing.hpp"
#include "CglClique.hpp"
#include "CglFlowCover.hpp"
#include "CglGomory.hpp"
#include "CqlKnapsackCover.hpp"
#include "CglMixedIntegerRounding2.hpp"
#include "CglOddHole.hpp"
#include "CglRedSplit.hpp"
#include "CglTwomir.hpp"
#include "CbcModel.hpp"
#include "CbcHeuristic.hpp"
#include "CbcHeuristicFPump.hpp"
#include "CbcHeuristicGreedy.hpp"
#include "CbcHeuristicLocal.hpp"
#include "CbcTreeLocal.hpp"
#include "CbcGenMessages.hpp"
```

Classes

- · class CbcGenCtlBlk
- struct CbcGenCtlBlk::genParamsInfo_struct

Start and end of cbc-generic parameters in parameter vector.

struct CbcGenCtlBlk::cbcParamsInfo struct

Start and end of CbcModel parameters in parameter vector.

struct CbcGenCtlBlk::osiParamsInfo struct

Start and end of OsiSolverInterface parameters in parameter vector.

struct CbcGenCtlBlk::debugSolInfo_struct

Array of primal variable values for debugging.

struct CbcGenCtlBlk::babState_struct

State of branch-and-cut.

struct CbcGenCtlBlk::djFixCtl_struct

Control use of reduced cost fixing prior to B&C.

· struct CbcGenCtlBlk::chooseStrongCtl_struct

Control variables for a strong branching method.

Namespaces

CbcGenParamUtils

Macros

#define CBC_GENERIC_VERSION "00.01.00"

Functions

void CbcGenParamUtils::addCbcGenParams (int &numParams, CoinParamVec ¶mVec, CbcGenCtlBlk *ctl-Blk)

8.36.1 Macro Definition Documentation

8.36.1.1 #define CBC_GENERIC_VERSION "00.01.00"

Definition at line 53 of file CbcGenCtlBlk.hpp.

8.37 /home/ted/COIN/trunk/Cbc/src/CbcGeneral.hpp File Reference

```
#include "CbcBranchBase.hpp"
```

Classes

· class CbcGeneral

Define a catch all class.

8.38 /home/ted/COIN/trunk/Cbc/src/CbcGeneralDepth.hpp File Reference

```
#include "CbcGeneral.hpp"
#include "CbcBranchBase.hpp"
#include "CbcSubProblem.hpp"
```

8.39 /home/ted/COIN/trunk/Cbc/src/CbcGenMessages.hpp File Reference

This file contains the enum that defines symbolic names for for cbc-generic messages.

Enumerations

enum CbcGenMsgCode { CBCGEN_TEST_MSG = 1, CBCGEN_NEW_SOLVER, CBCGEN_CONFUSION, CB-CGEN_DUMMY_END }

Symbolic names for cbc-generic messages.

8.39.1 Detailed Description

This file contains the enum that defines symbolic names for for cbc-generic messages.

Definition in file CbcGenMessages.hpp.

8.39.2 Enumeration Type Documentation

8.39.2.1 enum CbcGenMsgCode

Symbolic names for cbc-generic messages.

These are the 'internal IDs' for cbc-generic messages.

Enumerator

CBCGEN_TEST_MSG

CBCGEN_NEW_SOLVER
CBCGEN_CONFUSION
CBCGEN_DUMMY_END

Definition at line 36 of file CbcGenMessages.hpp.

8.40 /home/ted/COIN/trunk/Cbc/src/CbcGenOsiParam.hpp File Reference

Classes

· class CbcOsiParam

Class for control parameters that act on a OsiSolverInterface object.

Namespaces

CbcOsiParamUtils

Functions

- void CbcOsiParamUtils::addCbcOsiParams (int &numParams, CoinParamVec ¶mVec, OsiSolverInterface *osi)
- void CbcOsiParamUtils::loadOsiParamObj (const CoinParamVec paramVec, CbcGenCtlBlk *ctlBlk)
- void CbcOsiParamUtils::setOsiSolverInterfaceDefaults (OsiSolverInterface *osi)
- int CbcOsiParamUtils::pushCbcOsiLogLevel (CoinParam *param)
- int CbcOsiParamUtils::pushCbcOsiInt (CoinParam *param)
- int CbcOsiParamUtils::pushCbcOsiDbl (CoinParam *param)
- int CbcOsiParamUtils::pushCbcOsiKwd (CoinParam *param)
- int CbcOsiParamUtils::pushCbcOsiHint (CoinParam *param)

8.41 /home/ted/COIN/trunk/Cbc/src/CbcGenParam.hpp File Reference

Classes

class CbcGenParam

Class for cbc-generic control parameters.

Namespaces

CbcGenParamUtils

Functions

- void CbcGenParamUtils::addCbcGenParams (int &numParams, CoinParamVec ¶mVec, CbcGenCtlBlk *ctl-Blk)
- void CbcGenParamUtils::loadGenParamObj (const CoinParamVec paramVec, int first, int last, CbcGenCtlBlk *ctl-Blk)
- void CbcGenParamUtils::saveSolution (const OsiSolverInterface *osi, std::string fileName)

- bool CbcGenParamUtils::readSolution (std::string fileName, int &numRows, int &numCols, double &objVal, double **rowActivity, double **dualVars, double **primalVars, double **reducedCosts)
- int CbcGenParamUtils::doBaCParam (CoinParam *param)
- int CbcGenParamUtils::doDebugParam (CoinParam *param)
- int CbcGenParamUtils::doExitParam (CoinParam *param)
- int CbcGenParamUtils::doHelpParam (CoinParam *param)
- int CbcGenParamUtils::doImportParam (CoinParam *param)
- int CbcGenParamUtils::doPrintMaskParam (CoinParam *param)
- int CbcGenParamUtils::doNothingParam (CoinParam *param)
- int CbcGenParamUtils::doSolutionParam (CoinParam *param)
- int CbcGenParamUtils::doUnimplementedParam (CoinParam *param)
- int CbcGenParamUtils::doVersionParam (CoinParam *param)
- int CbcGenParamUtils::pushCbcGenDblParam (CoinParam *param)
- int CbcGenParamUtils::pushCbcGenIntParam (CoinParam *param)
- int CbcGenParamUtils::pushCbcGenKwdParam (CoinParam *param)
- int CbcGenParamUtils::pushCbcGenStrParam (CoinParam *param)
- int CbcGenParamUtils::pushCbcGenCutParam (CoinParam *param)

8.42 /home/ted/COIN/trunk/Cbc/src/CbcHeuristic.hpp File Reference

```
#include <string>
#include <vector>
#include "CoinPackedMatrix.hpp"
#include "OsiCuts.hpp"
#include "CoinHelperFunctions.hpp"
#include "OsiBranchingObject.hpp"
```

Classes

• class CbcHeuristicNode

A class describing the branching decisions that were made to get to the node where a heuristic was invoked from.

- class CbcHeuristicNodeList
- · class CbcHeuristic

Heuristic base class.

class CbcRounding

Rounding class.

· class CbcHeuristicPartial

Partial solution class If user knows a partial solution this tries to get an integer solution it uses hotstart information.

class CbcSerendipity

heuristic - just picks up any good solution found by solver - see OsiBabSolver

class CbcHeuristicJustOne

Just One class - this chooses one at random.

8.43 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicDINS.hpp File Reference

```
#include "CbcHeuristic.hpp"
```

Classes

• class CbcHeuristicDINS

8.44 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicDive.hpp File Reference

```
#include "CbcHeuristic.hpp"
```

Classes

- struct PseudoReducedCost
- · class CbcHeuristicDive

Dive class.

8.45 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveCoefficient.hpp File Reference

```
#include "CbcHeuristicDive.hpp"
```

Classes

· class CbcHeuristicDiveCoefficient

DiveCoefficient class.

8.46 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveFractional.hpp File Reference

```
#include "CbcHeuristicDive.hpp"
```

Classes

· class CbcHeuristicDiveFractional

DiveFractional class.

8.47 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveGuided.hpp File Reference

```
#include "CbcHeuristicDive.hpp"
```

Classes

· class CbcHeuristicDiveGuided

DiveGuided class.

8.48 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveLineSearch.hpp File Reference

```
#include "CbcHeuristicDive.hpp"
```

Classes

class CbcHeuristicDiveLineSearch

DiveLineSearch class.

8.49 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicDivePseudoCost.hpp File Reference

```
#include "CbcHeuristicDive.hpp"
```

Classes

class CbcHeuristicDivePseudoCost

DivePseudoCost class.

8.50 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveVectorLength.hpp File Reference

```
#include "CbcHeuristicDive.hpp"
```

Classes

· class CbcHeuristicDiveVectorLength

DiveVectorLength class.

8.51 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicDW.hpp File Reference

```
#include "CbcHeuristic.hpp"
```

Classes

· class CbcHeuristicDW

This is unlike the other heuristics in that it is very very compute intensive.

8.52 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicFPump.hpp File Reference

```
#include "CbcHeuristic.hpp"
#include "OsiClpSolverInterface.hpp"
```

Classes

class CbcHeuristicFPump

Feasibility Pump class.

8.53 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicGreedy.hpp File Reference

```
#include "CbcHeuristic.hpp"
```

Classes

· class CbcHeuristicGreedyCover

Greedy heuristic classes.

- · class CbcHeuristicGreedyEquality
- · class CbcHeuristicGreedySOS

Greedy heuristic for SOS and L rows (and positive elements)

8.54 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicLocal.hpp File Reference

```
#include "CbcHeuristic.hpp"
```

Classes

· class CbcHeuristicLocal

LocalSearch class.

- · class CbcHeuristicProximity
- · class CbcHeuristicNaive

Naive class a) Fix all ints as close to zero as possible b) Fix all ints with nonzero costs and < large to zero c) Put bounds round continuous and UIs and maximize.

· class CbcHeuristicCrossover

Crossover Search class.

8.55 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicPivotAndFix.hpp File Reference

```
#include "CbcHeuristic.hpp"
```

Classes

· class CbcHeuristicPivotAndFix

LocalSearch class.

8.56 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicRandRound.hpp File Reference

```
#include "CbcHeuristic.hpp"
```

Classes

· class CbcHeuristicRandRound

LocalSearch class.

8.57 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicRENS.hpp File Reference

```
#include "CbcHeuristic.hpp"
```

Classes

· class CbcHeuristicRENS

LocalSearch class.

8.58 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicRINS.hpp File Reference

```
#include "CbcHeuristic.hpp"
#include "CbcHeuristicRENS.hpp"
#include "CbcHeuristicDINS.hpp"
#include "CbcHeuristicVND.hpp"
```

Classes

· class CbcHeuristicRINS

LocalSearch class.

8.59 /home/ted/COIN/trunk/Cbc/src/CbcHeuristicVND.hpp File Reference

```
#include "CbcHeuristic.hpp"
```

Classes

class CbcHeuristicVND

LocalSearch class.

8.60 /home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp File Reference

```
#include "CoinModel.hpp"
#include "OsiClpSolverInterface.hpp"
#include "OsiChooseVariable.hpp"
#include "CbcFathom.hpp"
#include "CbcHeuristic.hpp"
#include "OsiBranchingObject.hpp"
#include <string>
#include "CglStored.hpp"
```

Classes

class OsiSolverLink

This is to allow the user to replace initialSolve and resolve This version changes coefficients.

· class OsiLinkedBound

List of bounds which depend on other bounds.

class CbcHeuristicDynamic3

heuristic - just picks up any good solution

- class OsiOldLink
- class OsiOldLinkBranchingObject

Branching object for Linked ordered sets.

class OsiOneLink

Define data for one link.

class OsiLink

Define Special Linked Ordered Sets.

· class OsiLinkBranchingObject

Branching object for Linked ordered sets.

class OsiBiLinear

Define BiLinear objects.

· class OsiBiLinearBranchingObject

Branching object for BiLinear objects.

· class OsiBiLinearEquality

Define Continuous BiLinear objects for an == bound.

class OsiSimpleFixedInteger

Define a single integer class - but one where you keep branching until fixed even if satisfied.

· class OsiUsesBiLinear

Define a single variable class which is involved with OsiBiLinear objects.

class OsiChooseStrongSubset

This class chooses a variable to branch on.

class CglTemporary

Stored Temporary Cut Generator Class - destroyed after first use.

class OsiSolverLinearizedQuadratic

This is to allow the user to replace initialSolve and resolve.

Functions

 ClpSimplex * approximateSolution (CoinModel &coinModel, int numberPasses, double deltaTolerance, int mode=0)

Return an approximate solution to a CoinModel.

8.60.1 Function Documentation

8.60.1.1 ClpSimplex* approximateSolution (CoinModel & coinModel, int numberPasses, double deltaTolerance, int mode = 0)

Return an approximate solution to a CoinModel.

Lots of bounds may be odd to force a solution. mode = 0 just tries to get a continuous solution

8.61 /home/ted/COIN/trunk/Cbc/src/CbcMessage.hpp File Reference

```
#include "CoinMessageHandler.hpp"
```

Classes

· class CbcMessage

Enumerations

```
    enum CBC_Message {
        CBC_END_GOOD, CBC_MAXNODES, CBC_MAXTIME, CBC_MAXSOLS,
        CBC_EVENT, CBC_MAXITERS, CBC_SOLUTION, CBC_END_SOLUTION,
        CBC_SOLUTION2, CBC_END, CBC_INFEAS, CBC_STRONG,
        CBC_SOLINDIVIDUAL, CBC_INTEGERINCREMENT, CBC_STATUS, CBC_GAP,
        CBC_ROUNDING, CBC_TREE_SOL, CBC_ROOT, CBC_GENERATOR,
        CBC_BRANCH, CBC_STRONGSOL, CBC_NOINT, CBC_VUB_PASS,
        CBC_VUB_END, CBC_NOTFEAS1, CBC_NOTFEAS2, CBC_NOTFEAS3,
        CBC_CUTOFF_WARNING1, CBC_ITERATE_STRONG, CBC_PRIORITY, CBC_WARNING_STRONG,
        CBC_START_SUB, CBC_END_SUB, CBC_THREAD_STATS, CBC_CUTS_STATS,
        CBC_STRONG_STATS, CBC_UNBOUNDED, CBC_OTHER_STATS, CBC_HEURISTICS_OFF,
        CBC_STATUS2, CBC_FPUMP1, CBC_FPUMP2, CBC_STATUS3,
        CBC_OTHER_STATS2, CBC_RELAXED1, CBC_RELAXED2, CBC_RESTART,
        CBC_GENERAL, CBC_ROOT_DETAIL, CBC_FATHOM_CHANGE, CBC_DUMMY_END }
```

8.61.1 Enumeration Type Documentation

8.61.1.1 enum CBC Message

This deals with Cbc messages (as against Clp messages etc).

This deals with Cbc messages (as against Clp messages etc).

CoinMessageHandler.hpp is the general part of message handling. All it has are enum's for the various messages. CbcMessage.cpp has text in various languages.

It is trivial to use the .hpp and .cpp file as a basis for messages for other components.

Enumerator

```
CBC_END_GOOD
CBC_MAXNODES
CBC_MAXTIME
CBC_MAXSOLS
CBC_EVENT
CBC_MAXITERS
CBC_SOLUTION
CBC_END_SOLUTION
CBC_SOLUTION2
CBC_END
CBC_INFEAS
```

CBC_STRONG

CBC_SOLINDIVIDUAL

CBC_INTEGERINCREMENT

CBC_STATUS

CBC GAP

CBC_ROUNDING

CBC_TREE_SOL

CBC_ROOT

CBC_GENERATOR

CBC_BRANCH

CBC_STRONGSOL

CBC_NOINT

CBC_VUB_PASS

CBC_VUB_END

CBC_NOTFEAS1

CBC_NOTFEAS2

CBC_NOTFEAS3

CBC_CUTOFF_WARNING1

CBC_ITERATE_STRONG

CBC_PRIORITY

CBC_WARNING_STRONG

CBC_START_SUB

CBC_END_SUB

CBC_THREAD_STATS

CBC_CUTS_STATS

CBC_STRONG_STATS

CBC_UNBOUNDED

CBC_OTHER_STATS

CBC_HEURISTICS_OFF

CBC_STATUS2

CBC_FPUMP1

CBC_FPUMP2

CBC_STATUS3

CBC_OTHER_STATS2

CBC_RELAXED1

CBC_RELAXED2

CBC_RESTART

CBC_GENERAL

CBC_ROOT_DETAIL

CBC_FATHOM_CHANGE

CBC_DUMMY_END

Definition at line 24 of file CbcMessage.hpp.

8.62 /home/ted/COIN/trunk/Cbc/src/CbcMipStartIO.hpp File Reference

```
#include <vector>
#include <string>
#include <utility>
```

Functions

- int readMIPStart (CbcModel *model, const char *fileName, std::vector< std::pair< std::string, double >> &col-Values, double &solObj)
- int computeCompleteSolution (CbcModel *model, const std::vector< std::string > colNames, const std::vector< std::pair< std::string, double > > &colValues, double *sol, double &obj)

8.62.1 Function Documentation

- 8.62.1.1 int readMIPStart (CbcModel * model, const char * fileName, std::vector < std::pair < std::string, double > > & colValues, double & solObj)
- 8.62.1.2 int computeCompleteSolution (CbcModel * model, const std::vector < std::string > colNames, const std::vector < std::pair < std::string, double > > & colValues, double * sol, double & obj)

8.63 /home/ted/COIN/trunk/Cbc/src/CbcModel.hpp File Reference

```
#include <string>
#include <vector>
#include "CoinMessageHandler.hpp"
#include "OsiSolverInterface.hpp"
#include "OsiBranchingObject.hpp"
#include "CoinWarmStartBasis.hpp"
#include "CbcCompareBase.hpp"
#include "CbcCountRowCut.hpp"
#include "CbcMessage.hpp"
#include "CbcEventHandler.hpp"
#include "ClpDualRowPivot.hpp"
```

Classes

class CbcModel

Simple Branch and bound class.

Functions

- void getIntegerInformation (const OsiObject *object, double &originalLower, double &originalUpper)
 So we can use osiObject or CbcObject during transition.
- int CbcMain (int argc, const char *argv[], OsiClpSolverInterface &solver, CbcModel **babSolver)
- int CbcMain (int argc, const char *argv[], CbcModel &babSolver)
- int callCbc (const char *input2, OsiClpSolverInterface &solver1)
- int callCbc (const char *input2)

- int callCbc (const std::string input2, OsiClpSolverInterface &solver1)
- int callCbc (const std::string input2)
- void CbcMain0 (CbcModel &babSolver)
- int CbcMain1 (int argc, const char *argv[], CbcModel &babSolver)
- int callCbc (const char *input2, CbcModel &babSolver)
- int callCbc (const std::string input2, CbcModel &babSolver)
- int callCbc1 (const char *input2, CbcModel &babSolver)
- int callCbc1 (const std::string input2, CbcModel &babSolver)
- int callCbc1 (const char *input2, CbcModel &babSolver, int(CbcModel *currentSolver, int whereFrom))
- int callCbc1 (const std::string input2, CbcModel &babSolver, int(CbcModel *currentSolver, int whereFrom))
- int CbcMain1 (int argc, const char *argv[], CbcModel &babSolver, int(CbcModel *currentSolver, int whereFrom))
- void setCutAndHeuristicOptions (CbcModel &model)

```
8.63.1 Function Documentation
```

```
8.63.1.1 void getIntegerInformation ( const OsiObject * object, double & originalLower, double & originalUpper )
So we can use osiObject or CbcObject during transition.
8.63.1.2 int CbcMain (int argc, const char * argv[], OsiClpSolverInterface & solver, CbcModel ** babSolver)
8.63.1.3
         int CbcMain ( int argc, const char * argv[], CbcModel & babSolver )
8.63.1.4
         int callCbc ( const char * input2, OsiClpSolverInterface & solver1 )
8.63.1.5
         int callCbc ( const char * input2 )
8.63.1.6
         int callCbc ( const std::string input2, OsiClpSolverInterface & solver1 )
8.63.1.7 int callCbc (const std::string input2)
8.63.1.8 void CbcMain0 ( CbcModel & babSolver )
8.63.1.9 int CbcMain1 (int argc, const char * argv[], CbcModel & babSolver)
8.63.1.10 int callCbc ( const char * input2, CbcModel & babSolver )
8.63.1.11 int callCbc ( const std::string input2, CbcModel & babSolver )
8.63.1.12 int callCbc1 ( const char * input2, CbcModel & babSolver )
8.63.1.13 int callCbc1 ( const std::string input2, CbcModel & babSolver )
          int callCbc1 ( const char * input2, CbcModel & babSolver, int(CbcModel *currentSolver, int whereFrom) )
8.63.1.15 int callCbc1 ( const std::string input2, CbcModel & babSolver, int(CbcModel *currentSolver, int whereFrom) )
8.63.1.16 int CbcMain1 (int argc, const char * argv[], CbcModel & babSolver, int(CbcModel *currentSolver, int whereFrom)
8.63.1.17 void setCutAndHeuristicOptions ( CbcModel & model )
```

8.64 /home/ted/COIN/trunk/Cbc/src/CbcNode.hpp File Reference

```
#include <string>
#include <vector>
#include "CoinWarmStartBasis.hpp"
#include "CoinSearchTree.hpp"
#include "CbcBranchBase.hpp"
#include "CbcNodeInfo.hpp"
#include "CbcFullNodeInfo.hpp"
#include "CbcPartialNodeInfo.hpp"
```

Classes

class CbcNode

Information required while the node is live.

8.65 /home/ted/COIN/trunk/Cbc/src/CbcNodeInfo.hpp File Reference

```
#include <string>
#include <vector>
#include "CoinWarmStartBasis.hpp"
#include "CoinSearchTree.hpp"
#include "CbcBranchBase.hpp"
```

Classes

class CbcNodeInfo

Information required to recreate the subproblem at this node.

8.66 /home/ted/COIN/trunk/Cbc/src/CbcNWay.hpp File Reference

Classes

class CbcNWay

Define an n-way class for variables.

· class CbcNWayBranchingObject

N way branching Object class.

8.67 /home/ted/COIN/trunk/Cbc/src/CbcObject.hpp File Reference

```
#include <string>
#include <vector>
#include "OsiBranchingObject.hpp"
```

Classes

struct CbcStrongInfo

Abstract base class for 'objects'.

class CbcObject

8.68 /home/ted/COIN/trunk/Cbc/src/CbcObjectUpdateData.hpp File Reference

```
#include "CbcObject.hpp"
```

Classes

class CbcObjectUpdateData

8.69 /home/ted/COIN/trunk/Cbc/src/CbcParam.hpp File Reference

```
#include "OsiSolverInterface.hpp"
#include "CbcModel.hpp"
```

Classes

· class CbcParam

Very simple class for setting parameters.

Enumerations

enum CbcParameterType {

CBC_PARAM_GENERALQUERY = -100, CBC_PARAM_FULLGENERALQUERY, CLP_PARAM_DBL_PRIMALTOLERANCE = 1, CLP_PARAM_DBL_DUALTOLERANCE,

CBC_PARAM_DBL_CUTOFF, CLP_PARAM_DBL_TIMELIMIT, CLP_PARAM_DBL_DUALBOUND, CLP_PARAM_DBL_PRIMALWEIGHT.

CLP_PARAM_DBL_OBJSCALE, CLP_PARAM_DBL_RHSSCALE, CBC_PARAM_DBL_INFEASIBILITYWEIG-HT = 51, CBC_PARAM_DBL_INTEGERTOLERANCE,

CBC_PARAM_DBL_INCREMENT, CBC_PARAM_DBL_ALLOWABLEGAP, CBC_PARAM_DBL_DJFIX = 81, C-BC_PARAM_DBL_GAPRATIO,

CBC_PARAM_DBL_TIGHTENFACTOR, CLP_PARAM_INT_LOGLEVEL = 101, CLP_PARAM_INT_SOLVERL-OGLEVEL, CBC_PARAM_INT_MAXNODES,

CBC_PARAM_INT_STRONGBRANCHING, CLP_PARAM_INT_MAXFACTOR, CLP_PARAM_INT_PERTVALUE, CLP_PARAM_INT_MAXITERATION,

CLP_PARAM_INT_PRESOLVEPASS, CLP_PARAM_INT_IDIOT, CLP_PARAM_INT_SPRINT, CLP_PARAM_INT_OUTPUTFORMAT,

CLP_PARAM_INT_SLPVALUE, CLP_PARAM_INT_PRESOLVEOPTIONS, CLP_PARAM_INT_PRINTOPTIONS, CLP_PARAM_INT_SPECIALOPTIONS,

CLP_PARAM_STR_DIRECTION = 201, CLP_PARAM_STR_DUALPIVOT, CLP_PARAM_STR_SCALING, CLP-PARAM_STR_ERRORSALLOWED,

CLP_PARAM_STR_KEEPNAMES, CLP_PARAM_STR_SPARSEFACTOR, CLP_PARAM_STR_PRIMALPIVO-T, CLP_PARAM_STR_PRESOLVE,

CLP PARAM STR CRASH, CLP PARAM STR BIASLU, CLP PARAM STR PERTURBATION, CLP PARA-

M_STR_MESSAGES,

CLP_PARAM_STR_AUTOSCALE, CLP_PARAM_STR_CHOLESKY, CLP_PARAM_STR_KKT, CLP_PARAM_-STR_BARRIERSCALE.

CLP_PARAM_STR_GAMMA, CLP_PARAM_STR_CROSSOVER, CLP_PARAM_STR_PFI, CLP_PARAM_NOTUSED ALGORITHM,

CBC_PARAM_STR_NODESTRATEGY = 251, CBC_PARAM_STR_BRANCHSTRATEGY, CBC_PARAM_NOT-USED ADDCUTSSTRATEGY, CBC_PARAM_STR_GOMORYCUTS,

CBC_PARAM_STR_PROBINGCUTS, CBC_PARAM_STR_KNAPSACKCUTS, CBC_PARAM_NOTUSED_OD-DHOLECUTS, CBC_PARAM_STR_ROUNDING,

CBC_PARAM_STR_SOLVER, CBC_PARAM_STR_CLIQUECUTS, CBC_PARAM_STR_COSTSTRATEGY, C-BC_PARAM_STR_FLOWCUTS,

CBC_PARAM_STR_MIXEDCUTS, CBC_PARAM_STR_TWOMIRCUTS, CBC_PARAM_STR_PREPROCESS, CLP_PARAM_ACTION_DIRECTORY = 301,

CLP_PARAM_ACTION_IMPORT, CLP_PARAM_ACTION_EXPORT, CLP_PARAM_ACTION_RESTORE, CLP-PARAM_ACTION_SAVE,

CLP_PARAM_ACTION_DUALSIMPLEX, CLP_PARAM_ACTION_PRIMALSIMPLEX, CLP_PARAM_ACTION_-MAXIMIZE, CLP_PARAM_ACTION_MINIMIZE,

CLP_PARAM_ACTION_EXIT, CLP_PARAM_ACTION_STDIN, CLP_PARAM_ACTION_UNITTEST, CLP_PARAM_ACTION_NETLIB_DUAL,

CLP_PARAM_ACTION_NETLIB_PRIMAL, CLP_PARAM_ACTION_SOLUTION, CLP_PARAM_ACTION_TIGHTEN, CLP_PARAM_ACTION_FAKEBOUND,

CLP_PARAM_ACTION_HELP, CLP_PARAM_ACTION_PLUSMINUS, CLP_PARAM_ACTION_NETWORK, CLP_PARAM_ACTION_ALLSLACK,

CLP_PARAM_ACTION_REVERSE, CLP_PARAM_ACTION_BARRIER, CLP_PARAM_ACTION_NETLIB_BARRIER, CLP_PARAM_ACTION_REALLY_SCALE,

CLP_PARAM_ACTION_BASISIN, CLP_PARAM_ACTION_BASISOUT, CLP_PARAM_ACTION_SOLVECONTI-NUOUS, CBC_PARAM_ACTION_BAB,

CBC_PARAM_ACTION_MIPLIB, CLP_PARAM_ACTION_CLEARCUTS, CLP_VERSION_NOTUSED_PRINTV-ERSION, CBC_PARAM_NOTUSED_OSLSTUFF = 401,

CBC_PARAM_NOTUSED_CBCSTUFF, CBC_PARAM_NOTUSED_INVALID = 1000 }

Parameter codes.

8.69.1 Enumeration Type Documentation

8.69.1.1 enum CbcParameterType

Parameter codes.

Parameter type ranges are allocated as follows

- 1 100 double parameters
- 101 200 integer parameters
- 201 250 string parameters
- 251 300 cuts etc(string but broken out for clarity)
- 301 400 'actions'

'Actions' do not necessarily invoke an immediate action; it's just that they don't fit neatly into the parameters array.

This coding scheme is in flux. CBC_PARAM_STR_NODESTRATEGY, CBC_PARAM_STR_BRANCHSTRATEGY, CB-C_PARAM_NOTUSED_ADDCUTSSTRATEGY, CLP_PARAM_ACTION_CLEARCUTS, CBC_PARAM_NOTUSED_O-SLSTUFF, CBC_PARAM_NOTUSED_CBCSTUFF are not used at present (03.10.24).

Enumerator

CBC_PARAM_GENERALQUERY

CBC PARAM FULLGENERALQUERY

CLP_PARAM_DBL_PRIMALTOLERANCE

CLP_PARAM_DBL_DUALTOLERANCE

CBC_PARAM_DBL_CUTOFF

CLP_PARAM_DBL_TIMELIMIT

CLP_PARAM_DBL_DUALBOUND

CLP_PARAM_DBL_PRIMALWEIGHT

CLP_PARAM_DBL_OBJSCALE

CLP_PARAM_DBL_RHSSCALE

CBC_PARAM_DBL_INFEASIBILITYWEIGHT

CBC_PARAM_DBL_INTEGERTOLERANCE

CBC_PARAM_DBL_INCREMENT

CBC PARAM DBL ALLOWABLEGAP

CBC PARAM DBL DJFIX

CBC PARAM DBL GAPRATIO

CBC PARAM DBL TIGHTENFACTOR

CLP_PARAM_INT_LOGLEVEL

CLP_PARAM_INT_SOLVERLOGLEVEL

CBC_PARAM_INT_MAXNODES

CBC_PARAM_INT_STRONGBRANCHING

CLP_PARAM_INT_MAXFACTOR

CLP_PARAM_INT_PERTVALUE

CLP PARAM INT MAXITERATION

CLP_PARAM_INT_PRESOLVEPASS

CLP_PARAM_INT_IDIOT

CLP_PARAM_INT_SPRINT

CLP_PARAM_INT_OUTPUTFORMAT

CLP PARAM INT SLPVALUE

CLP PARAM INT PRESOLVEOPTIONS

CLP_PARAM_INT_PRINTOPTIONS

CLP_PARAM_INT_SPECIALOPTIONS

CLP_PARAM_STR_DIRECTION

CLP_PARAM_STR_DUALPIVOT

CLP_PARAM_STR_SCALING

CLP_PARAM_STR_ERRORSALLOWED

CLP_PARAM_STR_KEEPNAMES

CLP_PARAM_STR_SPARSEFACTOR

CLP_PARAM_STR_PRIMALPIVOT

CLP_PARAM_STR_PRESOLVE

CLP_PARAM_STR_CRASH

- CLP_PARAM_STR_BIASLU
- CLP_PARAM_STR_PERTURBATION
- CLP_PARAM_STR_MESSAGES
- CLP_PARAM_STR_AUTOSCALE
- CLP_PARAM_STR_CHOLESKY
- CLP PARAM STR KKT
- CLP_PARAM_STR_BARRIERSCALE
- CLP_PARAM_STR_GAMMA
- CLP_PARAM_STR_CROSSOVER
- CLP_PARAM_STR_PFI
- CLP_PARAM_NOTUSED_ALGORITHM
- CBC_PARAM_STR_NODESTRATEGY
- CBC_PARAM_STR_BRANCHSTRATEGY
- CBC_PARAM_NOTUSED_ADDCUTSSTRATEGY
- CBC_PARAM_STR_GOMORYCUTS
- CBC_PARAM_STR_PROBINGCUTS
- CBC_PARAM_STR_KNAPSACKCUTS
- CBC PARAM NOTUSED ODDHOLECUTS
- CBC_PARAM_STR_ROUNDING
- CBC_PARAM_STR_SOLVER
- CBC_PARAM_STR_CLIQUECUTS
- CBC_PARAM_STR_COSTSTRATEGY
- CBC_PARAM_STR_FLOWCUTS
- CBC_PARAM_STR_MIXEDCUTS
- CBC_PARAM_STR_TWOMIRCUTS
- CBC_PARAM_STR_PREPROCESS
- CLP_PARAM_ACTION_DIRECTORY
- CLP_PARAM_ACTION_IMPORT
- CLP_PARAM_ACTION_EXPORT
- CLP_PARAM_ACTION_RESTORE
- CLP PARAM ACTION SAVE
- CLP_PARAM_ACTION_DUALSIMPLEX
- CLP_PARAM_ACTION_PRIMALSIMPLEX
- CLP_PARAM_ACTION_MAXIMIZE
- CLP_PARAM_ACTION_MINIMIZE
- CLP_PARAM_ACTION_EXIT
- CLP_PARAM_ACTION_STDIN
- CLP_PARAM_ACTION_UNITTEST
- CLP_PARAM_ACTION_NETLIB_DUAL
- CLP_PARAM_ACTION_NETLIB_PRIMAL
- CLP_PARAM_ACTION_SOLUTION
- CLP_PARAM_ACTION_TIGHTEN

CLP_PARAM_ACTION_FAKEBOUND

CLP_PARAM_ACTION_HELP

CLP_PARAM_ACTION_PLUSMINUS

CLP_PARAM_ACTION_NETWORK

CLP_PARAM_ACTION_ALLSLACK

CLP_PARAM_ACTION_REVERSE

CLP_PARAM_ACTION_BARRIER

CLP_PARAM_ACTION_NETLIB_BARRIER

CLP_PARAM_ACTION_REALLY_SCALE

CLP PARAM ACTION BASISIN

CLP_PARAM_ACTION_BASISOUT

CLP_PARAM_ACTION_SOLVECONTINUOUS

CBC_PARAM_ACTION_BAB

CBC_PARAM_ACTION_MIPLIB

CLP_PARAM_ACTION_CLEARCUTS

CLP_VERSION_NOTUSED_PRINTVERSION

CBC_PARAM_NOTUSED_OSLSTUFF

CBC_PARAM_NOTUSED_CBCSTUFF

CBC_PARAM_NOTUSED_INVALID

Definition at line 35 of file CbcParam.hpp.

8.70 /home/ted/COIN/trunk/Cbc/src/CbcPartialNodeInfo.hpp File Reference

```
#include <string>
#include <vector>
#include "CoinWarmStartBasis.hpp"
#include "CoinSearchTree.hpp"
#include "CbcBranchBase.hpp"
#include "CbcNodeInfo.hpp"
```

Classes

· class CbcPartialNodeInfo

Holds information for recreating a subproblem by incremental change from the parent.

8.71 /home/ted/COIN/trunk/Cbc/src/CbcSimpleInteger.hpp File Reference

#include "CbcBranchingObject.hpp"

Classes

class CbcIntegerBranchingObject

Simple branching object for an integer variable.

class CbcSimpleInteger

Define a single integer class.

8.72 /home/ted/COIN/trunk/Cbc/src/CbcSimpleIntegerDynamicPseudoCost.hpp File Reference

```
#include "CbcSimpleInteger.hpp"
```

Classes

• class CbcSimpleIntegerDynamicPseudoCost

Define a single integer class but with dynamic pseudo costs.

· class CbcIntegerPseudoCostBranchingObject

Simple branching object for an integer variable with pseudo costs.

Macros

- #define TYPERATIO 0.9
- #define MINIMUM MOVEMENT 0.1
- #define TYPE2 0
- #define INFEAS 1
- #define MOD SHADOW 1
- #define WEIGHT_AFTER 0.8
- #define WEIGHT_BEFORE 0.1
- #define WEIGHT_PRODUCT

8.72.1 Macro Definition Documentation

8.72.1.1 #define TYPERATIO 0.9

Definition at line 13 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

8.72.1.2 #define MINIMUM_MOVEMENT 0.1

Definition at line 14 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

8.72.1.3 #define TYPE2 0

Definition at line 15 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

8.72.1.4 #define INFEAS 1

Definition at line 17 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

8.72.1.5 #define MOD_SHADOW 1

Definition at line 18 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

```
8.72.1.6 #define WEIGHT_AFTER 0.8
```

Definition at line 20 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

```
8.72.1.7 #define WEIGHT BEFORE 0.1
```

Definition at line 21 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

```
8.72.1.8 #define WEIGHT_PRODUCT
```

Definition at line 23 of file CbcSimpleIntegerDynamicPseudoCost.hpp.

8.73 /home/ted/COIN/trunk/Cbc/src/CbcSimpleIntegerPseudoCost.hpp File Reference

```
#include "CbcSimpleInteger.hpp"
```

Classes

class CbcSimpleIntegerPseudoCost

Define a single integer class but with pseudo costs.

8.74 /home/ted/COIN/trunk/Cbc/src/CbcSolver.hpp File Reference

Defines CbcSolver, the proposed top-level class for the new-style cbc solver.

```
#include <string>
#include <vector>
#include "CoinMessageHandler.hpp"
#include "OsiClpSolverInterface.hpp"
#include "CbcModel.hpp"
#include "CbcOrClpParam.hpp"
```

Classes

class CbcSolver

This allows the use of the standalone solver in a flexible manner.

struct CbcSolverUsefulData

Structure to hold useful arrays.

class CbcUser

A class to allow the use of unknown user functionality.

class CbcStopNow

Support the use of a call back class to decide whether to stop.

8.74.1 Detailed Description

Defines CbcSolver, the proposed top-level class for the new-style cbc solver. This class is currently an orphan. With the removal of all code flagged with the NEWS_STYLE_SOLVER, this class is never instantiated (and cannot be instantiated). It is available to be coopted as a top-level object wrapping the current CbcMain0 and CbcMain1, should that appear to be a desireable path forward. – Ih, 091211 –

Definition in file CbcSolver.hpp.

8.75 /home/ted/COIN/trunk/Cbc/src/CbcSolverAnalyze.hpp File Reference

Look to see if a constraint is all-integer (variables & coeffs), or could be all integer.

Functions

 int * analyze (OsiClpSolverInterface *solverMod, int &numberChanged, double &increment, bool changeInt, Coin-MessageHandler *generalMessageHandler, bool noPrinting)

8.75.1 Detailed Description

Look to see if a constraint is all-integer (variables & coeffs), or could be all integer.

Definition in file CbcSolverAnalyze.hpp.

8.75.2 Function Documentation

8.75.2.1 int* analyze (OsiClpSolverInterface * solverMod, int & numberChanged, double & increment, bool changeInt, CoinMessageHandler * generalMessageHandler, bool noPrinting)

8.76 /home/ted/COIN/trunk/Cbc/src/CbcSolverExpandKnapsack.hpp File Reference

Expanding possibilities of x*y, where x*y are both integers, constructing a knapsack constraint.

Functions

- OsiSolverInterface * expandKnapsack (CoinModel &model, int *whichColumn, int *knapsackStart, int *knapsack-Row, int &numberKnapsack, CglStored &stored, int logLevel, int fixedPriority, int SOSPriority, CoinModel &tightenedModel)
- void afterKnapsack (const CoinModel &coinModel2, const int *whichColumn, const int *knapsackStart, const int *knapsackRow, int numberKnapsack, const double *knapsackSolution, double *solution, int logLevel)

8.76.1 Detailed Description

Expanding possibilities of x*y, where x*y are both integers, constructing a knapsack constraint. Results in a tighter model.

Definition in file CbcSolverExpandKnapsack.hpp.

8.76.2 Function Documentation

- 8.76.2.1 OsiSolverInterface* expandKnapsack (CoinModel & model, int * whichColumn, int * knapsackStart, int * knapsackRow, int & numberKnapsack, CglStored & stored, int logLevel, int fixedPriority, int SOSPriority, CoinModel & tightenedModel)
- 8.76.2.2 void afterKnapsack (const CoinModel & coinModel2, const int * whichColumn, const int * knapsackStart, const int * knapsackRow, int numberKnapsack, const double * knapsackSolution, double * solution, int logLevel)

8.77 /home/ted/COIN/trunk/Cbc/src/CbcSolverHeuristics.hpp File Reference

Routines for doing heuristics.

Functions

- void crunchIt (ClpSimplex *model)
- OsiClpSolverInterface * fixVubs (CbcModel &model, int skipZero2, int &doAction, CoinMessageHandler *, const double *lastSolution, double dextra[6], int extra[5])
- int doHeuristics (CbcModel *model, int type, CbcOrClpParam *parameters_, int numberParameters_, int no-Printing_, int initialPumpTune)
 - 1 add heuristics to model 2 do heuristics (and set cutoff and best solution) 3 for miplib test so skip some (out model later)

8.77.1 Detailed Description

Routines for doing heuristics.

Definition in file CbcSolverHeuristics.hpp.

- 8.77.2 Function Documentation
- 8.77.2.1 void crunchlt (ClpSimplex * model)
- 8.77.2.2 OsiClpSolverInterface* fixVubs (CbcModel & model, int skipZero2, int & doAction, CoinMessageHandler * , const double * lastSolution, double dextra[6], int extra[5])
- 8.77.2.3 int doHeuristics (CbcModel * model, int type, CbcOrClpParam * parameters_, int numberParameters_, int noPrinting_, int initialPumpTune)
- 1 add heuristics to model 2 do heuristics (and set cutoff and best solution) 3 for miplib test so skip some (out model later)

8.78 /home/ted/COIN/trunk/Cbc/src/CbcSOS.hpp File Reference

Classes

class CbcSOS

Branching object for Special Ordered Sets of type 1 and 2.

class CbcSOSBranchingObject

Branching object for Special ordered sets.

8.79 /home/ted/COIN/trunk/Cbc/src/CbcStatistics.hpp File Reference

#include "CbcModel.hpp"

Classes

class CbcStatistics

For gathering statistics.

8.80 /home/ted/COIN/trunk/Cbc/src/CbcStrategy.hpp File Reference

```
#include "CbcModel.hpp"
```

Classes

· class CbcStrategy

Strategy base class.

class CbcStrategyNull

Null class.

· class CbcStrategyDefault

Default class.

• class CbcStrategyDefaultSubTree

Default class for sub trees.

8.81 /home/ted/COIN/trunk/Cbc/src/CbcSubProblem.hpp File Reference

8.82 /home/ted/COIN/trunk/Cbc/src/CbcThread.hpp File Reference

```
#include "CbcModel.hpp"
#include "CbcNode.hpp"
```

Classes

class CbcThread

A class to encapsulate thread stuff.

• class CbcBaseModel

Base model.

8.83 /home/ted/COIN/trunk/Cbc/src/CbcTree.hpp File Reference

```
#include <vector>
#include <algorithm>
#include <cmath>
#include "CoinHelperFunctions.hpp"
#include "CbcCompare.hpp"
```

Classes

• class CbcTree

Using MS heap implementation.

8.84 /home/ted/COIN/trunk/Cbc/src/CbcTreeLocal.hpp File Reference

```
#include "CbcTree.hpp"
#include "CbcNode.hpp"
#include "OsiRowCut.hpp"
```

Classes

- class CbcTreeLocal
- class CbcTreeVariable

8.85 /home/ted/COIN/trunk/Cbc/src/ClpAmplObjective.hpp File Reference

```
#include "ClpObjective.hpp"
#include "CoinPackedMatrix.hpp"
```

Classes

• class ClpAmplObjective

Ampl Objective Class.

8.86 /home/ted/COIN/trunk/Cbc/src/ClpConstraintAmpl.hpp File Reference

```
#include "ClpConstraint.hpp"
```

Classes

class ClpConstraintAmpl

Ampl Constraint Class.

8.87 /home/ted/COIN/trunk/Cbc/src/config_cbc_default.h File Reference

Macros

- #define CBC_VERSION "trunk"
- #define CBC_VERSION_MAJOR 9999
- #define CBC_VERSION_MINOR 9999
- #define CBC_VERSION_RELEASE 9999

8.87.1 Macro Definition Documentation

8.87.1.1 #define CBC_VERSION "trunk"

Definition at line 8 of file config_cbc_default.h.

8.87.1.2 #define CBC_VERSION_MAJOR 9999

Definition at line 11 of file config_cbc_default.h.

8.87.1.3 #define CBC_VERSION_MINOR 9999

Definition at line 14 of file config_cbc_default.h.

8.87.1.4 #define CBC_VERSION_RELEASE 9999

Definition at line 17 of file config_cbc_default.h.

8.88 /home/ted/COIN/trunk/Cbc/src/config default.h File Reference

```
#include "configall_system.h"
#include "config_cbc_default.h"
```

Macros

- #define COIN_CBC_CHECKLEVEL 0
- #define COIN_CBC_VERBOSITY 0
- #define COIN_HAS_CGL 1
- #define COIN_HAS_CLP 1
- #define COIN_HAS_COINUTILS 1
- #define COIN_HAS_OSI 1
- #define COIN_HAS_VOL 1

8.88.1 Macro Definition Documentation

8.88.1.1 #define COIN_CBC_CHECKLEVEL 0

Definition at line 14 of file config_default.h.

8.88.1.2 #define COIN_CBC_VERBOSITY 0

Definition at line 17 of file config_default.h.

8.88.1.3 #define COIN_HAS_CGL 1

Definition at line 20 of file config_default.h.

8.88.1.4 #define COIN_HAS_CLP 1

Definition at line 23 of file config_default.h.

```
8.88.1.5 #define COIN_HAS_COINUTILS 1
```

Definition at line 26 of file config default.h.

```
8.88.1.6 #define COIN_HAS_OSI 1
```

Definition at line 29 of file config_default.h.

```
8.88.1.7 #define COIN_HAS_VOL 1
```

Definition at line 32 of file config default.h.

8.89 /home/ted/COIN/trunk/Cbc/src/OsiCbc/OsiCbcSolverInterface.hpp File Reference

```
#include <string>
#include <cfloat>
#include <map>
#include "CbcModel.hpp"
#include "CoinPackedMatrix.hpp"
#include "OsiSolverInterface.hpp"
#include "CbcStrategy.hpp"
#include "CoinWarmStartBasis.hpp"
```

Classes

· class OsiCbcSolverInterface

Cbc Solver Interface.

Functions

- bool OsiCbcHasNDEBUG ()
- void OsiCbcSolverInterfaceUnitTest (const std::string &mpsDir, const std::string &netlibDir)

A function that tests the methods in the OsiCbcSolverInterface class.

Variables

• static const double OsiCbcInfinity = COIN_DBL_MAX

```
8.89.1 Function Documentation
```

```
8.89.1.1 bool OsiCbcHasNDEBUG ( )
```

8.89.1.2 void OsiCbcSolverInterfaceUnitTest (const std::string & mpsDir, const std::string & netlibDir)

A function that tests the methods in the OsiCbcSolverInterface class.

8.89.2 Variable Documentation

8.89.2.1 const double OsiCbcInfinity = COIN_DBL_MAX [static]

Definition at line 20 of file OsiCbcSolverInterface.hpp.

Index

Symbols	\sim CbcEventHandler
\sim CbcBaseModel	CbcEventHandler, 101
CbcBaseModel, 28	\sim CbcFathom
\sim CbcBranchAllDifferent	CbcFathom, 104
CbcBranchAllDifferent, 29	\sim CbcFathomDynamicProgramming
\sim CbcBranchCut	CbcFathomDynamicProgramming, 107
CbcBranchCut, 31	\sim CbcFeasibilityBase
\sim CbcBranchDecision	CbcFeasibilityBase, 110
CbcBranchDecision, 34	\sim CbcFixVariable
\sim CbcBranchDefaultDecision	CbcFixVariable, 114
CbcBranchDefaultDecision, 37	\sim CbcFixingBranchingObject
\sim CbcBranchDynamicDecision	CbcFixingBranchingObject, 112
CbcBranchDynamicDecision, 39	~CbcFollowOn
\sim CbcBranchToFixLots	CbcFollowOn, 117
CbcBranchToFixLots, 48	~CbcFullNodeInfo
~CbcBranchingObject	CbcFullNodeInfo, 120
CbcBranchingObject, 43	~CbcGenCtlBlk
∼CbcCbcParam	CbcGenCtlBlk, 129
CbcCbcParam, 53	~CbcGenParam
∼CbcClique	CbcGenParam, 143
•	~CbcGeneral
CbcClique, 56 CbcCliqueBranchingObject	
	CbcGeneral, 138 ~CbcHeuristic
CbcCliqueBranchingObject, 59	
~CbcCompare	Challerwistic, 148
CbcCompare, 61	~CbcHeuristicCrossover
~CbcCompareBase	CbcHeuristicCrossover, 156
CbcCompareBase, 62	~CbcHeuristicDINS
~CbcCompareDefault	CbcHeuristicDINS, 159
CbcCompareDefault, 66	~CbcHeuristicDW
\sim CbcCompareDepth	CbcHeuristicDW, 181
CbcCompareDepth, 70	\sim CbcHeuristicDive
\sim CbcCompareEstimate	CbcHeuristicDive, 163
CbcCompareEstimate, 71	\sim CbcHeuristicDiveCoefficient
\sim CbcCompareObjective	CbcHeuristicDiveCoefficient, 167
CbcCompareObjective, 72	\sim CbcHeuristicDiveFractional
\sim CbcConsequence	CbcHeuristicDiveFractional, 169
CbcConsequence, 73	\sim CbcHeuristicDiveGuided
\sim CbcCountRowCut	CbcHeuristicDiveGuided, 170
CbcCountRowCut, 75	\sim CbcHeuristicDiveLineSearch
\sim CbcCutBranchingObject	CbcHeuristicDiveLineSearch, 172
CbcCutBranchingObject, 78	\sim CbcHeuristicDivePseudoCost
\sim CbcCutGenerator	CbcHeuristicDivePseudoCost, 174
CbcCutGenerator, 83	~CbcHeuristicDiveVectorLength
\sim CbcCutModifier	CbcHeuristicDiveVectorLength, 176
CbcCutModifier, 91	~CbcHeuristicDynamic3
\sim CbcCutSubsetModifier	CbcHeuristicDynamic3, 191
CbcCutSubsetModifier, 92	~CbcHeuristicFPump
~CbcDummyBranchingObject	CbcHeuristicFPump, 195
CbcDummyBranchingObject, 94	~CbcHeuristicGreedyCover
~CbcDynamicPseudoCostBranchingObject	CbcHeuristicGreedyCover, 202
CbcDynamicPseudoCostBranchingObject, 97	~CbcHeuristicGreedyEquality
Sobynamici scadocosibianciningObject, 37	- Sport touristical cody Equality

Ob all a mistic One a du Farralita do Co	Ol O - : D 0.45
CbcHeuristicGreedyEquality, 205	CbcOsiParam, 345
~CbcHeuristicGreedySOS	~CbcOsiSolver
CbcHeuristicGreedySOS, 208	CbcOsiSolver, 347
~CbcHeuristicJustOne	~CbcParam
CbcHeuristicJustOne, 211	CbcParam, 350
~CbcHeuristicLocal	~CbcPartialNodeInfo
CbcHeuristicLocal, 213	CbcPartialNodeInfo, 355
~CbcHeuristicNaive	~CbcRounding
CbcHeuristicNaive, 216	CbcRounding, 358
~CbcHeuristicNode	~CbcRowCuts
CbcHeuristicNode, 217	CbcRowCuts, 360
~CbcHeuristicNodeList	~CbcSOS
CbcHeuristicNodeList, 218	CbcSOS, 392
~CbcHeuristicPartial	\sim CbcSOSBranchingObject
CbcHeuristicPartial, 220	CbcSOSBranchingObject, 396
~CbcHeuristicPivotAndFix	\sim CbcSerendipity
CbcHeuristicPivotAndFix, 222	CbcSerendipity, 361
\sim CbcHeuristicProximity	\sim CbcSimpleInteger
CbcHeuristicProximity, 224	CbcSimpleInteger, 364
\sim CbcHeuristicRENS	~CbcSimpleIntegerDynamicPseudoCost
CbcHeuristicRENS, 228	CbcSimpleIntegerDynamicPseudoCost, 371
\sim CbcHeuristicRINS	~CbcSimpleIntegerPseudoCost
CbcHeuristicRINS, 231	CbcSimpleIntegerPseudoCost, 382
\sim CbcHeuristicRandRound	~CbcSolver
CbcHeuristicRandRound, 226	CbcSolver, 386
~CbcHeuristicVND	~CbcStatistics
CbcHeuristicVND, 234	CbcStatistics, 398
~CbcldiotBranch	~CbcStopNow
CbcldiotBranch, 237	CbcStopNow, 401
~CbcIntegerBranchingObject	~CbcStrategy
CbcIntegerBranchingObject, 240	CbcStrategy, 403
~CbcIntegerPseudoCostBranchingObject	~CbcStrategyDefault
CbcIntegerPseudoCostBranchingObject, 244	CbcStrategyDefault, 407
~CbcLongCliqueBranchingObject	~CbcStrategyDefaultSubTree
CbcLongCliqueBranchingObject, 246	CbcStrategyDefaultSubTree, 409
~CbcLotsize	~CbcStrategyNull
CbcLotsize, 249	CbcStrategyNull, 411
~CbcLotsizeBranchingObject	~CbcThread
CbcLotsizeBranchingObject, 253	CbcThread, 414
~CbcModel	~CbcTree
CbcModel, 273	CbcTree, 417
~CbcNWay	~CbcTreeLocal
	CbcTreeLocal, 423
CbcNWay, 328 ChcNWayPranching Chicat	,
~CbcNWayBranchingObject	~CbcTreeVariable
CbcNWayBranchingObject, 331	CbcTreeVariable, 426
~CbcNode	~CbcUser
CbcNode, 313	CbcUser, 430
~CbcNodeInfo	~CglTemporary
CbcNodeInfo, 321	CglTemporary, 432
~CbcObject	~ClpAmplObjective
CbcObject, 334	ClpAmplObjective, 435
~CbcObjectUpdateData	~ClpConstraintAmpl
CbcObjectUpdateData, 340	ClpConstraintAmpl, 437
\sim CbcOsiParam	\sim OsiBiLinear

OsiBiLinear, 445	/home/ted/COIN/trunk/Cbc/src/CbcCompareDepth.hpp,
~OsiBiLinearBranchingObject	514
OsiBiLinearBranchingObject, 452	/home/ted/COIN/trunk/Cbc/src/CbcCompareEstimate
~OsiBiLinearEquality	hpp, 514
OsiBiLinearEquality, 454	/home/ted/COIN/trunk/Cbc/src/CbcCompareObjective
~OsiCbcSolverInterface	hpp, 514
OsiCbcSolverInterface, 461	/home/ted/COIN/trunk/Cbc/src/CbcConfig.h, 515
~OsiChooseStrongSubset	/home/ted/COIN/trunk/Cbc/src/CbcConsequence.hpp,
OsiChooseStrongSubset, 474	515
~OsiLink	/home/ted/COIN/trunk/Cbc/src/CbcCountRowCut.hpp,
OsiLink, 477	515
~OsiLinkBranchingObject	/home/ted/COIN/trunk/Cbc/src/CbcCutGenerator.hpp, 515
OsiLinkBranchingObject, 478	/home/ted/COIN/trunk/Cbc/src/CbcCutModifier.hpp, 516
~OsiLinkedBound	/home/ted/COIN/trunk/Cbc/src/CbcCutSubsetModifier
OsiLinkedBound, 480	hpp, 516
~OsiOldLink	/home/ted/COIN/trunk/Cbc/src/CbcDummyBranching-
OsiOldLink, 482	Object.hpp, 516
~OsiOldLinkBranchingObject	/home/ted/COIN/trunk/Cbc/src/CbcEventHandler.hpp, 517
OsiOldLinkBranchingObject, 484	/home/ted/COIN/trunk/Cbc/src/CbcFathom.hpp, 517
~OsiOneLink	/home/ted/COIN/trunk/Cbc/src/CbcFathomDynamic-
OsiOneLink, 485	Programming.hpp, 518
~OsiSimpleFixedInteger	/home/ted/COIN/trunk/Cbc/src/CbcFeasibilityBase.hpp,
OsiSimpleFixedInteger, 487	518
~OsiSolverLinearizedQuadratic	/home/ted/COIN/trunk/Cbc/src/CbcFixVariable.hpp, 518
OsiSolverLinearizedQuadratic, 489	/home/ted/COIN/trunk/Cbc/src/CbcFollowOn.hpp, 518
~OsiSolverLink	/home/ted/COIN/trunk/Cbc/src/CbcFullNodeInfo.hpp, 519
OsiSolverLink, 495	/home/ted/COIN/trunk/Cbc/src/CbcGenCbcParam.hpp,
~OsiUsesBiLinear	519
OsiUsesBiLinear, 502	/home/ted/COIN/trunk/Cbc/src/CbcGenCtlBlk.hpp, 519
/home/ted/COIN/trunk/Cbc/src/CbcBranchActual.hpp, 509	/home/ted/COIN/trunk/Cbc/src/CbcGenMessages.hpp,
/home/ted/COIN/trunk/Cbc/src/CbcBranchAllDifferent	521
hpp, 509	/home/ted/COIN/trunk/Cbc/src/CbcGenOsiParam.hpp,
/home/ted/COIN/trunk/Cbc/src/CbcBranchBase.hpp, 510	522
/home/ted/COIN/trunk/Cbc/src/CbcBranchCut.hpp, 511	/home/ted/COIN/trunk/Cbc/src/CbcGenParam.hpp, 522
/home/ted/COIN/trunk/Cbc/src/CbcBranchDecision.hpp,	/home/ted/COIN/trunk/Cbc/src/CbcGeneral.hpp, 521
511	/home/ted/COIN/trunk/Cbc/src/CbcGeneralDepth.hpp,
/home/ted/COIN/trunk/Cbc/src/CbcBranchDefaultDecision	521 /home/tod/COIN/trunk/Cha/ara/Challouristia han 522
hpp, 511	/home/ted/COIN/trunk/Cbc/src/CbcHeuristic.hpp, 523
/home/ted/COIN/trunk/Cbc/src/CbcBranchDynamic.hpp,	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDINS.hpp, 523
511	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDW.hpp, 525
/home/ted/COIN/trunk/Cbc/src/CbcBranchLotsize.hpp,	
512	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDive.hpp, 524
/home/ted/COIN/trunk/Cbc/src/CbcBranchToFixLots.hpp,	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveCoefficient
513 /home/ted/COIN/trunk/Cbc/src/CbcBranchingObject.hpp,	hpp, 524
	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveFractional.
512 /home/tod/COIN/trunk/Che/ara/CheClique han 513	hpp, 524
/home/ted/COIN/trunk/Cbc/src/CbcClique.hpp, 513 /home/ted/COIN/trunk/Cbc/src/CbcCompare.hpp, 513	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveGuided hpp, 524
·	• • •
/home/ted/COIN/trunk/Cbc/src/CbcCompareActual.hpp, 513	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveLine- Search.hpp, 525
/home/ted/COIN/trunk/Cbc/src/CbcCompareBase.hpp,	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDivePseudo-
514	Cost.hpp, 525
/home/ted/COIN/trunk/Cbc/src/CbcCompareDefault.hpp,	/home/ted/COIN/trunk/Cbc/src/CbcHeuristicDiveVector-
514	Length.hpp, 525

/home/ted/COIN/trunk/Cbc/src/CbcHeuristicFPump.hpp, 525	/home/ted/COIN/trunk/Cbc/src/OsiCbc/OsiCbcSolver- Interface.hpp, 546
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicGreedy.hpp, 526	/home/ted/COIN/trunk/Cbc/src/config_cbc_default.h, 54-/home/ted/COIN/trunk/Cbc/src/config_default.h, 545
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicLocal.hpp,	<u> </u>
526	A
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicPivotAndFix	ALGORITHM
hpp, 526	CbcOsiParam, 343
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicRENS.hpp,	ALLOWABLEGAP
527	CbcCbcParam, 51
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicRINS.hpp,	ALLSLACK
527	CbcOsiParam, 343
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicRandRound	AUTOSCALE
hpp, 526	CbcOsiParam, 343
/home/ted/COIN/trunk/Cbc/src/CbcHeuristicVND.hpp, 527	absoluteIncrement
/home/ted/COIN/trunk/Cbc/src/CbcLinked.hpp, 527	CbcHeuristicFPump, 196
/home/ted/COIN/trunk/Cbc/src/CbcMessage.hpp, 529	absoluteIncrement_
/home/ted/COIN/trunk/Cbc/src/CbcMipStartIO.hpp, 531	CbcHeuristicFPump, 199
/home/ted/COIN/trunk/Cbc/src/CbcModel.hpp, 531	accumulate
/home/ted/COIN/trunk/Cbc/src/CbcNWay.hpp, 533	CbcHeuristicFPump, 198
/home/ted/COIN/trunk/Cbc/src/CbcNode.hpp, 533	accumulate_
/home/ted/COIN/trunk/Cbc/src/CbcNodeInfo.hpp, 533	CbcHeuristicFPump, 200
/home/ted/COIN/trunk/Cbc/src/CbcObject.hpp, 533	action_
/home/ted/COIN/trunk/Cbc/src/CbcObjectUpdateData	CbcGenCtlBlk::djFixCtl_struct, 440
hpp, 534	active
/home/ted/COIN/trunk/Cbc/src/CbcParam.hpp, 534	CbcNode, 317
/home/ted/COIN/trunk/Cbc/src/CbcPartialNodeInfo.hpp,	active_
538	CbcNodeInfo, 326
/home/ted/COIN/trunk/Cbc/src/CbcSOS.hpp, 542	addCuts
/home/ted/COIN/trunk/Cbc/src/CbcSimpleInteger.hpp,	CbcEventHandler, 101
538	addBiLinearObjects
/home/ted/COIN/trunk/Cbc/src/CbcSimpleIntegerDynamic-	OsiUsesBiLinear, 503
PseudoCost.hpp, 539	addBoundModifier
/home/ted/COIN/trunk/Cbc/src/CbcSimpleIntegerPseudo-	OsiLinkedBound, 480
Cost.hpp, 540	OsiSolverLink, 495
/home/ted/COIN/trunk/Cbc/src/CbcSolver.hpp, 540	addBranchingInformation
/home/ted/COIN/trunk/Cbc/src/CbcSolverAnalyze.hpp,	CbcTree, 420
541	addCbcCbcParams
/home/ted/COIN/trunk/Cbc/src/CbcSolverExpandKnapsack	
hpp, 541	addCbcGenParams
/home/ted/COIN/trunk/Cbc/src/CbcSolverHeuristics.hpp,	CbcGenParamUtils, 21
542	addCbcOsiParams
/home/ted/COIN/trunk/Cbc/src/CbcStatistics.hpp, 542	CbcOsiParamUtils, 22
/home/ted/COIN/trunk/Cbc/src/CbcStrategy.hpp, 543	addCol
/home/ted/COIN/trunk/Cbc/src/CbcSubProblem.hpp, 543	OsiCbcSolverInterface, 469
/home/ted/COIN/trunk/Cbc/src/CbcThread.hpp, 543	addCols
/home/ted/COIN/trunk/Cbc/src/CbcTree.hpp, 543	OsiCbcSolverInterface, 469
/home/ted/COIN/trunk/Cbc/src/CbcTreeLocal.hpp, 544	addCutGenerator
/home/ted/COIN/trunk/Cbc/src/Cbc_C_Interface.h, 504	CbcModel, 296
/home/ted/COIN/trunk/Cbc/src/Cbc_ampl.h, 504	CbcSolver, 387
/home/ted/COIN/trunk/Cbc/src/ClpAmplObjective.hpp,	addCutlfNotDuplicate
544	CbcRowCuts, 360
/home/ted/COIN/trunk/Cbc/src/ClpConstraintAmpl.hpp,	addCutlfNotDuplicateWhenGreedy
544	CbcRowCuts, 360
· · ·	223, 1011 2410, 200

addCuts	CbcHeuristicGreedyCover, 203
CbcModel, 306	CbcHeuristicGreedyEquality, 206
CbcNodeInfo, 323	CbcHeuristicGreedySOS, 209
CbcRowCuts, 360	algorithm_
addCuts1	CbcFathomDynamicProgramming, 110
CbcModel, 306	CbcHeuristicGreedyCover, 203
addExtraRow	CbcHeuristicGreedyEquality, 206
OsiBiLinear, 449	CbcHeuristicGreedySOS, 209
addHelp	allActivated
CbcParam, 350	CbcNodeInfo, 325
addHeuristic	allBranchesGone
CbcHeuristicJustOne, 212	CbcNodeInfo, 322
CbcModel, 297	allDynamic
AddIntegers	CbcModel, 310
CbcModel, 275	allowImportErrors_
addObjects	CbcGenCtlBlk, 135
CbcModel, 276	alternateTest
addRow	CbcCompare, 61
OsiCbcSolverInterface, 469	CbcCompareBase, 64
addRows	alwaysCreate_
OsiCbcSolverInterface, 469	CbcBranchToFixLots, 50
addStatistics	ampl_info, 22
CbcCutGenerator, 89	arguments, 26
addTighterConstraints	branchDirection, 25
OsiSolverLink, 496	buffer, 26
addToSumDownChange	columnLower, 24
CbcSimpleIntegerDynamicPseudoCost, 374	columnStatus, 25
addToSumDownCost	columnUpper, 24
CbcSimpleIntegerDynamicPseudoCost, 374	cut, 26
addToSumDownDecrease	direction, 24
CbcSimpleIntegerDynamicPseudoCost, 375	dualSolution, 25
addToSumUpChange	elements, 25
CbcSimpleIntegerDynamicPseudoCost, 375	logLevel, 26
addToSumUpCost	nonLinear, 26
CbcSimpleIntegerDynamicPseudoCost, 374	numberArguments, 24
addToSumUpDecrease	numberBinary, 24
CbcSimpleIntegerDynamicPseudoCost, 375	numberColumns, 23
addUpdateInformation	numberElements, 24
CbcModel, 274	numberIntegers, 24
addUserFunction	numberRows, 23
CbcSolver, 387	numberSos, 24
addedCuts	objValue, 24
CbcModel, 308	objective, 24
adjustHeuristics	offset, 24
CbcModel, 307	primalSolution, 25
affinity	priorities, 25
CbcHeuristicDW, 188	problemStatus, 24
afterHeuristic	pseudoDown, 25
CbcEventHandler, 101	pseudoUp, 25
afterKnapsack	rowLower, 24
CbcSolverExpandKnapsack.hpp, 541	rowStatus, 25
afterNodeNumber_	rowUpper, 24
CbcCompareDefault, 69	rows, 25
algorithm	sosIndices, 26

sosPriority, 25	attempts_
sosReference, 26	CbcHeuristicCrossover, 157
sosStart, 25	avgDistance
sosType, 25	CbcHeuristicNode, 218
special, 26	
starts, 25	В
ampl_obj_prec	BAB
Cbc_ampl.h, 504	CbcGenParam, 141
analyze	BACAbandon
CbcNode, 315	CbcGenCtlBlk, 128
CbcSolver, 387	BACFinish
CbcSolverAnalyze.hpp, 541	CbcGenCtlBlk, 128
analyzeObjective	BACInvalid
CbcModel, 275	CbcGenCtlBlk, 128
analyzeObjects	BACNotRun
OsiSolverLink, 496	CbcGenCtlBlk, 128
answerSolver	BACStop
CbcGenCtlBlk::babState_struct, 27	CbcGenCtlBlk, 128
append	BACUser
CbcHeuristicNodeList, 218	CbcGenCtlBlk, 128
CbcParam, 350	BACmFinish
applyBounds	CbcGenCtlBlk, 129
CbcFullNodeInfo, 120	BACmGap
CbcNodeInfo, 322	CbcGenCtlBlk, 129
CbcPartialNodeInfo, 355	BACmInfeas
applyColCut	CbcGenCtlBlk, 129
OsiCbcSolverInterface, 473	BACmInvalid
applyConsequence	CbcGenCtlBlk, 129
CbcNWay, 328	BACmNodeLimit
applyRowCut	CbcGenCtlBlk, 129
OsiCbcSolverInterface, 473	BACmOther
applyRowCuts	CbcGenCtlBlk, 129
OsiCbcSolverInterface, 469	BACmSolnLimit
applyToModel	CbcGenCtlBlk, 129
CbcFullNodeInfo, 120	BACmTimeLimit
CbcNodeInfo, 321	CbcGenCtlBlk, 129
CbcPartialNodeInfo, 355	BACmUbnd
applyToSolver	CbcGenCtlBlk, 129
CbcConsequence, 74	BACmUser
CbcFixVariable, 115	CbcGenCtlBlk, 129
approximateSolution	BACWBAC
CbcLinked.hpp, 528	CbcGenCtlBlk, 129
arguments	BACwBareRoot
ampl_info, 26	CbcGenCtlBlk, 129
artificialCost	BACWIPP
	CbcGenCtlBlk, 129
CbcHeuristicFPump, 197	BACWIPPRelax
artificialCost_	
CbcHeuristicFPump, 200	CbcGenCtlBlk, 129
assignProblem	BACwInvalid
OsiCbcSolverInterface, 470	CbcGenCtlBlk, 129
assignSolver	BACwNotStarted
CbcModel, 302	CbcGenCtlBlk, 129
atSolution	BARRIER
CbcCutGenerator, 85	CbcOsiParam, 343

BARRIERSCALE CbCoSiParam, 343 BASISIN CbCoSiParam, 343 BASISOUT CbCoSiParam, 344 BASISOUT CbCoSiParam, 345 BPCost CbCGenCitBik, 127 BPEXI CbCGenCitBik, 128 BPOII CbCGenCitBik, 128 BPOII CbCGenCitBik, 128 BACMinor CbCGenCitBik, 128 BACMinor CbCGenCitBik, 128 BACMinor CbCGenCitBik, 128 BACMinor CbCGenCitBik, 129 BACMore CbCGenCitBik, 129 BACMore CbCGenCitBik, 129 BACMore CbCGenCitBik, 127 CbCGenCitBik, 128 CbCGenCitBik, 127 CbCGenCitBik, 128 CbCGenCitBik, 127 CbCGenCitBik, 128 CbCGenCitBik, 129 Data CbCGenCitBik, 127 CbCGenCitBik, 127 CbCGenCitBik, 127 CbCGenCitBik, 128 CbCGenCitBik, 127 CbCGenCitBik, 128 CbCGenCitBik, 127 CbCGenCitBik, 128 CbCGenCitBik, 129 C		
BASISIN CbcOsiParam, 343 BASISOUT CbcOsiParam, 343 BIASILU CbcOsiParam, 343 BPCost CbcGenCtiBlk, 127 BPExt CbcGenCtiBlk, 128 BPOff CbcGenCtiBlk, 127 CbcGenCtiBlk, 128 BPOff CbcGenCtiBlk, 128 BACMajro CbcGenCtiBlk, 128 BACMajro CbcGenCtiBlk, 128 BACMalror CbcGenCtiBlk, 128 BACMinor CbcGenCtiBlk, 128 BACMolinor CbcGenCtiBlk, 129 BPControl CbcGenCtiBlk, 129 BbcModel CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicVND, 236 baseSolution CbcHeuristicVND, 236 baseSolution CbcHeuristicVND, 236 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcEventHandler, 101 betAtternate CbcTree, 419 bestBranch CbcBranchDefaultDecision, 34 CbcBranchingObject, 78 CbcBranchingObject, 59 CbcCutBranchingObject, 59 CbcCutBranchingObject, 59 CbcCutBranchingObject, 78 CbcBranchDefaultDecision, 34 CbcBranchingObject, 59 CbcCutBranchingObject, 78 CbcBranchingObject, 78 CbcCutBranchingObject, 59 CbcCutBranchingObject, 59 CbcCutBranchingObject, 78 CbcBranchDefaultDecision, 34 CbcBranchingObject, 59 CbcCutBranchingObject, 59	BARRIERSCALE	CbcTree, 418
CbcOsiParam, 343 BASISOUT CbcOsiParam, 343 BIASLU CbcOsiParam, 343 BPCost CbcGenCtiBlk, 127 BPExt CbcGenCtiBlk, 128 BPOff CbcGenCtiBlk, 127 BPOrder CbcGenCtiBlk, 128 BACMlor CbcGenCtiBlk, 128 CbcGenCtiBlk, 128 CbcGenCtiBlk, 128 CbcGenCtiBlk, 128 CbcGenCtiBlk, 128 CbcGenCtiBlk, 129 CbcGenCtiBlk, 129 CbcGenCtiBlk, 127 CbbCGenCtiBlk, 137 babModel CbcSchover, 388 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 108 back CbcHauristicVND, 235 baseSolution CbcHeuristicVND, 235 baseSolution CbcHeuristicVND, 236 basisDiff CbcPartialNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 356 bestSolution CbcEventHandler, 101 betorEsolution2 CbcEventHandler, 101 betorEsolution2 CbcEventHandler, 101 bestBranch CbcBranchDefaultDecision, 34 CbcBranchingObject, 78 CbcCutBranchingObject, 59 CbcCutBranchingObject, 59 CbcCutBranchingObject, 59 CbcCutBranchingObject, 98		•
BASISOUT CbCoSiParam, 343 BIASLU CbCoSiParam, 343 BPCost CbcGenCtiBlk, 127 BPExt CbcGenCtiBlk, 128 BPOrlf CbcGenCtiBlk, 127 BPOrder CbcGenCtiBlk, 128 BACMiror CbcGenCtiBlk, 128 BACMiror CbcGenCtiBlk, 128 BACMiror CbcGenCtiBlk, 128 CbcGenCtiBlk, 128 BACMiror CbcGenCtiBlk, 128 BACMiror CbcGenCtiBlk, 128 BACMiror CbcGenCtiBlk, 128 CbcGenCtiBlk, 128 BACMiror CbcGenCtiBlk, 128 BACMiror CbcGenCtiBlk, 128 BACMiror CbcGenCtiBlk, 128 BACMiror CbcGenCtiBlk, 129 BPControl CbcGenCtiBlk, 129 BPControl CbcGenCtiBlk, 129 BPControl CbcGenCtiBlk, 129 CbcGenCtiBlk, 137 bab_ CbcGenCtiBlk, 137 bab_ CbcGenCtiBlk, 137 babModel CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDVN, 187 CbcHeuristicDVND, 236 baseSolution CbcHeuristicDVND, 236 baseSolution CbcHeuristicVND, 236 basis_ CbcPartialNodeInfo, 356 betoreSolution1 CbcEventHandler, 101 betofree, 419 bestBranch CbcBranchDecision, 34 CbcBranchDecision, 34 CbcBranchDecision, 35 CbcFathomDplc, 159 CbcCutBranchingObject, 78 CbcBranchDgelet, 44 CbcBranchingObject, 79 CbcCutBranchingObject, 79 CbcCutBranchingObject, 79 CbcCutBranchingObject, 79 CbcCutBranchingObject, 79 CbcCutBranchingObject, 78 CbcCutBranchingObject, 79 CbcCutBranchingObject, 78 CbcCutBranchingObject, 79 CbcCutBranchingObject, 78 CbcCutBranchingObject, 79 CbcCutBranchingObject, 78 CbcCutBranchingObject, 78 CbcCutBranchingObject, 78 CbcCutBranchingObject, 78 CbcCutBranchingObject, 78 CbcCutBranchingObject, 79 CbcCutBranchingObject, 79 CbcCutBranchingObject, 79 CbcCutBranchingObject, 78 CbcCutBranchingObject, 78 CbcCutBranchingObject, 79 CbcCutBranchingObject, 78 CbcDurmirePseudCotostBranchingObject, 98		
BIASLU CbcOsiParam, 343 BPCost CbcGenCtiBik, 127 BPExt CbcGenCtiBik, 128 BPOff CbcGenCtiBik, 127 BPOrder CbcGenCtiBik, 128 BACMajor CbcGenCtiBik, 128 BACMinor CbcGenCtiBik, 128 BACMinor CbcGenCtiBik, 128 BACMinor CbcGenCtiBik, 128 BACMinor CbcGenCtiBik, 129 BPControl CbcGenCtiBik, 127 bab_ CbcGenCtiBik, 127 bab_ CbcGenCtiBik, 137 babModel CbcGentristicDW, 187 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 108 back CbcHeuristicDW, 187 baseSolution CbcHeuristicDW, 187 baseSolution CbcHeuristicDW, 187 baseSolution CbcHeuristicDND, 235 baseSolution CbcHeuristicDND, 236 basis CbcFathomDynamicProgramming, 109 backwardRow CbcHeuristicDND, 236 baseSolution Cb	•	•
BIASLU CbcOsiParam, 343 BPCost CbcGenCtiBik, 127 BPExt CbcGenCtiBik, 128 BPOff CbcGenCtiBik, 127 BPOrder CbcGenCtiBik, 128 BACMajor CbcGenCtiBik, 128 BACMajor CbcGenCtiBik, 128 BACMijor CbcGenCtiBik, 128 BACMijor CbcGenCtiBik, 128 BACMijor CbcGenCtiBik, 128 BACMinor CbcGenCtiBik, 128 BACMinor CbcGenCtiBik, 128 BACMinor CbcGenCtiBik, 128 BACMinor CbcGenCtiBik, 129 BPControl CbcGenCtiBik, 129 BPControl CbcGenCtiBik, 127 bab_ CbcGenCtiBik, 137 babModel CbcSolverI, 187 babModel CbcSolverI, 187 babModel CbcSolverI, 188 back CbcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 109 backwardRow, CbcHeuristicDW, 187 baseSolution CbcHeuristicDW, 187 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 356 betoreSolution CbcEventHandler, 101 betAlternate CbCTree, 419 bestBranch CbcBranchDefaultDecision, 34 CbcBranchDefaultDecision, 34 CbcBranchDefaultDecision, 34 CbcBranchDefaultDecision, 34 CbcBranchDefaultDecision, 35 CbcGutBranchpOpiect, 78 OsiBiLinear, 446 OsiBiLinear, 448 boundType OsiBiLinear, 448 boundType OsiBiLinear, 448 CbcCiqueBranchingObject, 59 CbcCultBranchingObject, 59 CbcCultBranchingObject, 59 CbcCultBranchingObject, 94 CbcBranchDefaultDecision, 34 CbcBranchDefaultDecision, 34 CbcBranchDefaultDecision, 34 CbcBranchDefaultDecision, 34 CbcBranchDefaultDecision, 34 CbcBranchDefaultDecision, 35 CbcGultBranchingObject, 45 CbcCultBranchingObject, 59 CbcCultBranchingObject, 94 CbcCupramicPseudOcoatBranchingObject, 94 CbcDynamicPseudOcoatBranchingObject, 94 CbcDynamicPseudOcoatBranchingObject, 94 CbcDynamicPseudOcoatBranchingObject, 94		•
CbcOsiParam, 343 BPCost CbcGenCtiBlk, 127 BPExt CbcGenCtiBlk, 128 BPOff CbcGenCtiBlk, 127 BPExt CbcGenCtiBlk, 127 BPCort CbcGenCtiBlk, 127 BPCort CbcGenCtiBlk, 127 BPCort CbcGenCtiBlk, 128 BACMajor CbcGenCtiBlk, 128 BACMinor CbcGenCtiBlk, 128 BACMinor CbcGenCtiBlk, 128 BACMinor CbcGenCtiBlk, 128 BACMinor CbcGenCtiBlk, 129 BACMinor CbcGenCtiBlk, 129 BACMore CbcGenCtiBlk, 129 BACMore CbcGenCtiBlk, 129 BACMore CbcGenCtiBlk, 127 bab CbcGenCtiBlk, 127 bab CbcGenCtiBlk, 137 babModel CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 109 backwardRow CbcHeuristicPW, 187 baseSolution CbcHeuristicVND, 235 baseSolution CbcHeuristicVND, 236 basis CbcFattialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 356 beforeSolution1 CbcCventHandler, 101 bestAternate CbcFatenCDecision, 34 CbcBranchDecision, 35 CbcBranchDecision, 36 CbcBranchDecision, 36 CbcBranchDecision, 36 CbcBranchDynamicProgramming, 109 bestBranch CbcBranchDecision, 36 CbcCuptranchingObject, 45 CbcCuptranchingObject, 45 CbcCuptranchingObject, 59 CbcCuptranchingObject, 59 CbcCuptranchingObject, 59 CbcCuptranchingObject, 94 CbcDynamicPseudOcostBranchingObject, 94 CbcDynamicPseudOcostBranchingObject, 94 CbcDynamicPseudOcostBranchingObject, 94 CbcDynamicPseudOcostBranchingObject, 94 CbcDynamicPseudOcostBranchingObject, 94		-
BPCost CbcGenCtlBlk, 127 BPExt CbcGenCtlBlk, 128 BPOff CbcGenCtlBlk, 127 BPOrder CbcGenCtlBlk, 128 BACMajor CbcGenCtlBlk, 128 BACMajor CbcGenCtlBlk, 128 BACMilor CbcGenCtlBlk, 128 BACWhere CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 127 Bab CbcGenCtlBlk, 137 babModel CbcBranchDefaultDecision, 37 CbcBranchDefaultDecision, 39 biLinearPriority CbcSolverLink, 497 biLinearPriority CbsGenCtlBlk, 199 DackwardRow CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 baseSolution CbcHeuristicVND, 235 baseSolution CbcHeuristicVND, 235 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 betoffesOlution2 CbcEventHandler, 101 betoffesOlution2 CbcEventHandler, 101 betoffesOlution2 CbcBranchDefaultDecision, 37 CbcBranchingObject, 44 CbcCiqueBranchingObject, 59 CbcDynamicPseudOcostBranchingObject, 94		
CbcGenCtlBlk, 127 BPExt CbcGenCtlBlk, 128 BPOff CbcGenCtlBlk, 127 BPOrder CbcGenCtlBlk, 128 BACMajor CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 137 babModel CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 baseSolution_ CbcHeuristicVND, 236 basis CbcFullNodeInfo, 355 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 bestAlternate CbcBranchDecision, 34 CbcBranchDeject, 453 OsilLinear, 448 boundType OsiBiLinear, 448 boundType OsiBiLinear, 448 boundType OsiBiLinear, 448 boundType OsiBiLinear, 450 branch CbcBranchDjet, 59 CbcCullBranchingObject, 59 CbcCullBranchingObject, 59 CbcCullBranchingObject, 59 CbcCullBranchingObject, 94 CbcBranchDefaultDecision, 37 CbcBranchDget, 94 CbcBranchDget, 94 CbcCullBranchingObject, 94 CbcDynamicPseudOcostBranchingObject, 98		
BPExt CbcGenCtlBlk, 128 BPOff CbcGenCtlBlk, 127 BPOrder CbcGenCtlBlk, 128 BACMajor CbcGenCtlBlk, 128 BACMinor CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 127 bab CbcGenCtlBlk, 127 bab CbcGenCtlBlk, 137 babModel CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution CbcHeuristicDW, 187 CbcHeuristicDW, 187 baseSolution CbcHeuristicDW, 236 basis_ CbcHulNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 basisDiff_ CbcPartialNodeInfo, 355 basisDiff_ CbcPartialNodeInfo, 355 basisDiff_ CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 bestAlternate CbcBranchDecision, 34 CbcBranchDecision, 34 CbcBranchDecision, 35 CbcBranchDecision, 36 CbcBranchDecision, 37 CbcBranchDecision, 36 CbcBranchDecision, 37 CbcBranchOut, 31 CbcCutBranchingObject, 453 OsiBl.inear, 446 OsiBl.inear, 448 DoundType OsiBl.inear, 448 DoundType OsiBl.inear, 448 CbcCirqueBranchingObject, 78 CbcBranchDecision, 34 CbcBranchDefaultDecision, 37		_
CbcGenCtlBlk, 128 BPOff CbcGenCtlBlk, 127 BPOrder CbcGenCtlBlk, 128 BACMajor CbcGenCtlBlk, 128 BACMinor CbcGenCtlBlk, 128 BACMinor CbcGenCtlBlk, 128 BACMinor CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 127 bab CbcGenCtlBlk, 137 babModel CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 109 backwardRow CbcHeuristicDW, 187 baseSolution CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 236 basis CbcFullNodeInfo, 355 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 beforeSolution2 CbcBranchDecision, 34 CbcBranchDecision, 37 CbcDummyBranchingObject, 78 CbcCutBranchingObject, 78 CbcCutBranchingObje		
BPOff CbcGenCtlBlk, 127 BPOrder CbcGenCtlBlk, 128 BACMajor CbcGenCtlBlk, 128 BACMinor CbcGenCtlBlk, 128 BACWinor CbcGenCtlBlk, 128 BACWinor CbcGenCtlBlk, 128 BACWinor CbcGenCtlBlk, 129 BACWinor CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 127 bab CbcGenCtlBlk, 127 bab CbcGenCtlBlk, 137 babModel CbcSolver, 388 back CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 baseSolution CbcHeuristicVND, 235 baseSolution CbcHeuristicVND, 236 basis_ CbcPartialNodeInfo, 355 basiDiff CbcPartialNodeInfo, 355 basiDiff CbcPartialNodeInfo, 356 beforeSolution2 CbcEventHandler, 101 bestAlternate CbcBranchDecision, 34 CbcBranchingObject, 44 CbcBranchDecision, 34 CbcBranchingObject, 78 CbcCutBranchingObject, 78 CbcBranchingObject, 78 CbcBranchingObject, 78 CbcBranchingObject, 78 CbcCutBranchingObject, 78 CbcCutBranchingObject, 78 CbcBranchingObject, 78 CbcCutBranchingObject, 78 CbcCutBranchingObject, 78 CbcDummyBranchingObject, 78 CbcCutBranchingObject, 78 CbcCutBranchingObj		
CbcGenCtlBlk, 127 BPOrder CbcGenCtlBlk, 128 BACMajor CbcGenCtlBlk, 128 BACMinor CbcGenCtlBlk, 128 BACWhere CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 127 CbcGenCtlBlk, 137 babModel CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 109 backwardRow CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 baseSolution CbcHeuristicVND, 236 basis CbcFatllNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 betoreSolution2 CbcEventHandler, 101 betStAlternate CbcBranchDecision, 34 CbcBranchDejoet, 44 CbcBranchingObject, 44 CbcBranchingObject, 78 CbcCbculmymbranchingObject, 59 CbcCbulmymbranchingObject, 98 CbcCparnachingObject, 78 CbcCbulmymbranchingObject, 98 CbcCbulmymbranchingObject, 98 CbcCbulmymbranchingObject, 98 CbcCbulmymbranchingObject, 98	•	-
BPOrder CbcGenCtiBlk, 128 BACMajor CbcGenCtiBlk, 128 BACMinor CbcGenCtiBlk, 128 BACWhere CbcGenCtiBlk, 129 BPControl CbcGenCtiBlk, 127 bab_ CbcGenCtiBlk, 137 babModel CbcGentIBlk, 137 babModel CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicVND, 235 baseSolution_ CbcHeuristicVND, 236 basis_ CbcFullNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 355 beforeSolution1 CbcCevntHandler, 101 betStAlternate CbcBranchDecision, 34 CbcBranchDeriautiDecision, 39 biLinearPriority_ OsiSolverLink, 497 biLinearPriority_ CbcLetsize, 251 boundBranch CbcBranchDeriautiDecision, 31 CbcCutBranchingObject, 78 OsiBlLinear, 446 OsiBlLinear, 446 OsiBlLinear, 446 OsiBlLinear, 448 boundType_ OsiBlLinear, 448 boundType_ OsiBlLinear, 448 boundType_ CbcBranchDecision, 34 CbcBranchDecision, 37 CbcCbulBranchingObject, 78 CbcCbulBranchingObject, 79 CbcCbulBranchingObject, 94 CbcDynamicPseudoCostBranchingObject, 94 CbcDcDynamicPseudoCostBranchingObject, 98		·
CbcGenCtlBlk, 128 BACMajor CbcGenCtlBlk, 128 BACMinor CbcGenCtlBlk, 128 BACWhere CbcGenCtlBlk, 129 BACWhere CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 127 bab CbcGenCtlBlk, 137 babModel CbcGenCtlBlk, 137 CbcGenCtlBlk, 137 babModel CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution_ CbcHeuristicDW, 187 CbcHeuristicDW, 187 CbcHeuristicDW, 235 baseSolution_ CbcHeuristicVND, 235 basis_ CbcFullNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 basis_ CbcPartialNodeInfo, 355 beforeSolution1 CbcEventHandler, 101 bestAlternate CbcBranchDecision, 34 CbcBranchipogbject, 44 CbcBranchDecision, 34 CbcBranchipogbject, 44 CbcCbranchDecision, 34 CbcBranchipogbject, 78 CbcBranchipogbject, 78 CsiBiLinear, 446 CbcBranchDecision, 34 CbcBranchDecision, 34 CbcBranchDecision, 35 CbcCutlBranchingObject, 44 CbcCliqueBranchingObject, 78 CbcBranchDecision, 34 CbcBranchDecision, 34 CbcBranchDecision, 37 CbcCbummyBranchingObject, 78 CbcCbcutBranchingObject, 78 CbcCbcutBranchingObject, 44 CbcCliqueBranchingObject, 79 CbcCbcutBranchingObject, 78 CbcCbcutBranchingObject, 78 CbcCbcummyBranchingObject, 78 CbcCbcummyBranchingObject, 79 CbcCbcummyBranchingObject, 98 CbcCbummyBranchingObject, 98	·	
BACMajor CbcGenCtlBlk, 128 BACMinor CbcGenCtlBlk, 128 BACWhere CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 127 bab CbcGenCtlBlk, 137 babModel CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 109 backwardRow CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 baseSolution CbcHeuristicVND, 236 basisDilf CbcPartialNodeInfo, 355 basisDilf CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 bestAlternate CbcBranchDecision, 34 CbcBranchDig, 37 CbcBranchDecision, 36 CbcBranchDecision CbcEventHandler, 101 bestAlternate CbcBranchDecision, 34 CbcBranchDig, 37 CbcCbleuristicOW, 187 CbcBranchDecision CbcEventHandler, 101 bestAlternate CbcBranchDecision, 34 CbcBranchDecision, 34 CbcBranchDigolect, 78 CbcCutBranchingObject, 44 CbcBranchDecision, 34 CbcBranchDecision, 34 CbcBranchDecision, 34 CbcBranchDecision, 37 CbcCbcDymamicPseudoCostBranchingObject, 98 CbcDummyBranchingObject, 98 CbcDummyBranchingObject, 98		
CbcGenCtlBlk, 128 BACMinor CbcGenCtlBlk, 128 BACWhere CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 127 bab_ CbcGenCtlBlk, 127 bab_ CbcGenCtlBlk, 137 babModel CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution_ CbcHeuristicVND, 235 baseSolution CbcHeuristicVND, 236 basis_ CbcFatlINlodeInfo, 121 basisDiff CbcPartialNodeInfo, 356 beforeSolution1 CbcPartialNodeInfo, 356 beforeSolution2 CbcEventHandler, 101 bestAlternate CbcTree, 419 bestBranch CbcBranchDecision, 34 CbcBranchDecision, 37 CbcBcunmyBranchingObject, 98 CbcCugnamicProgramming, 109 bestBranch CbcBranchDecision, 34 CbcBranchDecision, 37 CbcBranchDefaultDecision, 37 CbcBcvpartialNodelofo, 356 CbcBranchDecision, 34 CbcBranchDecision, 34 CbcBranchDecision, 37 CbcBranchDefaultDecision, 37 CbcBranchDefocosoltpicn, 98		
BACMinor CbcGenCtlBlk, 128 CbcGenCtlBlk, 129 CbcGenCtlBlk, 129 CbcGenCtlBlk, 127 CbcGenCtlBlk, 127 CbcGenCtlBlk, 127 CbcGenCtlBlk, 137 CbcGenCtlBlk, 137 CbcGenCtlBlk, 137 CbcGenCtlBlk, 137 CbcGenCtlBlk, 137 CbcGenCtlBlk, 137 CbcBranchDefaultDecision, 34 CbcBranchDefaultDecision, 39 biLinearPriority CbcSolver, 388 Dack CbcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 DaseSolution CbcHeuristicVND, 235 DaseSolution_ CbcHeuristicVND, 236 CbcFatlNodeInfo, 121 DasisDiff CbcPartialNodeInfo, 355 DasisDiff_ CbcPartialNodeInfo, 356 DeforeSolution1 CbcEventHandler, 101 DeforeSolution2 CbcEventHandler, 101 DestAtlernate CbcTrae, 419 DestBranch CbcBranchDecision, 34 CbcBranchDecision, 34 CbcBranchDecision, 35 CbcBranchDecision, 34 CbcBranchDecision, 37 CbcCbummyBranchingObject, 98 CbcDummyBranchingObject, 98 CbcDummyBranchingObject, 98		
CbcGenCtlBlk, 128 BACWhere CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 127 bab_ CbcGenCtlBlk, 127 bab_ CbcGenCtlBlk, 137 babModel CbcSalver, 388 back CbcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 baseSolution CbcHeuristicVND, 236 basis_ CbcFullNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 356 beforeSolution1 CbcHeuristic CbcEventHandler, 101 bestAlternate CbcTree, 419 bestBranch CbcBranchDecision, 34 CbcDunamicPsecudoCostBranchingObject, 78 CbcCutBranchingObject, 78 CbcCutBranchingObject, 44 CbcCutBranchingObject, 78 CbcCutBranchingObject, 44 CbcCutBranchingObject, 45 CbcCutBranchingObject, 44 CbcClutBranchingObject, 78 CbcBranchOtt, 31 CbcPartialNodeInfo, 356		•
BACWhere CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 127 bab_ CbcGenCtlBlk, 137 bab_ CbcGenCtlBlk, 137 babModel CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 basis_ CbcFullNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 basisDiff CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 bestAlternate CbcEventHandler, 101 bestAlternate CbcBranchDecision, 34 CbcBranchDecision, 34 CbcBranchDecision, 34 CbcBranchDquamicPrograms CbcBranchDquamicProgramming, 109 biLinearPriority_ OsiSolverLink, 497 biLinearPriority_ OsiSolverLink, 500 binVarIndex_ DosiSolverLink, 500 binVarIndex_ CbcHeuristicDive, 166 bitPattern_ CbcHeuristicDive, 166 bitPattern_ CbcHeuristicDive, 166 bitPattern_ CbcHeuristicVND, 235 boundTyne CbcLotsize, 251 boundBranch CbcBranchDquamicProgramming, 110 bound CbcCutBranchingObject, 78 OsiBiLinear, 446 OsiBiLinear, 446 OsiBiLinear, 448 boundType OsiBiLinear, 448 boundType OsiBiLinear, 448 CbcBranchingObject, 44 CbcBranchingObject, 59 CbcCutBranchingObject, 59 CbcCutBranchingObject, 59 CbcCutBranchingObject, 59 CbcCutBranchingObject, 59 CbcCutBranchingObject, 78 CbcCutBranchingObject, 59		_
CbcGenCtlBlk, 129 BPControl CbcGenCtlBlk, 127 bab	•	
BPControl CbcGenCtlBlk, 127 CbcGenCtlBlk, 137 CbcGenCtlBlk, 137 CbcGenCtlBlk, 137 CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcBranchDynamicDecision, 39 biLinearPriority CbcSolver, 388 Dack CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 CbcHeuristicVND, 235 baseSolution CbcHeuristicVND, 236 basis_ CbcFullNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 basisDiff_ CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 bestAlternate CbcEventHandler, 101 bestAlternate CbcBranchDecision, 34 CbcBranchingObject, 44 CbcBranchingObject, 59 CbcDummyBranchingObject, 59 CbcDummyBranchingObject, 59 CbcDummyBranchingObject, 59 CbcDummyBranchingObject, 59 CbcDummyBranchingObject, 59 CbcDummyBranchingObject, 98 CbcDummyBranchingObject, 98		
CbcGenCtlBlk, 127 CbcGenCtlBlk, 137 CbcGenCtlBlk, 137 CbcCobranchDefaultDecision, 37 CbcCobranchDynamicDecision, 39 babModel CbcFathomDynamicProgramming, 108 back CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 baseSolution CbcHeuristicVND, 236 basis_ CbcFatllNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 basisDiff_ CbcPartialNodeInfo, 356 beforeSolution1 CbcDeratialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 bestAlternate CbcTree, 419 bestBranch CbcBranchDecision, 34 CbcBranchingObject, 78 CbcBranchingObject, 44 CbcCutBranchingObject, 44 CbcCutBranchingObject, 44 CbcCutBranchingObject, 44 CbcCutBranchingObject, 44 CbcCutBranchingObject, 45 OsiBiLinear, 448 boundType OsiBiLinear, 448 boundType OsiBiLinear, 448 CbcCutBranchingObject, 44 CbcCutBranchingObject, 44 CbcCutBranchingObject, 44 CbcCutBranchingObject, 78 CbcBranchDecision, 34 CbcCutBranchingObject, 78 CbcCutBranchingObject, 78 CbcDummyBranchingObject, 78 CbcDummyBranchingObject, 78 CbcDummyBranchingObject, 94 CbcDummyBranchingObject, 98		
bab_ CbcGenCtlBlk, 137 CbcBranchDefaultDecision, 37 CbcBranchDynamicDecision, 39 babModel biLinearPriority OsiSolverLink, 497 biLinearPriority_ OsiSolverLink, 497 biLinearPriority_ OsiSolverLink, 500 binVarIndex_ CbcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 109 CbcHeuristicDive, 166 binVarIndex_ CbcHeuristicDW, 187 CbcFathomDynamicProgramming, 110 bound CbcHeuristicVND, 235 CbcCHeuristicVND, 235 CbcCHeuristicVND, 236 CbcCHeuristicVND, 236 CbcCHeuristicVND, 236 CbcCutBranchingObject, 78 CbcFathonDynamicProgramming, 110 boundBranch CbcCHeuristicVND, 236 CbcCutBranchingObject, 78 OsiBiLinear, 446 CbcPartialNodeInfo, 355 OsiLink, 477 OsiBiLinearBranchingObject, 453 OsiLink, 477 DasisDiff_ OsiOldLink, 483 boundType DeforeSolution1 OsiBiLinear, 448 boundType CbcEventHandler, 101 boundType OsiBiLinear, 450 branch bestAlternate CbcEventHandler, 101 boundType CbcEventHandler, 101 boundType CbcEventHandler, 101 boundType CbcBranchingObject, 44 CbcBranchDecision, 34 CbcBranchingObject, 78 CbcCutBranchingObject, 98		
babModel biLinearPriority CbcSolver, 388 OsiSolverLink, 497 back ObcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 baseSolution_ CbcHeuristicVND, 236 basis_ CbcFullNodeInfo, 121 basisDiff OsiBiLinear, 446 basisDiff OsiBiLinear, 446 basisDiff OsiBiLinear, 448 beforeSolution1 CbcPartialNodeInfo, 355 beforeSolution1 CbcEventHandler, 101 beforeSolution2 CbcEventHandler, 101 bestAlternate CbcBranchingObject, 44 CbcBranchDecision, 34 CbcBranchDecision, 37 CbcBranchDecision, 37 CbcCutBranchingObject, 78 CbcBranchDecision, 37 CbcCutBranchingObject, 98 CbcCutBranchingObject, 98 CbcCutBranchingObject, 98 CbcBranchDecision, 37 CbcBranchingObject, 98		
babModel CbcSolver, 388 CbcSolver, 388 back CbcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 CbcHeuristicVND, 236 CbcHeuristicVND, 236 CbcFathomDynamicProgramming, 109 basis_ CbcFullNodeInfo, 121 CbcSpartialNodeInfo, 355 CbcPartialNodeInfo, 356 CbcOresSolution CbcEventHandler, 101 CbcEventHandler, 101 CbcStranch CbcTree, 419 CbcBranchDefaultDecision, 37 CbcCultBranchingObject, 98 CbcCultBranchingObject, 98 CbcCultBranchingObject, 98 CbcCultBranchingObject, 44 CbcDranchingObject, 44 CbcDranchingObject, 48 CbcCultBranchingObject, 44 CbcDranchingObject, 44 CbcDranchingObject, 48 CbcDunmyBranchingObject, 98 CbcCultBranchingObject, 98 CbcCultBranchingObject, 98 CbcCultBranchingObject, 98		
back CbcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 baseSolution_ CbcHeuristicVND, 236 basis_ CbcFullNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 basiDiff_ CbcPartialNodeInfo, 356 beforeSolution1 CbcPeuritlandler, 101 bestAlternate CbcEventHandler, 101 bestAlternate CbcBranchDefaultDecision, 34 CbcBranchDefaultDecision, 37 CbcBranchDefaultDecision, 37 CbcBranchDefaultDecision, 37 CbcBranchingObject, 98 CbcCutBranchingObject, 98 CbcCutBranchingObject, 44 CbcDranchingObject, 44 CbcDranchingObject, 44 CbcDranchingObject, 48 CbcDynamicPseudoCostBranchingObject, 98		•
back CbcFathomDynamicProgramming, 108 back_ CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 baseSolution_ CbcHeuristicVND, 236 basis_ CbcFullNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 basisDiff_ CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 bestAlternate CbcTree, 419 bestBranch CbcBranchDefaultDecision, 37 CbcBranchDefaultDecision, 37 CbcBranchDefaultDecision, 37 CbcBranchingObject, 98 CbcDynamicPseudoCostBranchingObject, 98 CbcDynamicPseudoCostBranchingObject, 98 CbcDynamicPseudoCostBranchingObject, 98		
CbcFathomDynamicProgramming, 108 back_		
back_ CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution		•
CbcFathomDynamicProgramming, 109 backwardRow_ CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 baseSolution_ CbcHeuristicVND, 236 basis_ CbcFathomDynamicProgramming, 110 basis_ CbcFathomDynamicProgramming, 110 bound CbcHeuristicVND, 235 cbcHeuristicVND, 236 basis_ CbcHeuristicVND, 236 cbcFullNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 cbcPartialNodeInfo, 355 basisDiff_ CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 beforeSolution2 CbcEventHandler, 101 bestAlternate CbcTree, 419 bestBranch CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcDynamicPseudoCostBranchingObject, 98		
backwardRow CbcHeuristicDW, 187	_	_
CbcHeuristicDW, 187 baseSolution CbcHeuristicVND, 235 baseSolution_ CbcHeuristicVND, 236 baseSolution_ CbcHeuristicVND, 236 basis_ CbcHeuristicVND, 236 basis_ CbcFullNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 basisDiff_ CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 beforeSolution2 CbcEventHandler, 101 bestAlternate CbcTree, 419 bestBranch CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcBundAgramming, 110 bound CbcCutBranchopynamicProgramming, 110 bound CbcBranchDefaultDecision, 37 CbcDummyBranchingObject, 78 CbcCutBranchingObject, 98 CbcDynamicPseudoCostBranchingObject, 98		
baseSolution CbcHeuristicVND, 235 CbcHeuristicVND, 236 CbcHeuristicVND, 236 CbcHeuristicVND, 236 CbcHeuristicVND, 236 CbcFullNodeInfo, 121 CbcFullNodeInfo, 121 CbcPartialNodeInfo, 355 CbcPartialNodeInfo, 355 CbcPartialNodeInfo, 356 CbcPartialNodeInfo, 356 DeforeSolution1 CbcEventHandler, 101 DeforeSolution2 CbcEventHandler, 101 DestAlternate CbcTree, 419 DestBranch CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcDunmyBranchingObject, 98 CbcDynamicPseudoCostBranchingObject, 98		_
CbcHeuristicVND, 235 baseSolution_ CbcHeuristicVND, 236 basis_ CbcFullNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 beforeSolution1 CbcEventHandler, 101 bestAlternate CbcTree, 419 bestBranch CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcBranchCut, 31 CbcBranchCut, 31 CbcCutBranchingObject, 78 CbcBranchingObject, 78 OsiBiLinear, 446 OsiBiLinear, 446 OsiBiLinear, 446 OsiBiLinear, 447 OsiOldLink, 483 CoildLink, 483 CoildLinear, 448 CoilduelBranchingObject, 44 CoilduelBranchingObject, 44 CoilduelBranchingObject, 44 CoilduelBranchingObject, 59 CoilduelBranchingObject, 78 CoildLink, 483 C		
baseSolution		
CbcHeuristicVND, 236 basis		
basis CbcFullNodeInfo, 121 OsiBiLinear, 446 basisDiff OsiBiLinearBranchingObject, 453 CbcPartialNodeInfo, 355 OsiLink, 477 basisDiff_ OsiOldLink, 483 CbcPartialNodeInfo, 356 boundType beforeSolution1 OsiBiLinear, 448 CbcEventHandler, 101 boundType_ beforeSolution2 OsiBiLinear, 450 CbcEventHandler, 101 branch bestAlternate CbcTree, 419 CbcCTree, 419 CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcDynamicPseudoCostBranchingObject, 98	-	
CbcFullNodeInfo, 121 basisDiff CbcPartialNodeInfo, 355 CbcPartialNodeInfo, 355 DsiLink, 477 basisDiff CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 beforeSolution2 CbcEventHandler, 101 bestAlternate CbcTree, 419 bestBranch CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcBultinear, 446 OsiBiLinear, 448 boundType OsiBiLinear, 448 boundType_ OsiBiLinear, 450 branch CbcBranchingObject, 44 CbcCliqueBranchingObject, 59 CbcCutBranchingObject, 78 CbcDummyBranchingObject, 94 CbcDynamicPseudoCostBranchingObject, 98		
basisDiff CbcPartialNodeInfo, 355 OsiLink, 477 basisDiff_ OsiOldLink, 483 CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 beforeSolution2 CbcEventHandler, 101 bestAlternate CbcTree, 419 bestBranch CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcDynamicPseudoCostBranchingObject, 98	_	- ·
CbcPartialNodeInfo, 355 basisDiff_		
basisDiff_ OsiOldLink, 483 CbcPartialNodeInfo, 356 beforeSolution1 OsiBiLinear, 448 CbcEventHandler, 101 beforeSolution2 OsiBiLinear, 450 CbcEventHandler, 101 bestAlternate CbcBranchingObject, 44 CbcTree, 419 bestBranch CbcCutBranchingObject, 78 CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcDynamicPseudoCostBranchingObject, 98		— ·
CbcPartialNodeInfo, 356 beforeSolution1 CbcEventHandler, 101 beforeSolution2 CbcEventHandler, 101 bestAlternate CbcTree, 419 bestBranch CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 beoundType OsiBiLinear, 448 boundType_ OsiBiLinear, 450 boundType_ OsiBiLinear, 450 boundType OsiBiLinear, 448 boundType OsiBiLinear, 448 CbcBranchType OsiBiLinear, 448 CbcBranchingObject, 44 CbcBranchingObject, 44 CbcBranchingObject, 59 CbcCutBranchingObject, 78 CbcDynamicPseudoCostBranchingObject, 98		
beforeSolution1 OsiBiLinear, 448 CbcEventHandler, 101 boundType_ beforeSolution2 OsiBiLinear, 450 CbcEventHandler, 101 branch bestAlternate CbcBranchingObject, 44 CbcTree, 419 CbcCliqueBranchingObject, 59 bestBranch CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcDynamicPseudoCostBranchingObject, 98	-	
CbcEventHandler, 101 beforeSolution2 CbcEventHandler, 101 bestAlternate CbcTree, 419 CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcBynamicPseudoCostBranchingObject, 98 CbcDynamicPseudoCostBranchingObject, 98		
beforeSolution2 OsiBiLinear, 450 CbcEventHandler, 101 branch bestAlternate CbcBranchingObject, 44 CbcTree, 419 CbcCliqueBranchingObject, 59 bestBranch CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcDummyBranchingObject, 94 CbcDynamicPseudoCostBranchingObject, 98		
CbcEventHandler, 101 bestAlternate CbcTree, 419 CbcCliqueBranchingObject, 59 bestBranch CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcDummyBranchingObject, 94 CbcDynamicPseudoCostBranchingObject, 98		
bestAlternate CbcBranchingObject, 44 CbcTree, 419 CbcCliqueBranchingObject, 59 bestBranch CbcBranchDecision, 34 CbcDummyBranchingObject, 78 CbcBranchDefaultDecision, 37 CbcDynamicPseudoCostBranchingObject, 98		
CbcTree, 419 CbcCliqueBranchingObject, 59 bestBranch CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcDynamicPseudoCostBranchingObject, 98		
bestBranch CbcCutBranchingObject, 78 CbcBranchDecision, 34 CbcBranchDefaultDecision, 37 CbcDynamicPseudoCostBranchingObject, 98		- ·
CbcBranchDecision, 34 CbcDummyBranchingObject, 94 CbcBranchDefaultDecision, 37 CbcDynamicPseudoCostBranchingObject, 98		· · · · · · · · · · · · · · · · · · ·
CbcBranchDefaultDecision, 37 CbcDynamicPseudoCostBranchingObject, 98		- ·
bestinode CbcFixingBranchingObject, 112		· · · · · · · · · · · · · · · · · · ·
	Destinode	ObchixingBranchingObject, 112

CbcIntegerBranchingObject, 241	CbcMessage.hpp, 530
CbcIntegerPseudoCostBranchingObject, 244	CBC_DUMMY_END
CbcLongCliqueBranchingObject, 247	CbcMessage.hpp, 530
CbcLotsizeBranchingObject, 253	CBC_END
CbcNode, 315	CbcMessage.hpp, 529
CbcNWayBranchingObject, 331	CBC_END_GOOD
CbcSOSBranchingObject, 396	CbcMessage.hpp, 529
OsiBiLinearBranchingObject, 453	CBC_END_SOLUTION
OsiLinkBranchingObject, 479	CbcMessage.hpp, 529
OsiOldLinkBranchingObject, 484	CBC_END_SUB
branchAndBound	CbcMessage.hpp, 530
CbcModel, 273	CBC_EVENT
OsiCbcSolverInterface, 462	CbcMessage.hpp, 529
branchDirection	CBC_FATHOM_CHANGE
ampl_info, 25	CbcMessage.hpp, 530
branchDirection_	CBC_FPUMP1
CbcSolverUsefulData, 390	CbcMessage.hpp, 530
branched	CBC_FPUMP2
CbcTree, 420	CbcMessage.hpp, 530
branched_	CBC_GAP
CbcTree, 421	CbcMessage.hpp, 530
branchedOn	CBC_GENERAL
CbcNodeInfo, 323	CbcMessage.hpp, 530
branchingMethod	CBC_GENERATOR
CbcModel, 295	CbcMessage.hpp, 530
branchingObject	CBC_HEURISTICS_OFF
CbcNode, 317	CbcMessage.hpp, 530
branchingStrategy	CBC_INFEAS
OsiBiLinear, 448	CbcMessage.hpp, 529
branchingStrategy_	CBC_INTEGERINCREMENT
OsiBiLinear, 450	CbcMessage.hpp, 530
branchingValue_	CBC_ITERATE_STRONG
CbcObjectUpdateData, 341	CbcMessage.hpp, 530
breadthDepth_	CBC_MAXITERS
CbcCompareDefault, 68	CbcMessage.hpp, 529
breakEven	CBC_MAXNODES
CbcSimpleInteger, 366	CbcMessage.hpp, 529
breakEven_	CBC_MAXSOLS
CbcSimpleInteger, 366	CbcMessage.hpp, 529
buffer	CBC_MAXTIME
ampl_info, 26	CbcMessage.hpp, 529
buildCut	CBC_NOINT
CbcldiotBranch, 238	CbcMessage.hpp, 530
buildRowBasis	CBC_NOTFEAS1
CbcFullNodeInfo, 120	CbcMessage.hpp, 530
CbcNodeInfo, 322	CBC_NOTFEAS2
CbcPartialNodeInfo, 355	CbcMessage.hpp, 530
	CBC_NOTFEAS3
C ODG DDANGU	CbcMessage.hpp, 530
CBC_BRANCH	CBC_OTHER_STATS
CbcMessage.hpp, 530	CbcMessage.hpp, 530
CBC_CUTOFF_WARNING1	CBC_OTHER_STATS2
CbcMessage.hpp, 530	CbcMessage.hpp, 530
CBC CUTS STATS	CBC PARAM ACTION BAB

CbcParam.hpp, 538	CbcParam.hpp, 537
CBC_PARAM_ACTION_MIPLIB	CBC_PARAM_STR_PROBINGCUTS
CbcParam.hpp, 538	CbcParam.hpp, 537
CBC_PARAM_DBL_ALLOWABLEGAP	CBC_PARAM_STR_ROUNDING
CbcParam.hpp, 536	CbcParam.hpp, 537
CBC_PARAM_DBL_CUTOFF	CBC_PARAM_STR_SOLVER
CbcParam.hpp, 536	CbcParam.hpp, 537
CBC_PARAM_DBL_DJFIX	CBC_PARAM_STR_TWOMIRCUTS
CbcParam.hpp, 536	CbcParam.hpp, 537
CBC_PARAM_DBL_GAPRATIO	CBC_PRIORITY
CbcParam.hpp, 536	CbcMessage.hpp, 530
CBC_PARAM_DBL_INCREMENT	CBC_RELAXED1
CbcParam.hpp, 536	CbcMessage.hpp, 530
CBC_PARAM_DBL_INFEASIBILITYWEIGHT	CBC_RELAXED2
CbcParam.hpp, 536	CbcMessage.hpp, 530
CBC_PARAM_DBL_INTEGERTOLERANCE	CBC_RESTART
CbcParam.hpp, 536	CbcMessage.hpp, 530
CBC_PARAM_DBL_TIGHTENFACTOR	CBC ROOT
CbcParam.hpp, 536	CbcMessage.hpp, 530
CBC_PARAM_FULLGENERALQUERY	CBC_ROOT_DETAIL
CbcParam.hpp, 536	CbcMessage.hpp, 530
CBC_PARAM_GENERALQUERY	CBC ROUNDING
CbcParam.hpp, 536	CbcMessage.hpp, 530
CBC_PARAM_INT_MAXNODES	CBC SOLINDIVIDUAL
	_
CbcParam.hpp, 536	CBC SOLUTION
CBC_PARAM_INT_STRONGBRANCHING	CBC_SOLUTION
CbcParam.hpp, 536	CBC SOLUTIONS
CBC_PARAM_NOTUSED_ADDCUTSSTRATEGY	CBC_SOLUTION2
CbcParam.hpp, 537	CbcMessage.hpp, 529
CBC_PARAM_NOTUSED_CBCSTUFF	CBC_START_SUB
CbcParam.hpp, 538	CbcMessage.hpp, 530
CBC_PARAM_NOTUSED_INVALID	CBC_STATUS
CbcParam.hpp, 538	CbcMessage.hpp, 530
CBC_PARAM_NOTUSED_ODDHOLECUTS	CBC_STATUS2
CbcParam.hpp, 537	CbcMessage.hpp, 530
CBC_PARAM_NOTUSED_OSLSTUFF	CBC_STATUS3
CbcParam.hpp, 538	CbcMessage.hpp, 530
CBC_PARAM_STR_BRANCHSTRATEGY	CBC_STRONG
CbcParam.hpp, 537	CbcMessage.hpp, 529
CBC_PARAM_STR_CLIQUECUTS	CBC_STRONG_STATS
CbcParam.hpp, 537	CbcMessage.hpp, 530
CBC_PARAM_STR_COSTSTRATEGY	CBC_STRONGSOL
CbcParam.hpp, 537	CbcMessage.hpp, 530
CBC_PARAM_STR_FLOWCUTS	CBC_THREAD_STATS
CbcParam.hpp, 537	CbcMessage.hpp, 530
CBC_PARAM_STR_GOMORYCUTS	CBC_TREE_SOL
CbcParam.hpp, 537	CbcMessage.hpp, 530
CBC_PARAM_STR_KNAPSACKCUTS	CBC_UNBOUNDED
CbcParam.hpp, 537	CbcMessage.hpp, 530
CBC_PARAM_STR_MIXEDCUTS	CBC_VUB_END
CbcParam.hpp, 537	CbcMessage.hpp, 530
CBC_PARAM_STR_NODESTRATEGY	CBC_VUB_PASS
CbcParam.hpp, 537	CbcMessage.hpp, 530
CBC PARAM STR PREPROCESS	CBC WARNING STRONG

CbcMessage.hpp, 530	CbcParam.hpp, 537
CBCCBC_FIRSTPARAM	CLP_PARAM_ACTION_EXIT
CbcCbcParam, 51	CbcParam.hpp, 537
CBCCBC_LASTPARAM	CLP_PARAM_ACTION_EXPORT
CbcCbcParam, 52	CbcParam.hpp, 537
CBCGEN_CONFUSION	CLP_PARAM_ACTION_FAKEBOUND
CbcGenMessages.hpp, 522	CbcParam.hpp, 537
CBCGEN_DUMMY_END	CLP_PARAM_ACTION_HELP
CbcGenMessages.hpp, 522	CbcParam.hpp, 538
CBCGEN_FIRSTPARAM	CLP PARAM ACTION IMPORT
CbcGenParam, 140	CbcParam.hpp, 537
CBCGEN LASTPARAM	CLP PARAM ACTION MAXIMIZE
CbcGenParam, 142	CbcParam.hpp, 537
CBCGEN_NEW_SOLVER	CLP_PARAM_ACTION_MINIMIZE
CbcGenMessages.hpp, 521	CbcParam.hpp, 537
CBCGEN TEST MSG	CLP_PARAM_ACTION_NETLIB_BARRIER
CbcGenMessages.hpp, 521	CbcParam.hpp, 538
CBCOSI_FIRSTPARAM	CLP_PARAM_ACTION_NETLIB_DUAL
CbcOsiParam, 343	CbcParam.hpp, 537
CBCOSI LASTPARAM	CLP_PARAM_ACTION_NETLIB_PRIMAL
CbcOsiParam, 344	CbcParam.hpp, 537
CGForceBut	CLP PARAM ACTION NETWORK
CbcGenCtlBlk, 127	CbcParam.hpp, 538
CGForceOn	CLP_PARAM_ACTION_PLUSMINUS
CbcGenCtlBlk, 127	CbcParam.hpp, 538
CGIfMove	CLP_PARAM_ACTION_PRIMALSIMPLEX
CbcGenCtlBlk, 127	CbcParam.hpp, 537
CGMarker	CLP_PARAM_ACTION_REALLY_SCALE
CbcGenCtlBlk, 127	CbcParam.hpp, 538
CGOff	CLP_PARAM_ACTION_RESTORE
CbcGenCtlBlk, 127	CbcParam.hpp, 537
CGOn	CLP_PARAM_ACTION_REVERSE
CbcGenCtlBlk, 127	CbcParam.hpp, 538
CGRoot	CLP PARAM ACTION SAVE
	CbcParam.hpp, 537
CbcGenCtlBlk, 127 CHOLESKY	CLP_PARAM_ACTION_SOLUTION
CbcOsiParam, 343	CbcParam.hpp, 537
CLEARCUTS ChaCar Barara 144	CLP_PARAM_ACTION_SOLVECONTINUOUS
CbcGenParam, 141	CbcParam.hpp, 538
CLIQUECUTS	CLP_PARAM_ACTION_STDIN
CbcGenParam, 141	CbcParam.hpp, 537
CLP_PARAM_ACTION_ALLSLACK	CLP_PARAM_ACTION_TIGHTEN
CbcParam.hpp, 538	CbcParam.hpp, 537
CLP_PARAM_ACTION_BARRIER	CLP_PARAM_ACTION_UNITTEST
CbcParam.hpp, 538	CbcParam.hpp, 537
CLP_PARAM_ACTION_BASISIN	CLP_PARAM_DBL_DUALBOUND
CbcParam.hpp, 538	CbcParam.hpp, 536
CLP_PARAM_ACTION_BASISOUT	CLP_PARAM_DBL_DUALTOLERANCE
CbcParam.hpp, 538	CbcParam.hpp, 536
CLP_PARAM_ACTION_CLEARCUTS	CLP_PARAM_DBL_OBJSCALE
CbcParam.hpp, 538	CbcParam.hpp, 536
CLP_PARAM_ACTION_DIRECTORY	CLP_PARAM_DBL_PRIMALTOLERANCE
CbcParam.hpp, 537	CbcParam.hpp, 536
CLP_PARAM_ACTION_DUALSIMPLEX	CLP_PARAM_DBL_PRIMALWEIGHT

CbcParam.hpp, 536	CbcParam.hpp, 536
CLP PARAM DBL RHSSCALE	CLP PARAM STR KKT
CbcParam.hpp, 536	CbcParam.hpp, 537
CLP_PARAM_DBL_TIMELIMIT	CLP_PARAM_STR_MESSAGES
CbcParam.hpp, 536	CbcParam.hpp, 537
CLP PARAM INT IDIOT	CLP_PARAM_STR_PERTURBATION
CbcParam.hpp, 536	CbcParam.hpp, 537
CLP_PARAM_INT_LOGLEVEL	CLP_PARAM_STR_PFI
CbcParam.hpp, 536	CbcParam.hpp, 537
CLP_PARAM_INT_MAXFACTOR	CLP_PARAM_STR_PRESOLVE
CbcParam.hpp, 536	CbcParam.hpp, 536
CLP_PARAM_INT_MAXITERATION	CLP_PARAM_STR_PRIMALPIVOT
CbcParam.hpp, 536	CbcParam.hpp, 536
CLP_PARAM_INT_OUTPUTFORMAT	CLP_PARAM_STR_SCALING
CLP PARAM INT. PERTVALUE	CbcParam.hpp, 536
CLP_PARAM_INT_PERTVALUE	CLP_PARAM_STR_SPARSEFACTOR
CbcParam.hpp, 536	CbcParam.hpp, 536
CLP_PARAM_INT_PRESOLVEOPTIONS	CLP_VERSION_NOTUSED_PRINTVERSION
CbcParam.hpp, 536	CbcParam.hpp, 538
CLP_PARAM_INT_PRESOLVEPASS	COMBINE
CbcParam.hpp, 536	CbcGenParam, 141
CLP_PARAM_INT_PRINTOPTIONS	COSTSTRATEGY
CbcParam.hpp, 536	CbcCbcParam, 52
CLP_PARAM_INT_SLPVALUE	CbcGenParam, 141
CbcParam.hpp, 536	CPP
CLP_PARAM_INT_SOLVERLOGLEVEL	CbcGenParam, 141
CbcParam.hpp, 536	CRASH
CLP_PARAM_INT_SPECIALOPTIONS	CbcOsiParam, 343
CbcParam.hpp, 536	CROSSOVER
CLP_PARAM_INT_SPRINT	CbcOsiParam, 343
CbcParam.hpp, 536	CUTDEPTH
CLP_PARAM_NOTUSED_ALGORITHM	CbcCbcParam, 52
CbcParam.hpp, 537	CbcGenParam, 141
CLP_PARAM_STR_AUTOSCALE	CUTOFF
CbcParam.hpp, 537	CbcCbcParam, 52
CLP_PARAM_STR_BARRIERSCALE	CUTPASS
CbcParam.hpp, 537	CbcCbcParam, 52
CLP_PARAM_STR_BIASLU	CUTSTRATEGY
CbcParam.hpp, 536	CbcGenParam, 141
CLP_PARAM_STR_CHOLESKY	CBC_Message
CbcParam.hpp, 537	CbcMessage.hpp, 529
CLP_PARAM_STR_CRASH	CBC VERSION
CbcParam.hpp, 536	config_cbc_default.h, 545
CLP PARAM STR CROSSOVER	CBC_VERSION_MAJOR
CbcParam.hpp, 537	config_cbc_default.h, 545
CLP_PARAM_STR_DIRECTION	CBC_VERSION_MINOR
CbcParam.hpp, 536	config_cbc_default.h, 545
CLP_PARAM_STR_DUALPIVOT	CGControl
CLP PARAM STR ERROPSALLOWED	COIN CRC VERROSITY
CLP_PARAM_STR_ERRORSALLOWED	COIN_CBC_VERBOSITY
CbcParam.hpp, 536	config_default.h, 545
CLP_PARAM_STR_GAMMA	COIN_HAS_CGL
CbcParam.hpp, 537	config_default.h, 545
CLP PARAM STR KEEPNAMES	COIN HAS CLP

C 1 C 11 E 45	L D
config_default.h, 545	LotsizeBranchObj, 512
COIN_HAS_COINUTILS	NWayBranchObj, 512
config_default.h, 545	OneGeneralBranchingObj, 512
COIN_HAS_OSI	SimpleIntegerBranchObj, 512
config_default.h, 546	SimpleIntegerDynamicPseudoCostBranchObj, 512
COIN_HAS_VOL	SoSBranchObj, 512
config_default.h, 546	CbcCbcParam
COINLINKAGE	ALLOWABLEGAP, 51
Cbc_C_Interface.h, 506	CBCCBC_FIRSTPARAM, 51
callBack	CBCCBC_LASTPARAM, 52
CbcStopNow, 401	COSTSTRATEGY, 52
callCbc	CUTDEPTH, 52
CbcModel.hpp, 532	CUTOFF, 52
callCbc1	CUTPASS, 52
CbcModel.hpp, 532	DIRECTION, 52
canDealWithOdd	GAPRATIO, 52
CbcHeuristic, 151	INCREMENT, 52
CbcHeuristicDynamic3, 192	INFEASIBILITYWEIGHT, 52
canDo	INTEGERTOLERANCE, 52
CbcUser, 431	LOGLEVEL, 52
canDoHeuristics	MAXIMIZE, 52
CbcBranchToFixLots, 49	MAXNODES, 52
CbcLotsize, 251	MINIMIZE, 52
CbcSOS, 394	MIPOPTIONS, 52
OsiBiLinear, 446	MOREMIPOPTIONS, 52
OsiLink, 477	NUMBERANALYZE, 52
OsiOldLink, 482	NUMBERBEFORE, 52
canDropCut	NUMBERMINI, 52
CbcCountRowCut, 76	STRONGBRANCHING, 52
canFix	TIMELIMIT_BAB, 52
CbcCutBranchingObject, 79	CbcCurrentCutoff
canHeuristicRun	CbcModel, 272
CbcHeuristicDive, 165	CbcCurrentMinimizationObjectiveValue
CbcHeuristicDiveGuided, 171	CbcModel, 273
canStopOnGap	CbcCurrentObjectiveValue
CbcModel, 280	CbcModel, 273
CbcAllowableFractionGap	CbcCutoffIncrement
CbcModel, 272	CbcModel, 272
CbcAllowableGap	CbcEventHandler
CbcModel, 272	addCuts, 101
CbcBranchBase.hpp	afterHeuristic, 101
CbcRangeDisjoint, 510	beforeSolution1, 101
CbcRangeOverlap, 510	beforeSolution1, 101 beforeSolution2, 101
CbcRangeSame, 510	endSearch, 101
-	heuristicPass, 101
CbcRangeSubset, 510	•
CbcRangeSuperset, 510	heuristicSolution, 101
CbcBranchingObject.hpp	killSolution, 101
CliqueBranchObj, 512	noAction, 101
CutBranchingObj, 512	node, 101
DummyBranchObj, 512	restart, 101
DynamicPseudoCostBranchObj, 512	restartRoot, 101
FollowOnBranchObj, 512	smallBranchAndBound, 101
GeneralDepthBranchObj, 512	solution, 101
LongCliqueBranchObj, 512	stop, 101

takeAction, 101	CBCGEN_LASTPARAM, 142
treeStatus, 101	CLEARCUTS, 141
CbcFathomDiscipline	CLIQUECUTS, 141
CbcModel, 272	COMBINE, 141
CbcGenCtlBlk	COSTSTRATEGY, 141
BACAbandon, 128	CPP, 141
BACFinish, 128	CUTDEPTH, 141
BACInvalid, 128	CUTSTRATEGY, 141
BACNotRun, 128	DEBUG, 141
BACStop, 128	DIRECTORY, 141
BACUser, 128	DJFIX, 141
BACmFinish, 129	DUMMY, 141
BACmGap, 129	ERRORSALLOWED, 141
BACmInfeas, 129	EXIT, 141
BACmInvalid, 129	EXPORT, 141
BACmNodeLimit, 129	FLOWCUTS, 141
BACmOther, 129	FPUMP, 141
BACmSolnLimit, 129	FPUMPITS, 141
BACmTimeLimit, 129	FULLGENERALQUERY, 141
BACmUbnd, 129	GENERALQUERY, 140
BACmUser, 129	GOMORYCUTS, 141
BACWBAC, 129	GREEDY, 141
BACwBareRoot, 129	HELP, 141
BACWIPP, 129	HEURISTICSTRATEGY, 141
BACwIPPRelax, 129	IMPORT, 141
BACwInvalid, 129	INTPRINT, 141
BACwNotStarted, 129	KNAPSACKCUTS, 141
BPCost, 127	LOCALTREE, 141
BPExt, 128	LOGLEVEL, 141
BPOff, 127	MESSAGES, 141
BPOrder, 128	MIPLIB, 141
CGForceBut, 127	MIXEDCUTS, 141
CGForceOn, 127	ODDHOLECUTS, 141
CGIfMove, 127	OUTDUPROWS, 141
CGMarker, 127	OUTPUTFORMAT, 141
CGOff, 127	PREPROCESS, 141
CGOn, 127	PRINTMASK, 141
CGRoot, 127	PRINTOPTIONS, 141
IPPEqual, 126	PRINTVERSION, 141
IPPEqualAll, 127	PRIORITYIN, 141
IPPOff, 126	PROBINGCUTS, 141
IPPOn, 126	REDSPLITCUTS, 141
IPPSOS, 126	ROUNDING, 141
IPPSave, 126	SHOWUNIMP, 142
IPPStrategy, 127	SOLUTION, 142
IPPTrySOS, 127	SOLVECONTINUOUS, 142
CbcGenMessages.hpp	SOLVER, 142
CBCGEN CONFUSION, 522	SOS, 142
CBCGEN_DUMMY_END, 522	STDIN, 142
CBCGEN_DOMMY_END, 522 CBCGEN_NEW_SOLVER, 521	STRENGTHEN, 142
CBCGEN_TEST_MSG, 521	TIGHTENFACTOR, 142
CbcGenParam	TWOMIRCUTS, 142
BAB, 141	UNITTEST, 142
CBCGEN_FIRSTPARAM, 140	USERCBC, 142

USESOLUTION, 142	CBC RELAXED2, 530
VERBOSE, 142	CBC RESTART, 530
CbcHeuristicFractionGap	CBC ROOT, 530
CbcModel, 273	CBC_ROOT_DETAIL, 530
CbcHeuristicGap	CBC_ROUNDING, 530
CbcModel, 273	CBC SOLINDIVIDUAL, 530
CbcInfeasibilityWeight	CBC SOLUTION, 529
CbcModel, 272	CBC_SOLUTION2, 529
CbcIntegerTolerance	CBC_START_SUB, 530
CbcModel, 272	CBC_STATUS, 530
CbcLargestChange	CBC STATUS2, 530
CbcModel, 273	CBC STATUS3, 530
CbcLastDblParam	CBC_STRONG, 529
CbcModel, 273	CBC_STRONG_STATS, 530
CbcLastIntParam	CBC STRONGSOL, 530
CbcModel, 272	CBC_THREAD_STATS, 530
CbcMaxNumNode	CBC_TREE_SOL, 530
CbcModel, 272	
CbcMaxNumSol	CBC_UNBOUNDED, 530 CBC_VUB_END, 530
CbcModel, 272	CBC_VUB_PASS, 530
CbcMaximumSeconds	CBC_WARNING_STRONG, 530
CbcModel, 272	CbcModel
CbcMessage.hpp	CbcAllowableFractionGap, 272
CBC_BRANCH, 530	CbcAllowableGap, 272
CBC_CUTOFF_WARNING1, 530	CbcCurrentCutoff, 272
CBC_CUTS_STATS, 530	CbcCurrentMinimizationObjectiveValue, 273
CBC_DUMMY_END, 530	CbcCurrentObjectiveValue, 273
CBC_END, 529	CbcCutoffIncrement, 272
CBC_END_GOOD, 529	CbcFathomDiscipline, 272
CBC_END_SOLUTION, 529	CbcHeuristicFractionGap, 273
CBC_END_SUB, 530	CbcHeuristicGap, 273
CBC_EVENT, 529	CbcInfeasibilityWeight, 272
CBC_FATHOM_CHANGE, 530	CbcIntegerTolerance, 272
CBC_FPUMP1, 530	CbcLargestChange, 273
CBC_FPUMP2, 530	CbcLastDblParam, 273
CBC_GAP, 530	CbcLastIntParam, 272
CBC_GENERAL, 530	CbcMaxNumNode, 272
CBC_GENERATOR, 530	CbcMaxNumSol, 272
CBC_HEURISTICS_OFF, 530	CbcMaximumSeconds, 272
CBC_INFEAS, 529	CbcNumberBranches, 272
CBC_INTEGERINCREMENT, 530	CbcOptimizationDirection, 273
CBC_ITERATE_STRONG, 530	CbcPrinting, 272
CBC MAXITERS, 529	CbcSmallChange, 273
CBC MAXNODES, 529	CbcSmallestChange, 273
CBC_MAXSOLS, 529	CbcStartSeconds, 273
CBC MAXTIME, 529	CbcSumChange, 273
CBC NOINT, 530	CbcNumberBranches
CBC NOTFEAS1, 530	CbcModel, 272
CBC NOTFEAS2, 530	CbcOptimizationDirection
CBC_NOTFEAS3, 530	CbcModel, 273
CBC_OTHER_STATS, 530	CbcOsiParam
CBC_OTHER_STATS2, 530	ALGORITHM, 343
CBC_PRIORITY, 530	ALLSLACK, 343
CBC_RELAXED1, 530	AUTOSCALE, 343
5_5_1 (ED) (ED 1, 500	,

BARRIER, 343	CBC PARAM DBL GAPRATIO, 536
BARRIERSCALE, 343	CBC PARAM DBL INCREMENT, 536
BASISIN, 343	CBC PARAM DBL INFEASIBILITYWEIGHT, 536
BASISOUT, 343	CBC_PARAM_DBL_INTEGERTOLERANCE, 536
BIASLU, 343	CBC PARAM DBL TIGHTENFACTOR, 536
CBCOSI FIRSTPARAM, 343	CBC PARAM FULLGENERALQUERY, 536
CBCOSI_LASTPARAM, 344	-
	CBC_PARAM_GENERALQUERY, 536
CHOLESKY, 343	CBC_PARAM_INT_MAXNODES, 536
CRASH, 343	CBC_PARAM_INT_STRONGBRANCHING, 536
CROSSOVER, 343	CBC_PARAM_NOTUSED_ADDCUTSSTRATEGY,
DUALBOUND, 343	537
DUALPIVOT, 343	CBC_PARAM_NOTUSED_CBCSTUFF, 538
DUALSIMPLEX, 343	CBC_PARAM_NOTUSED_INVALID, 538
DUALTOLERANCE, 343	CBC_PARAM_NOTUSED_ODDHOLECUTS, 537
FAKEBOUND, 343	CBC_PARAM_NOTUSED_OSLSTUFF, 538
GAMMA, 343	CBC_PARAM_STR_BRANCHSTRATEGY, 537
IDIOT, 343	CBC_PARAM_STR_CLIQUECUTS, 537
KEEPNAMES, 343	CBC_PARAM_STR_COSTSTRATEGY, 537
KKT, 343	CBC_PARAM_STR_FLOWCUTS, 537
MAXHOTITS, 343	CBC_PARAM_STR_GOMORYCUTS, 537
MAXITERATION, 343	CBC_PARAM_STR_KNAPSACKCUTS, 537
NETLIB_BARRIER, 343	CBC_PARAM_STR_MIXEDCUTS, 537
NETLIB_DUAL, 343	CBC_PARAM_STR_NODESTRATEGY, 537
NETLIB_PRIMAL, 343	CBC_PARAM_STR_PREPROCESS, 537
NETWORK, 343	CBC_PARAM_STR_PROBINGCUTS, 537
OBJSCALE, 343	CBC PARAM STR ROUNDING, 537
PERTURBATION, 343	CBC PARAM STR SOLVER, 537
PERTVALUE, 344	CBC_PARAM_STR_TWOMIRCUTS, 537
PFI, 344	CLP_PARAM_ACTION_ALLSLACK, 538
PLUSMINUS, 344	CLP PARAM ACTION BARRIER, 538
PRESOLVE, 344	CLP PARAM ACTION BASISIN, 538
PRESOLVEOPTIONS, 344	CLP PARAM ACTION BASISOUT, 538
PRESOLVEPASS, 344	CLP_PARAM_ACTION_CLEARCUTS, 538
PRIMALPIVOT, 344	CLP PARAM ACTION DIRECTORY, 537
PRIMALSIMPLEX, 344	CLP PARAM ACTION DUALSIMPLEX, 537
PRIMALTOLERANCE, 344	CLP_PARAM_ACTION_EXIT, 537
REALLY SCALE, 344	CLP_PARAM_ACTION_EXPORT, 537
RESTORE, 344	CLP_PARAM_ACTION_FAKEBOUND, 537
REVERSE, 344	CLP PARAM ACTION HELP, 538
RHSSCALE, 344	CLP PARAM ACTION IMPORT, 537
SAVE, 344	CLP PARAM ACTION MAXIMIZE, 537
SCALING, 344	CLP_PARAM_ACTION_MINIMIZE, 537
SLPVALUE, 344	CLP_PARAM_ACTION_NETLIB_BARRIER, 538
SOLVERLOGLEVEL, 344	CLP_PARAM_ACTION_NETLIB_DUAL, 537
SPARSEFACTOR, 344	CLP_PARAM_ACTION_NETLIB_PRIMAL, 537
SPECIALOPTIONS, 344	CLP_PARAM_ACTION_NETWORK, 538
SPRINT, 344	CLP_PARAM_ACTION_PLUSMINUS, 538
TIGHTEN, 344	CLP_PARAM_ACTION_PRIMALSIMPLEX, 537
CbcParam.hpp	CLP_PARAM_ACTION_REALLY_SCALE, 538
CBC_PARAM_ACTION_BAB, 538	CLP_PARAM_ACTION_RESTORE, 537
CBC_PARAM_ACTION_MIPLIB, 538	CLP_PARAM_ACTION_REVERSE, 538
CBC_PARAM_DBL_ALLOWABLEGAP, 536	CLP_PARAM_ACTION_SAVE, 537
CBC_PARAM_DBL_CUTOFF, 536	CLP_PARAM_ACTION_SOLUTION, 537
CBC_PARAM_DBL_DJFIX, 536	CLP_PARAM_ACTION_SOLVECONTINUOUS, 538

CLP_PARAM_ACTION_STDIN, 537	CbcRangeSuperset
CLP_PARAM_ACTION_TIGHTEN, 537	CbcBranchBase.hpp, 510
CLP_PARAM_ACTION_UNITTEST, 537	CbcSmallChange
CLP_PARAM_DBL_DUALBOUND, 536	CbcModel, 273
CLP_PARAM_DBL_DUALTOLERANCE, 536	CbcSmallestChange
CLP_PARAM_DBL_OBJSCALE, 536	CbcModel, 273
CLP PARAM DBL PRIMALTOLERANCE, 536	CbcStartSeconds
CLP PARAM DBL PRIMALWEIGHT, 536	CbcModel, 273
CLP PARAM DBL RHSSCALE, 536	CbcSumChange
CLP_PARAM_DBL_TIMELIMIT, 536	CbcModel, 273
CLP PARAM INT IDIOT, 536	Cbc_C_Interface.h
CLP PARAM INT LOGLEVEL, 536	COINLINKAGE, 506
CLP_PARAM_INT_MAXFACTOR, 536	Cbc_addColumns, 505
CLP_PARAM_INT_MAXITERATION, 536	Cbc_addRows, 505
CLP PARAM INT OUTPUTFORMAT, 536	Cbc addSOS Dense, 506
CLP PARAM INT PERTVALUE, 536	Cbc_addSOS_Sparse, 506
CLP_PARAM_INT_PRESOLVEOPTIONS, 536	Cbc_copyNames, 506
CLP PARAM INT PRESOLVEPASS, 536	Cbc_getVersion, 505
CLP_PARAM_INT_PRINTOPTIONS, 536	Cbc_loadProblem, 505
CLP PARAM INT SLPVALUE, 536	Cbc_registerCallBack, 506
CLP PARAM INT SOLVERLOGLEVEL, 536	Cbc addColumns
CLP_PARAM_INT_SPECIALOPTIONS, 536	Cbc_C_Interface.h, 505
CLP_PARAM_INT_SPRINT, 536	Cbc_addRows
CLP PARAM NOTUSED ALGORITHM, 537	Cbc_C_Interface.h, 505
CLP PARAM STR AUTOSCALE, 537	Cbc_addSOS_Dense
CLP PARAM STR BARRIERSCALE, 537	Cbc_C_Interface.h, 506
CLP PARAM STR BIASLU, 536	
CLP_PARAM_STR_CHOLESKY, 537	Cbc_addSOS_Sparse Cbc_C_Interface.h, 506
CLP_PARAM_STR_CRASH, 536	Cbc_ampl.h
CLP_PARAM_STR_CROSSOVER, 537	ampl_obj_prec, 504
CLP_PARAM_STR_DIRECTION, 536	freeArgs, 504
CLP_PARAM_STR_DUALPIVOT, 536	freeArrays1, 504
CLP_PARAM_STR_ERRORSALLOWED, 536	freeArrays2, 504
CLP_PARAM_STR_GAMMA, 537	readAmpl, 504
CLP_PARAM_STR_KEEPNAMES, 536	writeAmpl, 504
CLP_PARAM_STR_KKT, 537	Cbc_copyNames
CLP_PARAM_STR_MESSAGES, 537	Cbc_C_Interface.h, 506
CLP_PARAM_STR_PERTURBATION, 537	Cbc_getVersion
CLP_PARAM_STR_PFI, 537	Cbc_C_Interface.h, 505
CLP_PARAM_STR_PRESOLVE, 536	Cbc_loadProblem
CLP_PARAM_STR_PRIMALPIVOT, 536	Cbc_C_Interface.h, 505
CLP_PARAM_STR_SCALING, 536	Cbc_registerCallBack
CLP_PARAM_STR_SPARSEFACTOR, 536	Cbc_C_Interface.h, 506
CLP_VERSION_NOTUSED_PRINTVERSION, 538	CbcAction
CbcPrinting	CbcEventHandler, 101
CbcModel, 272	CbcBaseModel, 27
CbcRangeDisjoint	~CbcBaseModel, 28
CbcBranchBase.hpp, 510	CbcBaseModel, 27
CbcRangeOverlap	CbcBaseModel, 27
CbcBranchBase.hpp, 510	CbcBranchAllDifferent, 28
CbcRangeSame	\sim CbcBranchAllDifferent, 29
CbcBranchBase.hpp, 510	CbcBranchAllDifferent, 29
CbcRangeSubset	CbcBranchAllDifferent, 29
CbcBranchBase.hpp, 510	clone, 29

createCbcBranch, 29	CbcBranchDynamicDecision, 39
infeasibility, 29	CbcBranchDynamicDecision, 39
numberInSet_, 29	clone, 39
operator=, 29	getBestCriterion, 39
which_, 29	initialize, 39
CbcBranchBase.hpp	saveBranchingObject, 40
CbcCompareRanges, 510	setBestCriterion, 39
CbcRangeCompare, 510	updateInformation, 40
CbcBranchCut, 30	whichMethod, 40
~CbcBranchCut, 31	CbcBranchObjType
boundBranch, 31	CbcBranchingObject.hpp, 512
CbcBranchCut, 31	CbcBranchToFixLots, 47
CbcBranchCut, 31	~CbcBranchToFixLots, 48
clone, 31	alwaysCreate_, 50
createCbcBranch, 31	canDoHeuristics, 49
feasibleRegion, 31	CbcBranchToFixLots, 48
infeasibility, 31	CbcBranchToFixLots, 48
notPreferredNewFeasible, 32	clone, 48
operator=, 31	createCbcBranch, 49
preferredNewFeasible, 32	depth, 50
resetBounds, 32	deptri_, 50 djTolerance , 49
CbcBranchDecision, 32	fractionFixed, 49
	- -
~CbcBranchDecision, 34	infeasibility, 49
bestBranch, 34	mark_, 49
betterBranch, 34	matrixByRow_, 49
CbcBranchDecision, 34	numberClean_, 50
cbcModel, 35	operator=, 48
CbcBranchDecision, 34	redoSequenceEtc, 49
chooseMethod, 35	shallWe, 49
chooseMethod_, 36	CbcBranchingObject, 40
clone, 34	~CbcBranchingObject, 43
generateCpp, 35	branch, 44
getBestCriterion, 35	CbcBranchingObject, 43
initialize, 34	CbcBranchingObject, 43
model_, 35	clone, 43
object_, 35	compareBranchingObject, 46
saveBranchingObject, 34	compareOriginalObject, 46
setBestCriterion, 35	fillStrongInfo, 43
setChooseMethod, 35	fix, 44
updateInformation, 35	model, 45
whichMethod, 34	model_, 46
CbcBranchDefaultDecision, 36	object, 45
~CbcBranchDefaultDecision, 37	operator=, 43
bestBranch, 37	originalCbcObject_, 46
betterBranch, 37	previousBranch, 44
CbcBranchDefaultDecision, 37	print, 45
CbcBranchDefaultDecision, 37	resetNumberBranchesLeft, 44
clone, 37	setModel, 45
getBestCriterion, 37	setNumberBranches, 44
initialize, 37	setOriginalObject, 45
setBestCriterion, 37	tighten, 44
CbcBranchDynamicDecision, 38	type, 46
~CbcBranchDynamicDecision, 39	variable, 45
betterBranch, 39	variable_, 46
· - · · · · · · · · · · · · · ·	

way, 45	type, 60
way_, 46	CbcCompare, 60
CbcBranchingObject.hpp	\sim CbcCompare, 61
CbcBranchObjType, 512	alternateTest, 61
CbcCbcParam, 50	CbcCompare, 61
\sim CbcCbcParam, 53	CbcCompare, 61
CbcCbcParam, 52, 53	compareNodes, 61
CbcCbcParamCode, 51	comparisonObject, 61
CbcCbcParam, 52, 53	operator(), 61
clone, 53	test_, 61
obj, 53	CbcCompareBase, 61
operator=, 53	\sim CbcCompareBase, 62
paramCode, 53	alternateTest, 64
setObj, 53	CbcCompareBase, 62, 63
setParamCode, 53	CbcCompareBase, 62, 63
CbcCbcParamCode	clone, 63
CbcCbcParam, 51	equalityTest, 64
CbcCbcParamUtils, 20	every1000Nodes, 63
addCbcCbcParams, 20	fullScan, 63
loadCbcParamObj, 20	generateCpp, 63
pushCbcCbcDbl, 21	newSolution, 63
pushCbcCbcInt, 21	operator(), 64
setCbcModelDefaults, 20	operator=, 63
CbcClique, 54	sayThreaded, 64
\sim CbcClique, 56	test, 64
CbcClique, 56	test_, 64
CbcClique, 56	threaded_, 64
	tinoadod , o i
•	
cliqueType, 57	CbcCompareDefault, 64
cliqueType, 57 cliqueType_, 58	CbcCompareDefault, 64 ~CbcCompareDefault, 66
cliqueType, 57 cliqueType_, 58 clone, 56	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberMembers_, 57	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberNonSOSMembers, 56	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberNonSOSMembers, 56 numberNonSOSMembers_, 57	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberMembers_, 57 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberMembers_, 57 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getCutoff, 67
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers_, 56 numberMembers_, 57 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57 slack_, 58	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getCutoff, 67 getWeight, 67
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers_, 56 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57 slack_, 58 type, 57	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getCutoff, 67 getWeight, 67 newSolution, 67
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberMembers_, 57 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57 slack_, 58 type, 57 type_, 57	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getCutoff, 67 getWeight, 67 newSolution, 67 numberSolutions_, 68
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberMembers_, 57 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57 slack_, 58 type, 57 type_, 57 CbcCliqueBranchingObject, 58	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getCutoff, 67 getWeight, 67 newSolution, 67 numberSolutions_, 68 operator=, 66
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberMembers_, 57 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57 slack_, 58 type, 57 type_, 57 CbcCliqueBranchingObject, 58 ~CbcCliqueBranchingObject, 59	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getCutoff, 67 getWeight, 67 newSolution, 67 numberSolutions_, 68 operator=, 66 saveWeight_, 68
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberMembers_, 57 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57 slack_, 58 type, 57 type_, 57 CbcCliqueBranchingObject, 58 ~CbcCliqueBranchingObject, 59 branch, 59	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getWeight, 67 newSolution, 67 numberSolutions_, 68 operator=, 66 saveWeight_, 68 setBestPossible, 67
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers_, 56 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57 slack_, 58 type, 57 type_, 57 CbcCliqueBranchingObject, 58 ~CbcCliqueBranchingObject, 59 branch, 59 CbcCliqueBranchingObject, 59	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getCutoff, 67 newSolution, 67 numberSolutions_, 68 operator=, 66 saveWeight_, 68 setBestPossible, 67 setBreadthDepth, 67
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberMembers_, 57 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57 slack_, 58 type, 57 type_, 57 CbcCliqueBranchingObject, 59 branch, 59 CbcCliqueBranchingObject, 59 CbcCliqueBranchingObject, 59 CbcCliqueBranchingObject, 59	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getCutoff, 67 newSolution, 67 numberSolutions_, 68 operator=, 66 saveWeight_, 68 setBestPossible, 67 setBreadthDepth, 67 setCutoff, 67
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberMembers_, 57 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57 slack_, 58 type, 57 type_, 57 CbcCliqueBranchingObject, 58	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getCutoff, 67 getWeight, 67 newSolution, 67 numberSolutions_, 68 operator=, 66 saveWeight_, 68 setBestPossible, 67 setBreadthDepth, 67 setCutoff, 67 setWeight, 67
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberMembers_, 57 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57 slack_, 58 type, 57 type_, 57 CbcCliqueBranchingObject, 58	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getCutoff, 67 getWeight, 67 newSolution, 67 numberSolutions_, 68 operator=, 66 saveWeight_, 68 setBestPossible, 67 setBreadthDepth, 67 setCutoff, 67 setWeight, 67 setWeight, 67 setUpForDiving_, 69
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberMembers_, 57 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57 slack_, 58 type, 57 type_, 57 CbcCliqueBranchingObject, 58	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getWeight, 67 newSolution, 67 numberSolutions_, 68 operator=, 66 saveWeight_, 68 setBestPossible, 67 setCutoff, 67 setCutoff, 67 setCutoff, 67 setWeight, 67 setCutoff, 67 setWeight, 67 setWeight, 67 setWeight, 67 setWeight, 67
cliqueType, 57 cliqueType_, 58 clone, 56 createCbcBranch, 56 feasibleRegion, 56 infeasibility, 56 members, 57 members_, 57 numberMembers, 56 numberMembers_, 57 numberNonSOSMembers, 56 numberNonSOSMembers_, 57 operator=, 56 redoSequenceEtc, 57 slack_, 58 type, 57 type_, 57 CbcCliqueBranchingObject, 58	CbcCompareDefault, 64 ~CbcCompareDefault, 66 afterNodeNumber_, 69 bestPossible_, 68 breadthDepth_, 68 CbcCompareDefault, 66 CbcCompareDefault, 66 cleanDive, 68 clone, 66 cutoff_, 68 every1000Nodes, 67 generateCpp, 67 getBestPossible, 67 getCutoff, 67 getWeight, 67 newSolution, 67 numberSolutions_, 68 operator=, 66 saveWeight_, 68 setBestPossible, 67 setBreadthDepth, 67 setCutoff, 67 setWeight, 67 setWeight, 67 setUpForDiving_, 69

treeSize_, 68	compareOriginalObject, 78
weight_, 68	down_, 79
CbcCompareDepth, 69	operator=, 78
~CbcCompareDepth, 70	print, 78
CbcCompareDepth, 70	type, 78
CbcCompareDepth, 70	up_, 79
clone, 70	CbcCutGenerator, 79
generateCpp, 70	∼CbcCutGenerator, 83
operator=, 70	addStatistics, 89
test, 70	atSolution, 85
CbcCompareEstimate, 70	CbcCutGenerator, 82
\sim CbcCompareEstimate, 71	CbcCutGenerator, 82
CbcCompareEstimate, 71	cutGeneratorName, 83
CbcCompareEstimate, 71	generateCuts, 83
clone, 71	generateTuning, 83
generateCpp, 71	generator, 86
operator=, 71	globalCuts, 89
test, 71	globalCutsAtRoot, 89
CbcCompareObjective, 71	howOften, 83
~CbcCompareObjective, 72	howOftenInSub, 84
CbcCompareObjective, 72	inaccuracy, 84
CbcCompareObjective, 72	incrementNumberColumnCuts, 87
clone, 72	incrementNumberCutsActive, 87
generateCpp, 72	incrementNumberCutsInTotal, 86
operator=, 72	incrementNumberElementsInTotal, 86
test, 72	incrementNumberTimesEntered, 86
CbcCompareRanges	incrementTimeInCutGenerator, 85
CbcBranchBase.hpp, 510	ineffectualCuts, 88
CbcConsequence, 73	maximumTries, 84
~CbcConsequence, 73	mustCallAgain, 87
applyToSolver, 74	needsOptimalBasis, 87
CbcConsequence, 73	normal, 85
CbcConsequence, 73	numberActiveCutsAtRoot, 89
clone, 73	numberColumnCuts, 86
operator=, 73	numberCutsActive, 87
CbcCountRowCut, 74	numberCutsAtRoot, 88
~CbcCountRowCut, 75	numberCutsInTotal, 86
canDropCut, 76	numberElementsInTotal, 86
CbcCountRowCut, 75	numberShortCutsAtRoot, 89
CbcCountRowCut, 75	numberTimesEntered, 86
decrement, 75	operator=, 83
increment, 75	refreshModel, 83
numberPointingToThis, 76	scaleBackStatistics, 89
setInfo, 76	setAtSolution, 85
whichCutGenerator, 76	setGlobalCuts, 89
CbcCutBranchingObject, 76	setGlobalCutsAtRoot, 89
~CbcCutBranchingObject, 78	setHowOften, 83
boundBranch, 78	setInaccuracy, 84
branch, 78	setIneffectualCuts, 88
canFix_, 79	setMaximumTries, 84
CbcCutBranchingObject, 77	setModel, 89
CbcCutBranchingObject, 77	setMustCallAgain, 87
clone, 78	setNeedsOptimalBasis, 87
compareBranchingObject, 78	setNormal, 85

setNumberActiveCutsAtRoot, 89	CbcDummyBranchingObject, 94
setNumberColumnCuts, 86	clone, 94
setNumberCutsActive, 87	compareBranchingObject, 95
setNumberCutsAtRoot, 88	compareOriginalObject, 95
setNumberCutsInTotal, 86	operator=, 94
setNumberElementsInTotal, 86	print, 95
setNumberShortCutsAtRoot, 89	type, 95
setNumberTimesEntered, 86	CbcDynamicPseudoCostBranchingObject, 95
setSwitchOfflfLessThan, 87	\sim CbcDynamicPseudoCostBranchingObject, 97
setSwitchedOff, 87	branch, 98
setTiming, 85	CbcDynamicPseudoCostBranchingObject, 97
setWhatDepth, 84	CbcDynamicPseudoCostBranchingObject, 97
setWhatDepthInSub, 84	changeInGuessed, 98
setWhenInfeasible, 85	changeInGuessed_, 99
setWhetherCallAtEnd, 88	clone, 97
setWhetherInMustCallAgainMode, 88	fillPart, 98
setWhetherToUse, 88	fillStrongInfo, 98
switchOffIfLessThan, 87	object, 98
switchedOff, 87	object_, 99
switches, 84	operator=, 97
timeInCutGenerator, 85	setChangeInGuessed, 98
timing, 85	setObject, 98
whatDepth, 84	type, 98
whatDepthInSub, 84	CbcEvent
whenInfeasible, 85	CbcEventHandler, 101
whetherCallAtEnd, 88	CbcEventHandler, 99
whetherInMustCallAgainMode, 88	∼CbcEventHandler, 101
whetherToUse, 88	CbcAction, 101
CbcCutGenerator.hpp	CbcEvent, 101
SCANCUTS, 516	CbcEventHandler, 101
SCANCUTS_PROBING, 516	CbcEventHandler, 101
CbcCutModifier, 90	clone, 102
~CbcCutModifier, 91	dfltAction_, 102
CbcCutModifier, 90	eaMap_, 103
CbcCutModifier, 90	eaMapPair, 100
clone, 91	event, 102
generateCpp, 91	getModel, 102
modify, 91	model_, 102
operator=, 91	operator=, 102
CbcCutSubsetModifier, 91	setAction, 102
~CbcCutSubsetModifier, 92	setDfltAction, 102
CbcCutSubsetModifier, 92	setModel, 102
CbcCutSubsetModifier, 92	CbcFathom, 103
clone, 92	~CbcFathom, 104
firstOdd_, 93	CbcFathom, 104
generateCpp, 93	CbcFathom, 104
modify, 93	clone, 104
operator=, 92	fathom, 104
CbcDblParam	model_, 104
CbcModel, 272	possible, 104
CbcDummyBranchingObject, 93	possible_, 104 possible_, 105
~CbcDummyBranchingObject, 94	resetModel, 104
branch, 94	setModel, 104 ChoEathomDynamioProgramming, 105
CbcDummyBranchingObject, 94	CbcFathomDynamicProgramming, 105

~CbcFathomDynamicProgramming, 107	branch, 112
algorithm_, 110	CbcFixingBranchingObject, 112
back, 108	CbcFixingBranchingObject, 112
back_, 109	clone, 112
bitPattern_, 110	compareBranchingObject, 113
CbcFathomDynamicProgramming, 107	compareOriginalObject, 113
CbcFathomDynamicProgramming, 107	operator=, 112
checkPossible, 108	print, 112
clone, 107	type, 112
coefficients_, 109	CbcFollowOn, 115
cost, 108	\sim CbcFollowOn, 117
cost_, 108	CbcFollowOn, 117
fathom, 107	CbcFollowOn, 117
indices_, 109	clone, 117
lookup_, 109	createCbcBranch, 117
maximumSize, 107	feasibleRegion, 117
maximumSizeAllowed_, 109	gutsOfFollowOn, 117
numberActive_, 109	infeasibility, 117
numberBits_, 109	matrix_, 117
numberNonOne_, 110	matrixByRow_, 117
resetModel, 107	operator=, 117
rhs_, 109	rhs_, 117
setAlgorithm, 108	CbcFullNodeInfo, 118
setMaximumSize, 108	~CbcFullNodeInfo, 120
setModel, 107	applyBounds, 120
setTarget, 108	applyToModel, 120
size_, 108	basis_, 121
startBit_, 109	buildRowBasis, 120
target, 108	CbcFullNodeInfo, 119
target_, 109	CbcFullNodeInfo, 119
tryColumn, 108	clone, 120
type_, 108	lower, 120
CbcFeasibilityBase, 110	lower_, 121
~CbcFeasibilityBase, 110	mutableLower, 120
CbcFeasibilityBase, 110, 111	mutableUpper, 121
CbcFeasibilityBase, 110, 111	numberIntegers_, 121
clone, 111	setColLower, 120
feasible, 111	setColUpper, 121
operator=, 111	upper, 120
CbcFixVariable, 113	upper_, 120 upper_, 121
~CbcFixVariable, 114	CbcGenCtlBlk, 121
applyToSolver, 115	~CbcGenCtlBlk, 129
CbcFixVariable, 114	allowImportErrors_, 135
CbcFixVariable, 114	BACMajor, 128
clone, 114	BACMinor, 128
newBound_, 115	BACWhere, 129
numberStates_, 115	BPControl, 127
operator=, 114	bab_, 137
startLower_, 115	CGControl, 127
startUpper_, 115	CbcGenCtlBlk, 129
states_, 115	CbcGenParamUtils::addCbcGenParams, 134
variable_, 115	cbcParams_, 135
CbcFixingBranchingObject, 111	CbcGenCtlBlk, 129
~CbcFixingBranchingObject, 112	chooseStrong_, 137

debugCreate_, 136	setMessages, 134
debugFile_, 136	setMirAction, 131
debugSol_, 136	setProbingAction, 130
defaultSettings_, 136	setRedSplitAction, 131
dfltDirectory_, 134	setRoundingAction, 132
dfltSolver_, 136	setTreeLocalAction, 133
djFix_, 137	setTwomirAction, 131
genParams_, 135	totalTime_, 136
getClique, 130	translateMajor, 133
getCombine, 132	translateMinor, 133
getCutDepth, 130	verbose_, 135
getFPump, 131	version_, 134
getFlow, 130	CbcGenCtlBlk::babState_struct, 26
getGomory, 131	answerSolver_, 27
getGreedyCover, 132	haveAnswer_, 27
getGreedyEquality, 132	majorStatus_, <mark>27</mark>
getIPPAction, 130	minorStatus_, 27
getKnapsack, 131	where_, 27
getMir, 131	CbcGenCtlBlk::cbcParamsInfo_struct, 353
getProbing, 130	first_, 353
getRedSplit, 131	last_, 353
getRounding, 132	CbcGenCtlBlk::chooseStrongCtl_struct, 433
getTreeLocal, 132	numBeforeTrust_, 433
getTwomir, 131	numStrong_, 433
goodModel_, 136	shadowPriceMode_, 433
IPPControl, 126	CbcGenCtlBlk::debugSolInfo_struct, 439
lastMpsIn_, 134	numCols_, 440
lastSolnOut_, 135	values_, 440
logLevel, 134	CbcGenCtlBlk::djFixCtl_struct, 440
message, 133	action_, 440
messageHandler, 134	threshold_, 440
model_, 136	CbcGenCtlBlk::genParamsInfo_struct, 441
osiParams_, 135	first_, 441
paramVec_, 135	last_, 441
paramsProcessed_, 135	CbcGenCtlBlk::osiParamsInfo_struct, 486
passInMessageHandler, 133	first_, 486
printBaBStatus, 133	last_, 486
printMask_, 135	CbcGenMessages.hpp
printMode_, 135	CbcGenMsgCode, 521
printOpt_, 134	CbcGenMsgCode
priorityAction_, 137	CbcGenMessages.hpp, 521
setBaBStatus, 133	CbcGenParam, 139
setByUser_, 136	\sim CbcGenParam, 143
setCliqueAction, 130	CbcGenParam, 142, 143
setCombineAction, 132	CbcGenParamCode, 140
setCutDepth, 130	CbcGenParam, 142, 143
setFPumpAction, 131	clone, 143
setFlowAction, 130	obj, 143
setGomoryAction, 131	operator=, 143
setGreedyCoverAction, 132	paramCode, 143
setGreedyEqualityAction, 132	setObj, 143
setIPPAction, 130	setParamCode, 143
setKnapsackAction, 131	CbcGenParamCode
setLogLevel, 134	CbcGenParam, 140

ChaCanParamilitiia 21	lostPunDoon 154
CbcGenParamUtils, 21	lastRunDeep_, 154
addCbcGenParams, 21	minDistanceToRun_, 154
doBaCParam, 21	model_, 152
doDebugParam, 21	numCouldRun, 152
doExitParam, 21	numCouldRun_, 154
doHelpParam, 21	numInvocationsInDeep_, 154
doImportParam, 21	numInvocationsInShallow_, 154
doNothingParam, 21	numRuns, 152
doPrintMaskParam, 21	numRuns_, 154
doSolutionParam, 22	numberNodes, 149
doUnimplementedParam, 22	numberNodes_, 153
doVersionParam, 22	numberNodesDone_, 155
loadGenParamObj, 21	numberSolutionsFound, 150
pushCbcGenCutParam, 22	numberSolutionsFound_, 155
pushCbcGenDblParam, 22	operator=, 148
pushCbcGenIntParam, 22	printDistanceToNodes, 152
pushCbcGenKwdParam, 22	randomNumberGenerator_, 153
pushCbcGenStrParam, 22	resetModel, 148
readSolution, 21	runNodes_, 154
saveSolution, 21	setDecayFactor, 151
CbcGenParamUtils::addCbcGenParams	setFeasibilityPumpOptions, 150
CbcGenCtlBlk, 134	setFractionSmall, 150
CbcGeneral, 137	setHeuristicName, 151
~CbcGeneral, 138	setHowOftenShallow, 152
CbcGeneral, 138	setInputSolution, 151
CbcGeneral, 138	setMinDistanceToRun, 152
clone, 138	setModel, 148
createCbcBranch, 138	setModelOnly, 150
feasibleRegion, 138	setNumberNodes, 149
infeasibility, 138	setSeed, 151
operator=, 138	setShallowDepth, 151
redoSequenceEtc, 138	setSwitches, 149
CbcHeuristic, 143	setWhen, 149
~CbcHeuristic, 148	setWhereFrom, 151
canDealWithOdd, 151	shallowDepth_, 154
CbcHeuristic, 148	shouldHeurRun, 152
CbcHeuristic, 148	shouldHeurRun_randomChoice, 152
clone, 148	smallBranchAndBound, 150
cloneBut, 152	solution, 148
debugNodes, 152	solution2, 148
decayFactor_, 153	switches, 149
exitNow, 149	switches_, 153
feasibilityPumpOptions, 150	validate, 149
feasibilityPumpOptions_, 153	when, 149
fractionSmall, 150	when , 153
fractionSmall_, 153	whereFrom, 151
generateCpp, 150, 151	whereFrom , 153
getSeed, 151	CbcHeuristicCrossover, 155
heuristicName, 151	~CbcHeuristicCrossover, 156
heuristicName_, 153	attempts_, 157
howOften_, 153	CbcHeuristicCrossover, 156
howOftenShallow_, 154	CbcHeuristicCrossover, 156
incrementNumberSolutionsFound, 150	
	clone, 156
inputSolution_, 155	generateCpp, 156

numberSolutions_, 157	fullDWEverySoOften_, 188
operator=, 156	functionPointer_, 186
random_, 157	generateCpp, 181
resetModel, 156	getCurrentNumberNeeded, 184
setModel, 157	getCurrentNumberNodes, 184
setNumberSolutions, 157	getNumberNeeded, 183
solution, 157	getNumberNodes, 184
useNumber_, 157	heuristicCallBack, 181
CbcHeuristicDINS, 157	howOften , 188
~CbcHeuristicDINS, 159	initialLower, 184
CbcHeuristicDINS, 159	initialUpper, 185
CbcHeuristicDINS, 159	intArray_, 186
clone, 159	intArrays, 185
generateCpp, 159	intsInBlock, 185
howOften_, 160	
localSpace , 161	intsInBlock_, 188 keepContinuous, 189
• —	· —
maximumKeepSolutions_, 160	lastObjective_, 186
numberIntegers_, 161	maximumDW_, 189
numberKeptSolutions_, 160	nNeeded_, 190
numberSolutions_, 160	nNeededBase_, 190
numberSuccesses_, 160	nNodes_, 190
numberTries_, 160	nNodesBase_, 190
operator=, 159	numberBadPasses_, 190
resetModel, 159	numberBlocks, 182
setConstraint, 160	numberBlocks_, 189
setHowOften, 160	numberColumnsDW, 182, 183
setMaximumKeep, 160	numberColumnsDW_, 187
setModel, 159	numberDW_, 189
solution, 159	numberDWTimes, 183
solutionFix, 160	numberDWTimes_, 189
values_, 161	numberMasterColumns_, 189
CbcHeuristicDW, 176	numberMasterRows_, 189
∼CbcHeuristicDW, 181	numberPasses_, 188
affinity_, 188	objectiveDW, 183
backwardRow_, 187	objectiveDW_, 187
bestObjective, 182	objectiveValue, 185
bestObjective_, 186	objectiveValueWhen, 182
bestSolution, 182	operator=, 181
bestSolution_, 186	pass, 185
CbcHeuristicDW, 181	pass_, 189
CbcHeuristicDW, 181	passInContinuousSolution, 182
clone, 181	passInSolution, 182
columnsInBlock, 185	phase, 185
columnsInBlock , 188	phase_, 189
continuousSolution, 183	random , 187
continuousSolution_, 186	resetModel, 181
DWModel, 182	rowsInBlock , 188
doubleArray_, 186	saveLower_, 187
doubleArrays, 185	saveUpper_, 187
dwBlock_, 187	setCurrentNumberNeeded, 183
dwSolver_, 186	setCurrentNumberNeeded, 763
fingerPrint , 188	setHowOften, 184
fixedDj, 183	setModel, 182
fixedDj., 186	setNumberBadPasses, 183
11XGUDJ_, 100	sentumberbaul asses, 103

setNumberNeeded, 183	validate, 164
setNumberNodes, 184	vbRowIndex_, 166
setNumberPasses, 183	CbcHeuristicDiveCoefficient, 166
setProposalActions, 182	~CbcHeuristicDiveCoefficient, 167
setTargetObjective, 184	CbcHeuristicDiveCoefficient, 167
sizeFingerPrint_, 189	CbcHeuristicDiveCoefficient, 167
solution, 182	clone, 167
solveState_, 190	generateCpp, 168
solver, 182	operator=, 167
solver_, 186	selectVariableToBranch, 168
startColumnBlock, 185	CbcHeuristicDiveFractional, 168
startColumnBlock_, 188	~CbcHeuristicDiveFractional, 169
startRowBlock_, 188	CbcHeuristicDiveFractional, 169
targetObjective_, 185	CbcHeuristicDiveFractional, 169
weights_, 187	clone, 169
whichColumnBlock, 184	generateCpp, 169
whichColumnBlock , 187	operator=, 169
whichRowBlock, 184	selectVariableToBranch, 169
whichRowBlock , 187	CbcHeuristicDiveGuided, 170
CbcHeuristicDive, 161	~CbcHeuristicDiveGuided, 170
~CbcHeuristicDive, 163	canHeuristicRun, 171
binVarIndex_, 166	CbcHeuristicDiveGuided, 170
canHeuristicRun, 165	CbcHeuristicDiveGuided, 170
CbcHeuristicDive, 163	clone, 171
CbcHeuristicDive, 163	generateCpp, 171
clone, 163	operator=, 171
downArray_, 166	selectVariableToBranch, 171
downLocks_, 165	CbcHeuristicDiveLineSearch, 171
fathom, 164	~CbcHeuristicDiveLineSearch, 172
fixOtherVariables, 165	CbcHeuristicDiveLineSearch, 172
generateCpp, 163	CbcHeuristicDiveLineSearch, 172
initializeData, 165	clone, 172
matrix_, 165	generateCpp, 172
matrixByRow , 165	operator=, 172
maxIterations_, 166	selectVariableToBranch, 172
maxSimplexIterations, 164	CbcHeuristicDivePseudoCost, 173
•	
maxSimplexIterations_, 166	~CbcHeuristicDivePseudoCost, 174
maxSimplexIterationsAtRoot_, 166	CbcHeuristicDivePseudoCost, 174
maxTime_, 166	CbcHeuristicDivePseudoCost, 174
operator=, 163	clone, 174
percentageToFix_, 166	fixOtherVariables, 174
reducedCostFix, 165	generateCpp, 174
resetModel, 163	initializeData, 174
selectBinaryVariables, 164	operator=, 174
selectVariableToBranch, 165	selectVariableToBranch, 174
setMaxIterations, 164	CbcHeuristicDiveVectorLength, 175
setMaxSimplexIterations, 164	~CbcHeuristicDiveVectorLength, 176
setMaxSimplexIterationsAtRoot, 165	CbcHeuristicDiveVectorLength, 175
setMaxTime, 165	CbcHeuristicDiveVectorLength, 175
setModel, 164	clone, 176
setPercentageToFix, 164	generateCpp, 176
solution, 164	operator=, 176
upArray_, 166	selectVariableToBranch, 176
upLocks_, 166	CbcHeuristicDynamic3, 190

~CbcHeuristicDynamic3, 191	setModel, 195
canDealWithOdd, 192	setReducedCostMultiplier, 198
CbcHeuristicDynamic3, 191	setRelativeIncrement, 196
CbcHeuristicDynamic3, 191	setWeightFactor, 197
clone, 191	solution, 195
resetModel, 192	startTime_, 199
setModel, 191	weightFactor, 197
solution, 191	weightFactor_, 199
CbcHeuristicFPump, 192	CbcHeuristicGreedyCover, 201
~CbcHeuristicFPump, 195	~CbcHeuristicGreedyCover, 202
absoluteIncrement, 196	algorithm, 203
absoluteIncrement_, 199	algorithm_, 203
accumulate, 198	CbcHeuristicGreedyCover, 202
accumulate_, 200	CbcHeuristicGreedyCover, 202
artificialCost, 197	clone, 202
artificialCost, 200	generateCpp, 202
CbcHeuristicFPump, 195	gutsOfConstructor, 203
CbcHeuristicFPump, 195	matrix , 203
clone, 195	numberTimes, 203
defaultRounding, 197	numberTimes_, 203
defaultRounding_, 199	operator=, 202
fakeCutoff, 196	originalNumberRows, 203
fakeCutoff , 199	resetModel, 202
fixOnReducedCosts, 198	setAlgorithm, 203
fixOnReducedCosts_, 200	setModel, 202
generateCpp, 195	setNumberTimes, 203
initialWeight, 197	solution, 202
_	
initialWeight_, 199	validate, 202
iterationRatio, 197	CbcHeuristicGreedyEquality, 203
iterationRatio_, 200 maximumPasses, 198	~CbcHeuristicGreedyEquality, 205
	algorithm, 206
maximumPasses_, 200 maximumRetries, 198	algorithm_, 206
•	CbcHeuristicGreedyEquality, 205
maximumRetries_, 200	CbcHeuristicGreedyEquality, 205
maximumTime, 196	clone, 205
maximumTime_, 199	fraction, 206
operator=, 195	fraction_, 206
reducedCostMultiplier, 199	generateCpp, 205
reducedCostMultiplier_, 200	gutsOfConstructor, 206
relative Increment, 196	matrix_, 206
relativeIncrement_, 199	numberTimes, 206
resetModel, 195	numberTimes_, 206
roundExpensive_, 200	operator=, 205
setAbsoluteIncrement, 196	originalNumberRows_, 206
setAccumulate, 198	resetModel, 205
setArtificialCost, 197	setAlgorithm, 206
setDefaultRounding, 196	setFraction, 206
setFakeCutoff, 196	setModel, 205
setFixOnReducedCosts, 198	setNumberTimes, 206
setInitialWeight, 197	solution, 205
setIterationRatio, 197	validate, 205
setMaximumPasses, 197	CbcHeuristicGreedySOS, 207
setMaximumRetries, 198	\sim CbcHeuristicGreedySOS, 208
setMaximumTime, 196	algorithm, 209

algorithm_, 209	CbcHeuristicNaive, 216
CbcHeuristicGreedySOS, 208	CbcHeuristicNaive, 216
CbcHeuristicGreedySOS, 208	clone, 216
clone, 208	generateCpp, 216
generateCpp, 208	large_, 217
gutsOfConstructor, 209	largeValue, 217
matrix_, 209	operator=, 216
numberTimes, 209	resetModel, 216
numberTimes_, 209	setLargeValue, 217
operator=, 208	setModel, 216
originalNumberRows, 209	solution, 216
originalRhs_, 209	CbcHeuristicNode, 217
resetModel, 209	~CbcHeuristicNode, 217
setAlgorithm, 209	avgDistance, 218
setModel, 208	CbcHeuristicNode, 217
setNumberTimes, 209	CbcHeuristicNode, 217
solution, 208	distance, 218
validate, 208	minDistance, 218
CbcHeuristicJustOne, 210	minDistancelsSmall, 218
~CbcHeuristicJustOne, 211	CbcHeuristicNodeList, 218
addHeuristic, 212	~CbcHeuristicNodeList, 218
•	append, 218
CbcHeuristicJustOne, 211	• • •
CbcHeuristicJustOne, 211	CbcHeuristicNodeList, 218
clone, 211	CbcHeuristicNodeList, 218
generateCpp, 211	node, 219
heuristic_, 212	operator=, 218
normalizeProbabilities, 212	size, 219
numberHeuristics_, 212	CbcHeuristicPartial, 219
operator=, 211	~CbcHeuristicPartial, 220
probabilities_, 212	CbcHeuristicPartial, 220
resetModel, 211	CbcHeuristicPartial, 220
selectVariableToBranch, 211	clone, 220
setModel, 211	fixPriority_, 221
solution, 211	generateCpp, 220
validate, 212	operator=, 220
CbcHeuristicLocal, 212	resetModel, 220
\sim CbcHeuristicLocal, 213	setFixPriority, 221
CbcHeuristicLocal, 213	setModel, 220
CbcHeuristicLocal, 213	shouldHeurRun, 221
clone, 213	solution, 220
generateCpp, 214	validate, 221
matrix_, 214	CbcHeuristicPivotAndFix, 221
numberSolutions_, 214	\sim CbcHeuristicPivotAndFix, 222
operator=, 213	CbcHeuristicPivotAndFix, 222
resetModel, 214	CbcHeuristicPivotAndFix, 222
setModel, 214	clone, 222
setSearchType, 214	generateCpp, 222
solution, 214	operator=, 222
solutionFix, 214	resetModel, 222
swap_, 214	setModel, 222
used, 214	solution, 223
used_, 215	CbcHeuristicProximity, 223
CbcHeuristicNaive, 215	~CbcHeuristicProximity, 224
\sim CbcHeuristicNaive, 216	CbcHeuristicProximity, 224

CbcHeuristicProximity, 224	resetModel, 227
clone, 224	setModel, 227
feasibilityPump, 225	solution, 227
generateCpp, 224	CbcHeuristicVND, 233
increment , 225	∼CbcHeuristicVND, 234
numberSolutions , 225	baseSolution, 235
operator=, 224	baseSolution_, 236
resetModel, 224	CbcHeuristicVND, 234
setIncrement, 225	CbcHeuristicVND, 234
setModel, 224	clone, 234
solution, 224	generateCpp, 234
used, 225	howOften_, 235
used_, 225	k_, 236
CbcHeuristicRENS, 227	kmax_, 236
~CbcHeuristicRENS, 228	lastNode_, 235
CbcHeuristicRENS, 228	nDifferent_, 236
CbcHeuristicRENS, 228	numberSolutions_, 235
clone, 228	numberSuccesses_, 235
numberTries_, 229	numberTries_, 235
operator=, 228 rensType_, 229	operator=, 234 resetModel, 234
	•
resetModel, 228	setHowOften, 235
setModel, 228	setModel, 235
setRensType, 229	solution, 235
solution, 229	solutionFix, 235
CbcHeuristicRINS, 229	stepSize_, 236
~CbcHeuristicRINS, 231	Chaldiat Proper 007
CbcHeuristicRINS, 231	~CbcldiotBranch, 237
CbcHeuristicRINS, 231	buildCut, 238
clone, 231	CbcldiotBranch, 237
generateCpp, 231	CbcldiotBranch, 237
howOften_, 232	clone, 237
lastNode_, 232	createCbcBranch, 238
numberSolutions_, 232	feasibleRegion, 238
numberSuccesses_, 232	infeasibility, 238
numberTries_, 232	initializeForBranching, 238
operator=, 231	operator=, 238
resetModel, 231	randomNumberGenerator_, 238
setHowOften, 231	savedRandomNumberGenerator_, 238
setLastNode, 232	CbcIntParam
setModel, 231	CbcModel, 272
setSolutionCount, 232	CbcIntegerBranchingObject, 239
solution, 231	\sim CbcIntegerBranchingObject, 240
solutionFix, 231	branch, 241
stateOfFixing_, 232	CbcIntegerBranchingObject, 240
used, 231	CbcIntegerBranchingObject, 240
used_, 232	clone, 241
CbcHeuristicRandRound, 225	compareBranchingObject, 242
\sim CbcHeuristicRandRound, 226	down_, 242
CbcHeuristicRandRound, 226	downBounds, 241
CbcHeuristicRandRound, 226	fillPart, 241
clone, 226	fix, 241
generateCpp, 227	operator=, 241
operator=, 226	print, 241

setDownBounds, 241	CbcLotsizeBranchingObject, 251
setUpBounds, 242	\sim CbcLotsizeBranchingObject, 253
tighten, 241	branch, 253
type, 242	CbcLotsizeBranchingObject, 252, 253
up_, 242	CbcLotsizeBranchingObject, 252, 253
upBounds, 241	clone, 253
CbcIntegerPseudoCostBranchingObject, 242	compareBranchingObject, 253
~CbcIntegerPseudoCostBranchingObject, 244	down_, 254
branch, 244	operator=, 253
CbcIntegerPseudoCostBranchingObject, 244	print, 253
CbcIntegerPseudoCostBranchingObject, 244	type, 253
changeInGuessed, 245	up_, 254
changeInGuessed_, 245	CbcMain
clone, 244	CbcModel.hpp, 532
compareBranchingObject, 245	CbcMain0
operator=, 244	CbcModel.hpp, 532
setChangeInGuessed, 245	CbcMain1
type, 245	CbcModel.hpp, 532
CbcLinked.hpp	CbcMessage, 254
approximateSolution, 528	CbcMessage, 255
CbcLongCliqueBranchingObject, 245	CbcMessage, 255
~CbcLongCliqueBranchingObject, 246	CbcMessage.hpp
branch, 247	CBC Message, 529
CbcLongCliqueBranchingObject, 246	Cbc_Message, 323 CbcMipStartIO.hpp
CbcLongCliqueBranchingObject, 246	computeCompleteSolution, 531
clone, 247	readMIPStart, 531
compareBranchingObject, 247	CbcModel, 255
compareOriginalObject, 247	~CbcModel, 273
operator=, 247	addCutGenerator, 296
print, 247	addCuts, 306
type, 247	addCuts1, 306
CbcLotsize, 247	addHeuristic, 297
~CbcLotsize, 249	AddIntegers, 275
bound, 251	addObjects, 276
canDoHeuristics, 251	addUpdateInformation, 274
CbcLotsize, 249	addedCuts, 308
CbcLotsize, 249	adjustHeuristics, 307
clone, 249	allDynamic, 310
columnNumber, 250	analyzeObjective, 275
createCbcBranch, 249	assignSolver, 302
feasibleRegion, 249	bestSolution, 291
findRange, 250	branchAndBound, 273
floorCeiling, 250	branchingMethod, 295
infeasibility, 249	canStopOnGap, 280
modelSequence, 250	CbcDblParam, 272
notPreferredNewFeasible, 250	CbcIntParam, 272
numberRanges, 251	CbcModel, 273
operator=, 249	CbcModel, 273
originalLowerBound, 250	checkModel, 302
originalUpperBound, 251	checkSolution, 289
preferredNewFeasible, 250	chooseBranch, 306
rangeType, 251	clearContinuousSolver, 303
resetBounds, 250	clearNumberGlobalViolations, 293
setModelSequence, 250	cliquePseudoCosts, 307

clone, 302	getEmptyBasis, 306
conflictCut, 283	getEventHandler, 298
continuousPriority, 309	getExtraNodeCount, 284
continuousSolution, 288	getHeuristicFractionGap, 279
continuousSolver, 303	getHeuristicGap, 279
convertToDynamic, 307	getInfeasibilityWeight, 278
createContinuousSolver, 303	getInfinity, 288
currentDepth, 282	getIntParam, 277
currentNode, 308	getIntegerTolerance, 278
currentNumberCuts, 308	getIterationCount, 284
currentSolution, 289	getMIPStart, 310
cutGenerator, 296	getMatrixByCol, 287
cutGenerators, 296	getMatrixByRow, 287
cutModifier, 295	getMaximumCutPasses, 280
dealWithEventHandler, 289	getMaximumCutPassesAtRoot, 280
defaultHandler, 299	getMaximumNodes, 277
deleteObjects, 276	getMaximumSeconds, 278
deleteSavedSolution, 292	getMaximumSolutions, 277
deleteSolutions, 305	getMinimizationObjValue, 290
doCutsNow, 281	getMinimumDrop, 280
doHeuristicsAtRoot, 307	getMultipleRootTries, 300
doOneNode, 274	getNodeCount, 284
fastNodeDepth, 309	getNodeCount2, 305
feasibleSolution, 289	getNumCols, 285
fillPseudoCosts, 307	getNumElements, 285
findCliques, 274	getNumRows, 285
findIntegers, 276	getNumberHeuristicSolutions, 292
flipModel, 276	getNumberThreads, 304
generateCpp, 310	getObjCoefficients, 287
getAllowableFractionGap, 279	getObjSense, 287
getAllowableGap, 279	getObjValue, 290
getAllowablePercentageGap, 279	getPreferredWay, 281
getApplicationData, 298	getPrintingMode, 278
getBestPossibleObjValue, 290	getRandomSeed, 300
getCbcColLower, 288	getReducedCost, 290
getCbcColSolution, 288	getRightHandSide, 286
getCbcColUpper, 288	getRowActivity, 290
getCbcReducedCost, 288	getRowLower, 286
getCbcRowActivity, 288	getRowPrice, 290
getCbcRowLower, 288	getRowRange, 286
getCbcRowPrice, 288	getRowSense, 286
getCbcRowUpper, 288	getRowUpper, 287
getColLower, 286	getSolutionCount, 291
getColSolution, 290	getSolverObjValue, 291
getColUpper, 286	getStopNumberIterations, 293
getContinuousInfeasibilities, 292	getThreadMode, 304
getContinuousObjective, 292	globalCuts, 308
getCurrentMinimizationObjValue, 290	goToDantzig, 302
getCurrentObjValue, 290	gutsOfCopy, 303
getCurrentPassNumber, 280	gutsOfDestructor, 303
getCurrentSeconds, 278	gutsOfDestructor2, 303
getCutoff, 277	haveMultiThreadSupport, 304
getCutoffIncrement, 280	heuristic, 297
getDblParam, 277	heuristicModel, 293

hotstartPriorities, 307	newLanguage, 299
hotstartSolution, 307	nodeComparison, 294
howOftenGlobalScan, 283	normalSolver, 300
incrementExtra, 309	numberAnalyzeIterations, 282
incrementIterationCount, 284	numberBeforeTrust, 281
incrementNodeCount, 284	numberCutGenerators, 296
incrementStrongInfo, 309	numberExtralterations, 309
incrementSubTreeStopped, 294	numberGlobalViolations, 293
incrementUsed, 289	numberHeuristics, 297
initialSolve, 273	numberIntegers, 285
integerPresolve, 275	numberObjects, 276
integerPresolveThisModel, 275	numberPenalties, 282
integerType, 285, 286	numberRowsAtContinuous, 285
integerVariable, 285	numberSavedSolutions, 291
isAbandoned, 283	numberStoppedSubTrees, 294
isBinary, 287	numberStrong, 281
isContinuous, 287	numberStrongIterations, 308
isContinuousUnbounded, 283	object, 276
isFreeBinary, 287	objects, 276
isInitialSolveAbandoned, 285	operator=, 302
isInitialSolveProvenDualInfeasible, 285	originalColumns, 283
isInitialSolveProvenOptimal, 285	originalModel, 275
isInitialSolveProvenPrimalInfeasible, 285	ownObjects, 302
isInteger, 287	parallelMode, 304
isIntegerNonBinary, 287	parentModel, 297
isLocked, 304	passInEventHandler, 298
isNodeLimitReached, 283	passInMessageHandler, 298
isProvenDualInfeasible, 283	passInPriorities, 298
isProvenInfeasible, 283	passInSolverCharacteristics, 298
isProvenOptimal, 283	passInSubTreeModel, 294
isSecondsLimitReached, 284	passInTreeHandler, 294
isSolutionLimitReached, 284	penaltyScaleFactor, 282
lastHeuristic, 297	phase, 292
lockThread, 304	previousBounds, 306
logLevel, 299	printFrequency, 283
makeGlobalCut, 274	priority, 298
makeGlobalCuts, 274	probingInfo, 308
makePartialCut, 274	problemFeasibility, 294
masterThread, 304	problemType, 282
maximumNumberIterations, 308	pseudoShadow, 307
maximumRows, 293	randomNumberGenerator, 308
maximumSavedSolutions, 291	redoWalkBack, 310
maximumSecondsReached, 278	reducedCostFix, 305
mergeModels, 305	referenceSolver, 303
messageHandler, 299	reserveCurrentSolution, 290
messages, 299	resetModel, 303
messagesPointer, 299	resetToReferenceSolver, 303
modelOwnsSolver, 302	resolve, 274, 305
modifiableObject, 276	resolveAfterTakeOffCuts, 293
moreSpecialOptions, 301	rootObjectiveAfterCuts, 292
moreSpecialOptions2, 301	saveBestSolution, 305
movelnfo, 303	saveExtraSolution, 305
moveToModel, 305	saveModel, 275
mutableStrongInfo, 309	saveReferenceSolver, 303
	23.2.2.2.2.2.2.3.

10.1.1	
savedSolution, 291	setNumberHeuristicSolutions, 292
savedSolutionObjective, 292	setNumberHeuristics, 297
sayEventHappened, 300	setNumberObjects, 276
searchStrategy, 295	setNumberPenalties, 282
secondaryStatus, 284	setNumberStrong, 281
setAllowableFractionGap, 279	setNumberStrongIterations, 308
setAllowableGap, 278	setNumberThreads, 304
setAllowablePercentageGap, 279	setObjSense, 292
setApplicationData, 298	setObjValue, 291
setBestObjectiveValue, 289	setObjectiveValue, 307
setBestSolution, 289, 291	setOptionalInteger, 276
setBestSolutionBasis, 310	setOriginalColumns, 283
setBranchingMethod, 295	setParentModel, 297
setContinuousInfeasibilities, 292	setPenaltyScaleFactor, 282
setContinuousObjective, 292	setPointers, 305
setContinuousPriority, 309	setPreferredWay, 281
setCurrentPassNumber, 281	setPrintFrequency, 283
setCutModifier, 295	setPrintingMode, 278
setCutoff, 277	setProblemFeasibility, 294
setCutoffAsConstraint, 301	setProblemStatus, 284
setCutoffIncrement, 279	setProblemType, 282
setDblParam, 277	setRandomSeed, 300
setDefaultHandler, 299	setResolveAfterTakeOffCuts, 293
setFastNodeDepth, 309	setSearchStrategy, 296
setHeuristicFractionGap, 279	setSecondaryStatus, 285
setHeuristicGap, 279	setSolutionCount, 291
setHeuristicModel, 294	setSpecialOptions, 299
setHotstartSolution, 280	setStateOfSearch, 295
setHowOftenGlobalScan, 282	setStopNumberIterations, 293
setInfeasibilityWeight, 278	setStoredRowCuts, 310
setInfoInChild, 305	setStrategy, 297
setIntParam, 277	setStrongStrategy, 296
setIntegerTolerance, 278	setTemporaryPointer, 301
setLanguage, 299	setTestSolution, 289
setLastHeuristic, 297	setThreadMode, 304
setLogLevel, 299	setTypePresolve, 295
setMIPStart, 310	setUseElapsedTime, 301
setMaximumCutPasses, 280	•
setMaximumCutPassesAtRoot, 280	setWhenCuts, 281 solver, 302
setMaximumNodes, 277	solverCharacteristics, 298
setMaximumNumberIterations, 309	specialOptions, 300
setMaximumSavedSolutions, 291	splitModel, 305
setMaximumSeconds, 278	startSplitModel, 305
setMaximumSolutions, 277	stateOfSearch, 295
setMinimizationObjValue, 290	status, 284
setMinimumDrop, 280	storedRowCuts, 309
setModelOwnsSolver, 302	strategy, 296
setMoreSpecialOptions, 300	strongInfo, 309
setMoreSpecialOptions2, 301	strongStrategy, 296
setMultipleRootTries, 300	subTreeModel, 294
setNextRowCut, 308	sumChangeObjective, 293
setNodeComparison, 294	swapSolver, 302
setNumberAnalyzeIterations, 282	synchronizeHandlers, 305
setNumberBeforeTrust, 281	synchronizeModel, 276

synchronizeNumberBeforeTrust, 307	clone, 331
takeOffCuts, 306	compareBranchingObject, 332
temporaryPointer, 301	compareOriginalObject, 331
testSolution, 289	numberBranches, 331
tightenVubs, 275	operator=, 331
topOfTree, 282	print, 331
tree, 294	twoWay, 331
typePresolve, 294	type, 331
unlockThread, 304	CbcNode, 310
useElapsedTime, 301	~CbcNode, 313
usedInSolution, 289	active, 317
usefulInformation, 310	analyze, 315
virginCutGenerator, 296	branch, 315
waitingForMiniBranchAndBound, 300	branchingObject, 317
	- ·
walkback, 304	CbcNode, 313
whenCuts, 281	CbcNode, 313
whichGenerator, 274	checkInfo, 318
workingBasis, 293	checkIsCutoff, 315
zapIntegerInformation, 307	chooseBranch, 313
cbcModel	chooseClpBranch, 315
CbcBranchDecision, 35	chooseDynamicBranch, 314
CbcOsiSolver, 347	chooseOsiBranch, 314
CbcModel.hpp	createInfo, 313
callCbc, 532	decrementCuts, 315
callCbc1, 532	decrementParentCuts, 315
CbcMain, 532	depth, 316
CbcMain0, 532	getState, 317
CbcMain1, 532	guessedObjectiveValue, 316
getIntegerInformation, 532	initializeInfo, 315
setCutAndHeuristicOptions, 532	modifiableBranchingObject, 317
cbcModel_	nodeInfo, 315
CbcOsiSolver, 347	nodeNumber, 317
CbcNWay, 326	nullNodeInfo, 315
∼CbcNWay, <mark>328</mark>	numberBranches, 316
applyConsequence, 328	numberUnsatisfied, 316
CbcNWay, 328	objectiveValue, 316
CbcNWay, 328	onTree, 317
clone, 328	operator=, 313
consequence_, 329	print, 318
createCbcBranch, 328	setActive, 317
feasibleRegion, 328	setBranchingObject, 317
infeasibility, 328	setDepth, 316
members, 329	setGuessedObjectiveValue, 316
members_, 329	setNodeNumber, 317
numberMembers, 329	setNumberUnsatisfied, 316
numberMembers_, 329	setObjectiveValue, 316
operator=, 328	setOnTree, 317
redoSequenceEtc, 329	setState, 317
setConsequence, 328	setSumInfeasibilities, 316
CbcNWayBranchingObject, 329	sumInfeasibilities, 316
~CbcNWayBranchingObject, 331	way, 316
branch, 331	CbcNodeInfo, 318
CbcNWayBranchingObject, 331	~CbcNodeInfo, 321
CbcNWayBranchingObject, 331	active_, 326

addCuts, 323			clone, 335
allActivated, 325			createBranch, 336
allBranchesGone, 32	.2		createCbcBranch, 335
applyBounds, 322			createOsiBranch, 336
applyToModel, 321			createUpdateInformation, 337
branchedOn, 323			feasibleRegion, 335
buildRowBasis, 322			floorCeiling, 336
CbcNodeInfo, 321			id, 337
CbcNodeInfo, 321			id_, 338
clone, 322			infeasibility, 335
cuts, 324			initializeForBranching, 338
cuts_, 326			model, 338
deactivate, 324			model_, 338
decrement, 322			notPreferredNewFeasible, 336
decrementCuts, 323			operator=, 335
decrementParentCut	c 32/		optionalObject, 337
deleteCut, 323	5, 524		position, 337
			•
deleteCuts, 323			position_, 338 preferredNewFeasible, 336
increment, 322			preferredWay, 338
incrementCuts, 324	intingToThio 200		
incrementNumberPo	-		preferredWay_, 338
incrementParentCuts	5, 324		redoSequenceEtc, 338
initializeInfo, 322			resetBounds, 336
mark, 325			setId, 337
marked, 325			setModel, 337
mutableOwner, 324			setPosition, 337
nodeNumber, 324			setPreferredWay, 338
nodeNumber_, 326			solverBranch, 336
nullOwner, 324			updateInformation, 337
nullParent, 323		Cbc	ObjectUpdateData, 339
numberBranchesLeft			~CbcObjectUpdateData, 340
numberBranchesLeft	_, 326		branchingValue_, 341
numberCuts, 324			CbcObjectUpdateData, 340
numberCuts_, 326			CbcObjectUpdateData, 340
numberPointingToTh			change_, 340
numberPointingToTh	is_, 325		cutoff_, 341
numberRows_, 326			intDecrease_, 340
owner, 324			object_, 340
owner_, 325			objectNumber_, 340
parent, 323			operator=, 340
parent_, 325			originalObjective_, 341
parentBranch, 325			status_, 340
parentBranch_, 325			way_, 340
setNodeNumber, 324	1	Cbc	OsiParam, 341
setNumberBranches	Left, 322		∼CbcOsiParam, 345
setNumberCuts, 324			CbcOsiParam, 344, 345
setNumberPointingTo	This, 323		CbcOsiParamCode, 343
throwAway, 323			CbcOsiParam, 344, 345
unmark, 325			clone, 345
unsetParentBasedDa	ata, <mark>325</mark>		obj, 345
CbcObject, 332			operator=, 345
∼CbcObject, 334			paramCode, 345
CbcObject, 334			setObj, 345
CbcObject, 334			setParamCode, 345

CbcOsiParamCode	CbcParameterType
CbcOsiParam, 343	CbcParam.hpp, 535
CbcOsiParamUtils, 22	cbcParams_
addCbcOsiParams, 22	CbcGenCtlBlk, 135
loadOsiParamObj, 22	CbcPartialNodeInfo, 354
pushCbcOsiDbl, 22	∼CbcPartialNodeInfo, 355
pushCbcOsiHint, 22	applyBounds, 355
pushCbcOsiInt, 22	applyToModel, 355
pushCbcOsiKwd, 22	basisDiff, 355
pushCbcOsiLogLevel, 22	basisDiff , 356
setOsiSolverInterfaceDefaults, 22	buildRowBasis, 355
CbcOsiSolver, 346	CbcPartialNodeInfo, 355
~CbcOsiSolver, 347	CbcPartialNodeInfo, 355
cbcModel, 347	clone, 355
cbcModel , 347	newBounds, 356
CbcOsiSolver, 347	newBounds , 356
CbcOsiSolver, 347	numberChangedBounds, 356
clone, 347	numberChangedBounds_, 356
operator=, 347	variables, 355
setCbcModel, 347	variables , 356
CbcParam, 348	CbcRangeCompare
~CbcParam, 350	CbcBranchBase.hpp, 510
addHelp, 350	CbcRounding, 356
append, 350	~CbcRounding, 358
CbcParam, 350	CbcRounding, 357
CbcParam, 350	CbcRounding, 357
checkDoubleParameter, 351	clone, 358
currentOption, 352	down_, 359
displayThis, 352	equal_, 359
doubleParameter, 351	generateCpp, 358
doubleValue, 352	matrix_, 359
indexNumber, 353	matrixByRow_, 359
intParameter, 351	operator=, 358
intValue, 352	resetModel, 358
matchName, 351	seed, 359
matches, 352	setModel, 358
	setSeed, 358
name, 350	
operator=, 350	solution, 358
parameterOption, 351	up_, 359
printLongHelp, 353	validate, 358
printOptions, 352	CbcRowCuts, 359
printString, 353	~CbcRowCuts, 360
setCurrentOption, 352	addCutlfNotDuplicate, 360
setDoubleParameter, 350, 351	addCutlfNotDuplicateWhenGreedy, 360
setDoubleValue, 352	addCuts, 360
setIntParameter, 351	CbcRowCuts, 360
setIntValue, 352	CbcRowCuts, 360
setLonghelp, 353	cut, 360
setStringValue, 352	eraseRowCut, 360
shortHelp, 350	numberCuts, 360
stringValue, 352	operator=, 360
type, 352	rowCutPtr, 360
CbcParam.hpp	sizeRowCuts, 360
CbcParameterType, 535	CbcSOS, 390

\sim CbcSOS, 392	clone, 364
canDoHeuristics, 394	columnNumber, 365
CbcSOS, 392	columnNumber_, 366
CbcSOS, 392	createCbcBranch, 364
clone, 392	feasibleRegion, 364, 365
createCbcBranch, 392	fillCreateBranch, 365
createUpdateInformation, 393	infeasibility, 364
feasibleRegion, 392	operator=, 364
infeasibility, 392	originalLower_, 366
members, 393	originalLowerBound, 365
mutableMembers, 394	originalUpper_, 366
mutableWeights, 394	originalUpperBound, 365
numberMembers, 393	osiObject, 364
numberTimesDown, 393	preferredWay_, 366
numberTimesUp, 394	resetBounds, 365
operator=, 392	resetSequenceEtc, 365
osiObject, 393	setBreakEven, 366
redoSequenceEtc, 393	setColumnNumber, 365
setIntegerValued, 394	setOriginalLowerBound, 365
setNumberMembers, 394	setOriginalUpperBound, 365
solverBranch, 393	solverBranch, 365
sosType, 393	CbcSimpleIntegerDynamicPseudoCost, 366
updateInformation, 393	~CbcSimpleIntegerDynamicPseudoCost, 371
weights, 394	addToSumDownChange, 374
CbcSOSBranchingObject, 394	addToSumDownCost, 374
~CbcSOSBranchingObject, 396	addToSumDownDecrease, 375
branch, 396	addToSumUpChange, 375
CbcSOSBranchingObject, 396	addToSumUpCost, 374
CbcSOSBranchingObject, 396	addToSumUpDecrease, 375
clone, 396	CbcSimpleIntegerDynamicPseudoCost, 371
compareBranchingObject, 397	CbcSimpleIntegerDynamicPseudoCost, 371
compareOriginalObject, 396	clone, 371
computeNonzeroRange, 397	copySome, 372
fix, 396	createCbcBranch, 372
operator=, 396	createUpdateInformation, 372
previousBranch, 396	downDynamicPseudoCost, 373
print, 396	downDynamicPseudoCost , 378
type, 396	downEstimate, 377
CbcSerendipity, 360	downShadowPrice, 373
~CbcSerendipity, 361	downShadowPrice , 378
CbcSerendipity, 361	incrementNumberBeforeTrust, 377
CbcSerendipity, 361	incrementNumberTimesDown, 376
clone, 361	incrementNumberTimesDownInfeasible, 376
generateCpp, 361	incrementNumberTimesUp, 376
operator=, 361	incrementNumberTimesUpInfeasible, 377
resetModel, 362	infeasibility, 372
setModel, 361	lastDownCost_, 379
solution, 362	lastDownDecrease_, 379
CbcSimpleInteger, 362	lastUpCost_, 379
∼CbcSimpleInteger, 364	lastUpDecrease_, 379
breakEven, 366	method, 377
breakEven , 366	method , 380
CbcSimpleInteger, 364	numberBeforeTrust, 377
CbcSimpleInteger, 364	numberBeforeTrust_, 380
Oboomiplemileger, 304	numberbeiore nust_, 300

numberTimesDown, 375	upShadowPrice, 373
numberTimesDown_, 379	upShadowPrice_, 379
numberTimesDownInfeasible, 376	updateAfter, 372
numberTimesDownInfeasible_, 379	updateAfterMini, 372
numberTimesDownLocalFixed_, 380	updateBefore, 372
numberTimesDownTotalFixed_, 380	updateDownDynamicPseudoCost, 373
numberTimesProbingTotal_, 380	updateInformation, 372
numberTimesUp, 376	updateUpDynamicPseudoCost, 373
numberTimesUp_, 379	CbcSimpleIntegerDynamicPseudoCost.hpp
numberTimesUpInfeasible, 376	INFEAS, 539
numberTimesUpInfeasible_, 380	MOD SHADOW, 539
numberTimesUpLocalFixed_, 380	TYPE2, 539
numberTimesUpTotalFixed_, 380	TYPERATIO, 539
operator=, 372	WEIGHT_AFTER, 539
print, 378	WEIGHT BEFORE, 540
same, 378	WEIGHT_PRODUCT, 540
setDownDynamicPseudoCost, 373	CbcSimpleIntegerPseudoCost, 381
setDownInformation, 377	~CbcSimpleIntegerPseudoCost, 382
setDownShadowPrice, 373	CbcSimpleIntegerPseudoCost, 382
setMethod, 377	CbcSimpleIntegerPseudoCost, 382
setNumberBeforeTrust, 377	clone, 382
setNumberDelore Hust, 377 setNumberTimesDown, 376	createCbcBranch, 383
setNumberTimesDownInfeasible, 376	downEstimate, 383
setNumberTimesUp, 376	downPseudoCost, 383
setNumberTimesUpInfeasible, 376	downPseudoCost_, 383
setProbingInformation, 377	infeasibility, 383
setSumDownChange, 374	method, 383
setSumDownCost, 374	method_, 384
setSumDownDecrease, 375	operator=, 382
setSumUpChange, 375	setDownPseudoCost, 383
setSumUpCost, 374	setMethod, 384
setSumUpDecrease, 375 setUpDownSeparator, 374	setUpDownSeparator, 383 setUpPseudoCost, 383
·	•
setUpDynamicPseudoCost, 373	upDownSeparator, 383
setUpInformation, 377	upDownSeparator_, 384
setUpShadowPrice, 373	upEstimate, 383
solverBranch, 372	upPseudoCost, 383
sumDownChange, 374	upPseudoCost_, 384
sumDownChange_, 378	CbcSolver, 384
sumDownCost, 374	~CbcSolver, 386
sumDownCost_, 378	addCutGenerator, 387
sumDownDecrease, 375	addUserFunction, 387
sumDownDecrease_, 379	analyze, 387
sumUpChange, 375	babModel, 388
sumUpChange_, 378	CbcSolver, 386
sumUpCost, 374	CbcSolver, 386
sumUpCost_, 378	cutGeneratorArray, 389
sumUpDecrease, 375	doubleValue, 388
sumUpDecrease_, 379	fillParameters, 387
upDownSeparator, 373	fillValuesInSolver, 387
upDownSeparator_, 378	intValue, 387
upDynamicPseudoCost, 373	model, 388
upDynamicPseudoCost_, 378	numberCutGenerators, 389
upEstimate, 377	numberUserFunctions, 388

operator=, 387	startingObjective, 399
originalCoinModel, 388	startingObjective_, 399
originalSolver, 388	updateInfeasibility, 398
setDoubleValue, 388	value, 399
setIntValue, 388	value_, 399
setOriginalCoinModel, 388	way, 399
setOriginalSolver, 388	way_, 400
setPrinting, 389	CbcStopNow, 400
setReadMode, 389	\sim CbcStopNow, 401
setUserCallBack, 387	callBack, 401
solve, 387	CbcStopNow, 401
startTime, 389	CbcStopNow, 401
updateModel, 387	clone, 402
userFunction, 388	operator=, 402
userFunctionArray, 388	CbcStrategy, 402
CbcSolverAnalyze.hpp	~CbcStrategy, 403
analyze, 541	CbcStrategy, 403
CbcSolverExpandKnapsack.hpp	CbcStrategy, 403
afterKnapsack, 541	clone, 403
expandKnapsack, 541	deletePreProcess, 404
CbcSolverHeuristics.hpp	depth_, 405
crunchlt, 542	fullNodeInfo, 405
doHeuristics, 542	generateCpp, 405
	getNested, 404
fixVubs, 542 CbcSolverUsefulData, 389	•
	partialNodeInfo, 405
branchDirection_, 390	preProcessState, 404
primalSolution_, 390	preProcessState_, 405
priorities_, 390	process, 404
pseudoDown_, 390	process_, 405
pseudoUp_, 390	setNested, 404
sosPriority_, 390	setPreProcessState, 404
CbcStatistics, 397	setupCutGenerators, 404
~CbcStatistics, 398	setupHeuristics, 404
CbcStatistics, 398	setupOther, 404
CbcStatistics, 398	setupPrinting, 404
depth, 399	status, 405
depth_, 400	CbcStrategyDefault, 405
endOfBranch, 398	~CbcStrategyDefault, 407
endingInfeasibility, 399	CbcStrategyDefault, 407
endingInfeasibility_, 400	CbcStrategyDefault, 407
endingObjective, 399	clone, 407
endingObjective_, 399	cutsOnlyAtRoot_, 408
id_, 400	desiredPreProcess, 407
node, 399	desiredPreProcess_, 408
numberIterations, 399	generateCpp, 407
numberIterations_, 400	numberBeforeTrust_, 408
operator=, 398	numberStrong_, 408
parentId_, 400	preProcessPasses, 407
parentNode, 399	preProcessPasses_, 408
print, 398	printLevel_, 408
sayInfeasible, 398	setupCutGenerators, 407
sequence_, 400	setupHeuristics, 407
startingInfeasibility, 399	setupOther, 407
startingInfeasibility_, 400	setupPreProcessing, 407

setupPrinting, 407	empty, 418
CbcStrategyDefaultSubTree, 408	endSearch, 419
~CbcStrategyDefaultSubTree, 409	fixTop, 419
CbcStrategyDefaultSubTree, 409	generateCpp, 418
CbcStrategyDefaultSubTree, 409	getBestPossibleObjective, 419
clone, 409	getMaximumBranching, 420
cutsOnlyAtRoot_, 410	getNumberBranching, 420
numberBeforeTrust_, 410	increaseSpace, 420
numberStrong , 410	lastDepth, 420
parentModel , 410	lastDepth_, 421
printLevel_, 410	lastObjective, 420
setupCutGenerators, 409	lastObjective, 420
setup-out-definerations, 409	lastUnsatisfied, 420
setupOther, 410	lastUnsatisfied_, 421
•	
setupPrinting, 410	maximumBranching_, 421
CbcStrategyNull, 410	maximumNodeNumber, 419
~CbcStrategyNull, 411	maximumNodeNumber_, 421
CbcStrategyNull, 411	newBound_, 421
CbcStrategyNull, 411	newBounds, 420
clone, 411	nodePointer, 419
setupCutGenerators, 411	nodes_, 421
setupHeuristics, 411	numberBranching_, 421
setupOther, 412	operator=, 418
setupPrinting, 412	pop, 418
CbcStrongInfo, 412	push, 418
downMovement, 413	realpop, 419
finishedDown, 413	realpush, 419
finishedUp, 413	rebuild, 418
fix, 414	resetNodeNumbers, 419
numIntInfeasDown, 413	setComparison, 418
numIntInfeasUp, 413	setMaximumBranching, 420
numltersDown, 414	setNumberBranching, 419
numltersUp, 413	size, 418
numObjInfeasDown, 413	top, 418
numObjInfeasUp, 413	CbcTreeLocal, 422
objectNumber, 414	\sim CbcTreeLocal, 423
possibleBranch, 413	CbcTreeLocal, 423
upMovement, 413	CbcTreeLocal, 423
CbcThread, 414	clone, 423
~CbcThread, 414	createCut, 424
CbcThread, 414	deleteCut, 424
CbcThread, 414	empty, 424
CbcTree, 414	endSearch, 424
~CbcTree, 417	generateCpp, 423
addBranchingInformation, 420	maxDiversification, 424
bestAlternate, 419	nodeLimit, 425
bestNode, 418	
branched, 420	operator=, 423 passInSolution, 424
	•
branched_, 421	pop, 423
CbcTree, 417	push, 423
CbcTree, 417	range, 424
cleanTree, 419	refine, 425
clone, 418	reverseCut, 424
comparison_, 421	setMaxDiversification, 424

setNodeLimit, 425	\sim CglTemporary, 432
setRange, 424	CglTemporary, 432
setRefine, 425	CglTemporary, 432
setTimeLimit, 425	clone, 433
setTypeCuts, 424	generateCuts, 432
timeLimit, 424	operator=, 433
top, 423	change_
typeCuts, 424	CbcObjectUpdateData, 340
CbcTreeVariable, 425	changeInGuessed
\sim CbcTreeVariable, 426	CbcDynamicPseudoCostBranchingObject, 98
CbcTreeVariable, 426	CbcIntegerPseudoCostBranchingObject, 245
CbcTreeVariable, 426	changeInGuessed_
clone, 426	CbcDynamicPseudoCostBranchingObject, 99
createCut, 427	CbcIntegerPseudoCostBranchingObject, 245
deleteCut, 427	checkDoubleParameter
empty, 427	CbcParam, 351
endSearch, 427	checkInfeasibility
generateCpp, 427	OsiBiLinear, 446
maxDiversification, 428	checkInfo
nodeLimit, 428	CbcNode, 318
operator=, 426	checkIsCutoff
passInSolution, 427	CbcNode, 315
pop, 427	checkModel
push, 427	CbcModel, 302
range, 427	checkPossible
refine, 428	CbcFathomDynamicProgramming, 108
reverseCut, 427	checkSolution
setMaxDiversification, 428	CbcModel, 289
setNodeLimit, 428	chooseBranch
setRange, 427	CbcModel, 306
setRefine, 428	CbcNode, 313
setTimeLimit, 428	chooseClpBranch
setTypeCuts, 428	CbcNode, 315
timeLimit, 428	chooseDynamicBranch
top, 427	CbcNode, 314
typeCuts, 428	chooseMethod
CbcUser, 428	CbcBranchDecision, 35
~CbcUser, 430	chooseMethod_
canDo, 431	CbcBranchDecision, 36
CbcUser, 430	chooseOsiBranch
CbcUser, 430	CbcNode, 314
clone, 431	chooseStrong_
coinModel, 430	CbcGenCtlBlk, 137
coinModel_, 431	chooseVariable
exportData, 430	OsiChooseStrongSubset, 475
exportSolution, 430	chosen_
fillInformation, 430	OsiBiLinear, 451
importData, 430	cleanDive
name, 431	CbcCompareDefault, 68
operator=, 431	cleanMatrix
solve, 431	OsiSolverLink, 496
stuff, 430	cleanTree
userName_, 431	CbcTree, 419
CglTemporary, 431	clearContinuousSolver

CbcModel, 303	CbcHeuristicDynamic3, 191
clearNumberGlobalViolations	CbcHeuristicFPump, 195
CbcModel, 293	CbcHeuristicGreedyCover, 202
CliqueBranchObj	CbcHeuristicGreedyEquality, 205
CbcBranchingObject.hpp, 512	CbcHeuristicGreedySOS, 208
cliquePseudoCosts	CbcHeuristicJustOne, 211
CbcModel, 307	CbcHeuristicLocal, 213
cliqueType	CbcHeuristicNaive, 216
CbcClique, 57	CbcHeuristicPartial, 220
cliqueType_	CbcHeuristicPivotAndFix, 222
CbcClique, 58	CbcHeuristicProximity, 224
clone	CbcHeuristicRandRound, 226
CbcBranchAllDifferent, 29	CbcHeuristicRENS, 228
CbcBranchCut, 31	CbcHeuristicRINS, 231
CbcBranchDecision, 34	CbcHeuristicVND, 234
CbcBranchDefaultDecision, 37	CbcldiotBranch, 237
CbcBranchDynamicDecision, 39	CbcIntegerBranchingObject, 241
CbcBranchingObject, 43	CbcIntegerPseudoCostBranchingObject, 244
CbcBranchToFixLots, 48	CbcLongCliqueBranchingObject, 247
CbcCbcParam, 53	CbcLotsize, 249
CbcClique, 56	CbcLotsizeBranchingObject, 253
CbcCliqueBranchingObject, 59	CbcModel, 302
CbcCompareBase, 63	CbcNodeInfo, 322
CbcCompareDefault, 66	CbcNWay, 328
CbcCompareDepth, 70	CbcNWayBranchingObject, 331
CbcCompareEstimate, 71	CbcObject, 335
CbcCompareObjective, 72	CbcOsiParam, 345
CbcConsequence, 73	CbcOsiSolver, 347
CbcCutBranchingObject, 78	CbcPartialNodeInfo, 355
CbcCutModifier, 91	CbcRounding, 358
CbcCutSubsetModifier, 92	CbcSerendipity, 361
CbcDummyBranchingObject, 94	CbcSimpleInteger, 364
CbcDynamicPseudoCostBranchingObject, 97	CbcSimpleIntegerDynamicPseudoCost, 371
CbcEventHandler, 102	CbcSimpleIntegerPseudoCost, 382
CbcFathom, 104	CbcSOS, 392
CbcFathomDynamicProgramming, 107	CbcSOSBranchingObject, 396
CbcFeasibilityBase, 111	CbcStopNow, 402
CbcFixingBranchingObject, 112	CbcStrategy, 403
CbcFixVariable, 114	CbcStrategyDefault, 407
CbcFollowOn, 117	CbcStrategyDefaultSubTree, 409
CbcFullNodeInfo, 120	CbcStrategyNull, 411
CbcGeneral, 138	CbcTree, 418
CbcGenParam, 143	CbcTreeLocal, 423
CbcHeuristic, 148	CbcTreeVariable, 426
CbcHeuristicCrossover, 156	CbcUser, 431
CbcHeuristicDINS, 159	CglTemporary, 433
CbcHeuristicDive, 163	ClpAmplObjective, 436
CbcHeuristicDiveCoefficient, 167	ClpConstraintAmpl, 438
CbcHeuristicDiveFractional, 169	OsiBiLinear, 445
CbcHeuristicDiveGuided, 171	OsiBiLinearBranchingObject, 452
CbcHeuristicDiveLineSearch, 172	OsiBiLinearEquality, 454
CbcHeuristicDivePseudoCost, 174	OsiCbcSolverInterface, 472
CbcHeuristicDiveVectorLength, 176	OsiChooseStrongSubset, 475
CbcHeuristicDW, 181	OsiLink, 477
Obditional Private Control of the Co	Joining 177

OsiLinkBranchingObject, 479	coinModel
OsiOldLink, 482	CbcUser, 431
OsiOldLinkBranchingObject, 484	OsiSolverLink, 499
OsiSimpleFixedInteger, 488	column
OsiSolverLinearizedQuadratic, 490	ClpConstraintAmpl, 438
OsiSolverLink, 495	columnLower
OsiUsesBiLinear, 502	ampl_info, 24
cloneBut	columnNumber
CbcHeuristic, 152	CbcLotsize, 250
ClpAmplObjective, 434	CbcSimpleInteger, 365
~ClpAmplObjective, 435	columnNumber
clone, 436	CbcSimpleInteger, 366
ClpAmplObjective, 435	columnStatus
ClpAmplObjective, 435	ampl_info, 25
deleteSome, 435	columnUpper
gradient, 435	ampl_info, 24
linearObjective, 436	columnsInBlock
markNonlinear, 436	CbcHeuristicDW, 185
newXValues, 436	columnsInBlock
objectiveValue, 435	CbcHeuristicDW, 188
operator=, 436	compareBranchingObject
reallyScale, 436	CbcBranchingObject, 46
reducedGradient, 435	CbcCliqueBranchingObject, 60
resize, 435	CbcCutBranchingObject, 78
stepLength, 435	CbcDummyBranchingObject, 95
	CbcFixingBranchingObject, 113
ClpConstraintAmpl, 436	
~ClpConstraintAmpl, 437	CbcIntegerBranchingObject, 242 CbcIntegerPseudoCostBranchingObject, 245
clone, 438	
ClpConstraintAmpl, 437	CbcLongCliqueBranchingObject, 247
ClpConstraintAmpl, 437	CbcLotsizeBranchingObject, 253
coefficient, 439	CbcNWayBranchingObject, 332
column, 438	CbcSOSBranchingObject, 397 compareNodes
deleteSome, 438	•
gradient, 438	CbcCompare, 61
markNonlinear, 438	compareOriginalObject
markNonzero, 438	CbcBranchingObject, 46
newXValues, 438	CbcCliqueBranchingObject, 60
numberCoefficients, 438	CbcCutBranchingObject, 78
operator=, 438	CbcDummyBranchingObject, 95
reallyScale, 438	CbcFixingBranchingObject, 113
resize, 438	CbcLongCliqueBranchingObject, 247
coefficient	CbcNWayBranchingObject, 331
ClpConstraintAmpl, 439	CbcSOSBranchingObject, 396
OsiBiLinear, 446	comparison_
coefficient_	CbcTree, 421
OsiBiLinear, 449	comparisonObject
coefficients_	CbcCompare, 61
CbcFathomDynamicProgramming, 109	computeCompleteSolution
CoinHashLink, 439	CbcMipStartIO.hpp, 531
index, 439	computeLambdas
next, 439	OsiBiLinear, 449
coinModel	computeNonzeroRange
CbcUser, 430	CbcSOSBranchingObject, 397
OsiSolverLink, 498	config_cbc_default.h

CBC_VERSION, 545	CbcModel, 303
config_default.h	createCut
COIN_HAS_CGL, 545	CbcTreeLocal, 424
COIN_HAS_CLP, 545	CbcTreeVariable, 427
COIN_HAS_OSI, 546	createInfo
COIN_HAS_VOL, 546	CbcNode, 313
conflictCut	createOsiBranch
CbcModel, 283	CbcObject, 336
consequence_	createUpdateInformation
CbcNWay, 329	CbcObject, 337
continuousPriority	CbcSimpleIntegerDynamicPseudoCost, 372
CbcModel, 309	CbcSOS, 393
continuousSolution	crunchIt
CbcHeuristicDW, 183	CbcSolverHeuristics.hpp, 542
CbcModel, 288	currentDepth
continuousSolution_	CbcModel, 282
CbcHeuristicDW, 186	currentNode
continuousSolver	CbcModel, 308
CbcModel, 303	currentNumberCuts
convertToDynamic	CbcModel, 308
CbcModel, 307	currentOption
convex_	CbcParam, 352
OsiSolverLink, 499	currentSolution
convexity_	CbcModel, 289
OsiBiLinear, 451	cut
copySome	ampl_info, 26
CbcSimpleIntegerDynamicPseudoCost, 372	CbcRowCuts, 360
cost	CutBranchingObj
CbcFathomDynamicProgramming, 108	CbcBranchingObject.hpp, 512
cost_	cutGenerator
CbcFathomDynamicProgramming, 108	CbcModel, 296
createBranch	cutGeneratorArray
CbcObject, 336	CbcSolver, 389
OsiBiLinear, 446	cutGeneratorName
OsiLink, 477	CbcCutGenerator, 83
OsiOldLink, 482	cutGenerators
OsiSimpleFixedInteger, 488	CbcModel, 296
OsiUsesBiLinear, 502	cutModifier
createCbcBranch	CbcModel, 295
CbcBranchAllDifferent, 29	cutoff_
CbcBranchCut, 31	CbcCompareDefault, 68
CbcBranchToFixLots, 49	CbcObjectUpdateData, 341
CbcClique, 56	cuts
CbcFollowOn, 117	CbcNodeInfo, 324
CbcGeneral, 138	cuts_
CbcldiotBranch, 238	CbcNodeInfo, 326
CbcLotsize, 249	cutsOnlyAtRoot_
CbcNWay, 328	CbcStrategyDefault, 408
CbcObject, 335	CbcStrategyDefaultSubTree, 410
CbcSimpleInteger, 364	
CbcSimpleIntegerDynamicPseudoCost, 372	D
CbcSimpleIntegerPseudoCost, 383	DEBUG
CbcSOS, 392	CbcGenParam, 141
createContinuousSolver	DIRECTION

ChaChaDayana FO	
CbcCbcParam, 52 defaultSettings_	
DIRECTORY CbcGenCtlBlk, 136	
CbcGenParam, 141 deleteColNames	467
DJFIX OsiCbcSolverInterface	, 467
CbcGenParam, 141 deleteCols	400
DUALBOUND OsiCbcSolverInterface	, 469
CbcOsiParam, 343 deleteCut	
DUALPIVOT CbcNodeInfo, 323	
CbcOsiParam, 343 CbcTreeLocal, 424	
DUALSIMPLEX CbcTreeVariable, 427	
CbcOsiParam, 343 deleteCuts	
DUALTOLERANCE CbcNodeInfo, 323	
CbcOsiParam, 343 deleteObjects	
DUMMY CbcModel, 276	
CbcGenParam, 141 deletePreProcess	
DWModel CbcStrategy, 404	
CbcHeuristicDW, 182 deleteRowNames	
deactivate OsiCbcSolverInterface	, 466
CbcNodeInfo, 324 deleteRows	
dealWithEventHandler OsiCbcSolverInterface	, 469
CbcModel, 289 deleteSavedSolution	
debugCreate_ CbcModel, 292	
CbcGenCtlBlk, 136 deleteSolutions	
debugFile_ CbcModel, 305	
CbcGenCtlBlk, 136 deleteSome	
debugNodes ClpAmplObjective, 435	5
CbcHeuristic, 152 ClpConstraintAmpl, 43	8
debugSol_ depth	
CbcGenCtlBlk, 136 CbcNode, 316	
decayFactor_ CbcStatistics, 399	
CbcHeuristic, 153 depth_	
decrement CbcBranchToFixLots,	50
CbcCountRowCut, 75 CbcStatistics, 400	
CbcNodeInfo, 322 CbcStrategy, 405	
decrementCuts desiredPreProcess	
CbcNode, 315 CbcStrategyDefault, 4	07
CbcNodeInfo, 323 desiredPreProcess_	
decrementParentCuts CbcStrategyDefault, 4	80
CbcNode, 315 dfltAction	
CbcNodeInfo, 324 CbcEventHandler, 102	2
defaultBound dfltDirectory	
OsiSolverLink, 497 CbcGenCtlBlk, 134	
defaultBound_ dfltRowColName	
OsiSolverLink, 500 OsiCbcSolverInterface	466
defaultHandler dfltSolver	,
CbcModel, 299 CbcGenCtlBlk, 136	
defaultMeshSize direction	
OsiSolverLink, 497 ampl_info, 24	
defaultMeshSize_ displayThis	
OsiSolverLink, 500 CbcParam, 352	
defaultRounding distance	
-	Q
CbcHeuristicFPump, 197 CbcHeuristicNode, 216	U
defaultRoundingdjFix CbcHeuristicFPump, 199	
Uncharrence Plimb IVV	

CbcBranchToFixLots, 49 doAOCuts OsiSolverLink, 495 doBaCParam CbcGenParamUtils, 21 doCutsNow CbcModel, 281 doDebugParam CbcGenParamUtils, 21 doEbitingleritegerPseudoCost, 383 downLocks CbcGenParamUtils, 21 doCoutsNow CbcModel, 281 doDebugParam CbcGenParamUtils, 21 doHepParam CbcGenParamUtils, 21 doHeuristicsAtRoot CbcModel, 307 doImportParam CbcGenParamUtils, 21 doNothtingParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doPrintMaskParam CbcGenParamUtils, 22 doPrintMaskParam CbcGenParamUtils, 22 doPrintMaskParam CbcGenParamUtils, 22 doSolutionParam CbcGenParamUtils, 22 doLesinpleIntegerPyamanicPseudoCost, 383 downNosadowPrice CbcParam, 351 CbcBenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doLolideparameter CbcGenParam, 351 CbcHeuristicDW, 185 doubleArray CbcHeuristicDW, 185 doubleArray CbcHeuristicDW, 185 doubleArray CbcHeuristicDW, 185 doubleArray CbcHeuristicDW, 186 doubleArray CbcHeuristicDW, 186 doubleArray CbcHeuristicDW, 185 doubleAray CbcHeuristicDW, 186 doubleAray Cbc	djTolerance_	downEstimate
doAOCuts OsiSolverLink, 495 doBaCParam CbcGenParamUtilis, 21 doCutsNow CbcModel, 281 doDebugParam CbcGenParamUtilis, 21 doExitParam CbcGenParamUtilis, 21 doExitParam CbcGenParamUtilis, 21 doExitParam CbcGenParamUtilis, 21 doHeirjstic CbcSolverHeuristics.hpp, 542 doHeuristicSAlRoot CbcGenParamUtilis, 21 doNothingParam CbcGenParamUtilis, 21 doSolutionParam CbcGenParamUtilis, 22 doVersionParam CbcGenParamUtilis, 22 doUersionParam CbcGenParamUtilis, 22 doUersionParam CbcGenParamUtilis, 22 doUersionParam CbcGenParamUtilis, 22 doUersionParam CbcGenParamUtilis, 22 doUelsArray CbcHeuristicDW, 186 doubleArray CbcHeuristic	-	CbcSimpleIntegerDynamicPseudoCost, 377
OsiSolverLink, 495 doBaCParam CbcGenParamUtils, 21 doCutsNow CbcModel, 281 doDebugParam CbcGenParamUtils, 21 doExitParam CbcGenParamUtils, 21 doExitParam CbcGenParamUtils, 21 doHeipParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doOneNode CbcModel, 274 doPrintMaskParam CbcGenParamUtils, 21 doVersionParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUersionParam CbcGenParamUtils, 22 doUersionParam CbcGenParamUtils, 22 doUersionParam CbcGenParamUtils, 22 doubleArrays CbcHeuristicDW, 186 doubleVariue CbcParam, 351 doubleValue CbcParam, 352 CbcColotizeBranchingObject, 242 CbcLotistzeBranchingObject, 244 CbcTreeVariable, 427 cbcEventHandler, 101 elements ampl_into, 25 emply CbcEventHandler, 101 elements cbcEventHandler, 101		
doBacParam CbcGenParamUtils, 21 doCutsNow CbcModel, 281 doDebugParam CbcGenParamUtils, 21 doExitParam CbcGenParamUtils, 21 doHelpParam CbcGenParamUtils, 21 doHelpram CbcGenParamUtils, 21 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristicsAlRoot CbcModel, 307 dolinportParam CbcGenParamUtils, 21 doNohlingParam CbcGenParamUtils, 21 doOneNode CbcModel, 274 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doUbleArray CbcHeuristicDW, 186 doubleArray CbcHeuristicDW, 186 doubleArray CbcHeuristicDW, 185 doubleArray CbcCeram, 351 doubleValue CbcParam, 352 CbcSolver, 388 down CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcLotsizeBranchingObject, 244 CbcTreeVariable, 427 CbcEventHandler, 101 ements cbcErentlandler, 101 ements cbcTreeVariable, 427 endoGlaranch CbcErentlandler, 101 ements cbcTreeVariable, 427 endoGlaranch CbcTreeVariable, 427 endomplandoco	OsiSolverLink, 495	
CbcGenParamUtils, 21 doCustNow CbcModel, 281 doDebugParam CbcGenParamUtils, 21 doExitParam CbcGenParamUtils, 21 doHelpParam CbcGenParamUtils, 21 doHeuristics AlRoot CbcModel, 307 doImportParam CbcGenParamUtils, 21 doOneNode CbcModel, 274 doPrintMaskParam CbcGenParamUtils, 21 doColnimplementedParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 d		-
doCushow CbcModel, 281 doDebugParam CbcGenParamUtils, 21 doExitParam CbcGenParamUtils, 21 doHelpParam CbcGenParamUtils, 21 doHelpParam CbcGenParamUtils, 21 doHelpParam CbcGenParamUtils, 21 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristicsAlRoot CbcGenParamUtils, 21 doNenorder CbcGenParamUtils, 21 doNenorder CbcGenParamUtils, 21 doNenorder CbcGenParamUtils, 21 doNenorder CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUlsingParam CbcGenParamUtils, 22 doUlsingParameter CbcGenParamUtils, 22 doubleParameter CbcParam, 351 doubleParameter CbcParam, 351 doubleParameter CbcCeventHandler, 103 eaMapPair CbcEventHandler, 103 eaMapPair CbcEventHandler, 100 elements ampl_info, 25 empty CbcTree, 418 CbcTreeLocal, 424 CbcTreeVariable, 427 endSearch CbcEventHandler, 101 endOfBranch CbcSlatistics, 398 endSearch CbcEventHandler, 101 endOfBranch CbcEventHand		
CbcModel, 281 doDebugParam CbcGenParamUtils, 21 doExitParam CbcGenParamUtils, 21 doHeipParam CbcGenParamUtils, 21 doHeipParam CbcGenParamUtils, 21 doHeipParam CbcGenParamUtils, 21 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristics CbcGenParamUtils, 21 doHouristicsAtRoot CbcModel, 307 doImportParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doVersionParam CbcGenParam, 141 EXIT CbcGenParam, 141 EX		
doDebugParam CbcGenParamUtils, 21 doExitiParam CbcGenParamUtils, 21 doHelpParam CbcGenParamUtils, 21 doHelpParam CbcGenParamUtils, 21 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristicsAtRoot CbcModel, 307 domportParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doOneNode CbcModel, 274 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doUersionParam CbcGenParamUtils, 22 doubleArray CbcHeuristicDW, 186 doubleArrays CbcHeuristicDW, 185 doubleArrays CbcHeuristicDW, 185 doubleArray CbcCeparam, 351 doubleArray CbcCuBranchingObject, 242 CbcSolver, 388 down CbcCuBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcLotsizeBranchingObject, 242 CbcChotsizeBranchingObject, 242 CbcChotsizeBranchingObject, 242 CbcReventHandler, 101 endOlBranch CbcStatistics, 398 endsearch CbcTree, 419 CbcTreeVariable, 427 endSearch CbcTreeVariable, 427 endIgnInfeasibility endingInfeasibility endingInfea		_
CbcGenParamUtils, 21 doExitParam CbcGenParamUtils, 21 doHelpParam CbcGenParamUtils, 21 doHelpParam CbcGenParamUtils, 21 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristics CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParam, 141 EXPORT CbcGenParam, 141 EXPORT CbcGenParam, 141 eaMap CbcEventHandler, 103 eaMapPair CbcEventHandler, 100 elements ampl_info, 25 empty CbcTree, 418 CbcTreeVariable, 427 endsearch CbcEventHandler, 101 endOfBranch CbcStatistics, 398 endSearch CbcTree, 419 CbcTreeVariable, 427 endisearch		
doExitParam		
CbcGenParamUtils, 21 doHelpParam CbcGenParamUtils, 21 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristicsAtRoot CbcModel, 307 doImportParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNoneNode CbcModel, 274 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doVersionParam CbcHeuristicDW, 186 doubleArray CbcHeuristicDW, 186 doubleArray CbcHeuristicDW, 185 doubleParamete CbcParam, 351 CbcHeuristicDW, 185 doubleParamete CbcParam, 352 CbcSolver, 388 down_ CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcLotszeBranchingObject, 242 CbcLotszeBranchingObject, 245 CbcRounding, 359 downArray_ CbcHeuristicDive, 166 downBounds CbcIntegerBranchingObject, 241 CbcClottreeVariable, 427 endSearch CbcSimpleIntegerDynamicPseudoCost, 373 endignIfe asibility classifications, 373 downShadowPrice CbcSimpleIntegerDynamicPseudoCost, 373 dounShadowPrice CbcSimpleIntegerDynamicPseudoCost, 373		-
doHelipParam CbcGenParamUtils, 21 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristicsAtRoot CbcModel, 307 doImportParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doOneNode CbcModel, 274 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUersionParam CbcGenParamUtils, 22 doUersionParam CbcGenParamUtils, 22 doUersionParam CbcGenParamUtils, 22 doUbleArray_ CbcHeuristicDW, 186 doubleArrays CbcHeuristicDW, 185 doubleParameter CbcParam, 351 doubleParameter CbcParam, 351 doubleValue CbcParam, 351 doubleValue CbcParam, 352 CbcCbufBranchingObject, 79 CbcCutBranchingObject, 242 CbcLotsizeBranchingObject, 254 CbcCutsizeBranchingObject, 254 CbcChotsizeBranchingObject, 254 CbcRounding, 359 downArray_ CbcHeuristicDive, 166 downBounds CbcIree, 419 CbcTree, 419 CbcTreeLocal, 424 CbcTreeVariable, 427 endingInfeasibility		
CbcGenParamUtils, 21 doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristicsAtRoot CbcModel, 307 doImportParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 21 doSolution CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doUeleArray_ CbcHeuristicDW, 186 doubleArray_ CbcHeuristicDW, 185 doubleParameter CbcParam, 351 doubleParameter CbcParam, 351 doubleParameter CbcParam, 352 CbcParam, 353 CbcHeuristicDW, 188 down_ CbcCenparaningObject, 79 CbcIntegerBranchingObject, 242 CbcLotsizeBranchingObject, 242 CbcLotsizeBranchingObject, 242 CbcLotsizeBranchingObject, 242 CbcLotsizeBranchingObject, 244 CbcRounding, 359 downArray_ CbcHeuristicDive, 166 downBounds CbcIree, 419 CbcTreeLocal, 424 CbcTreeLocal,		
doHeuristics CbcSolverHeuristics.hpp, 542 doHeuristicsXHRoot CbcModel, 307 doImportParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doOneNode CbcModel, 274 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doVimplementedParam CbcGenParamUtils, 22 doVimplementedParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doUbleArray CbcHeuristicDW, 186 doubleArrays CbcHeuristicDW, 185 doubleParameter CbcParam, 351 doubleValue CbcParam, 352 CbcSolver, 388 down_ CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcLotsizeBranchingObject, 254 CbcRounding, 359 downArray_ CbcHeuristicDive, 166 downBounds CbcIntegerBranchingObject, 241 downDynamicPseudoCost CbcSimpleIntegerDynamicPseudoCost, 373 dualSolution ampl_info, 25 DummyBranchObj CbcBranchingObject, 411 dwBlook_ CbcHeuristicDW, 187 dwBlock_ CbcBirpleIntegerDynamicPseudoCost, 373 dualSolution ampl_info, 25 DummyBranchObj CbcBranchingObject, 411 dwBlock_ CbcBirpleIntegerDynamicPseudoCost, 373 dualSolution ampl_info, 25 DummyBranchObj CbcHeuristicDW, 187 dwBlock_ CbcHeuristicDW, 186 DynamicPseudoCost, 373 dwBlock_ CbcBirpleIntegerDynamicPseudoCost, 373 dualSolution ampl_info, 25 DummyBranchObj CbcHeuristicDW, 187 dwBlock_ CbcHeuristicDW, 186 DynamicPseudoCost, 378 dwBlock_ CbcHeuristicDW, 187 dwBlock_ CbcHeuristicDW, 186 DynamicPseudoCost, 378 dwBlock_ CbcBranchingObject, 417 dwBlock_ CbcBranchingObject, 417 dwBlock_ CbcBranchingObject, 417 dwBlock_ CbcBranchingObject, 417 dwBlock_ CbcBranchingObject, 427 endsearch CbcBranchingObject, 427 endingInfeasibility	•	
CbcSolverHeuristics.hpp, 542 ddoHeuristicsAtRoot CbcModel, 307 doImportParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doOneNode CbcModel, 274 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 ERRORSALLOWED CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 EXIT CbcGenParamUtils, 22 EXIT CbcGenParam, 141 EXPORT CbcGenParam, 141 EXPORT CbcGenParam, 141 CbcHeuristicDW, 186 doubleArray_ CbcHeuristicDW, 185 doubleParameter CbcParam, 351 doubleParameter CbcParam, 351 doubleValue CbcParam, 352 CbcSolver, 388 down_ CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcLotsizeBranchingObject, 242 CbcCutBranchingObject, 254 CbcRounding, 359 CbcHeuristicDive, 166 downBounds CbcIrree, 419 CbcTree, 419 CbcTree, 419 CbcTreeLocal, 424 CbcTreeLocal, 427 CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility		-
doHeuristicsAtRoot CbcModel, 307 dolmportParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 21 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doUbleArray_ CbcHeuristicDW, 186 doubleArrays CbcHeuristicDW, 185 doubleParameter CbcParam, 351 doubleValue CbcParam, 352 CbcSolver, 388 down_ CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcLotsizeBranchingObject, 254 CbcRounding, 359 downArray_ CbcHeuristicDive, 166 downBounds CbcHeuristicDive, 166 downBounds CbcHeuristicDive, 166 downDounds CbcRounding, 359 CbcHeuristicDive, 166 CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility ampl_info, 25 cbcMorer, 418 CbcTree, 419 CbcTree, 419 CbcTree, 419 CbcTree, 419 CbcTree, 419 CbcTreeLocal, 424 CbcTreeVariable, 427 endingInfeasibility		
CbcModel, 307 dolmportParam CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doNohlingParam CbcGenParamUtils, 21 doNohlingParam CbcModel, 274 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doUbleArray_ CbcHeuristicDW, 186 doubleArray_ CbcHeuristicDW, 186 doubleArraya CbcParam, 351 doubleValue CbcParam, 351 doubleValue CbcParam, 352 CbcSolver, 388 down_ CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcLotsizeBranchingObject, 254 CbcRounding, 359 downArray_ CbcHeuristicDive, 166 downBounds CbcIree Local, 424 CbcCiree Variable, 427 CbcIree, 419 CbcSimpleIntegerDynamicPseudoCost, 373 DummyBranchObj CbcBeranchingObject.hpp, 512 dwBlock_ CbcBerariticDW, 187 dwSolver_ CbcHeuristicDW, 186 DynamicPseudoCost CbcBranchingObject.hpp, 512 dwBlock_ CbcBranchingObject.hpp, 512 dwBlock_ CbcHeuristicDW, 186 DynamicPseudoCost CbcBranchingObject.hpp, 512 dwBlock_ CbcBreuristicDW, 186 DynamicPseudoCost CbcBranchingObject.hpp, 512 dwBlock_ CbcBreanchingObject.hpp, 512 dwSlover_ CbcBranchingObject.hpp, 512 dwSlover_ CbcBranchingObject.hpp, 512 dwSlover_ CbcBreanchingObject.hpp, 512 dwSlover_ CbcBreanc		
dolmportParam		• —
CbcGenParamUtils, 21 doNothingParam CbcGenParamUtils, 21 doOneNode CbcModel, 274 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doUersionParam CbcGenParamUtils, 22 doUbleArray CbcHeuristicDW, 186 doubleArray CbcHeuristicDW, 185 doubleParameter CbcParam, 351 doubleValue CbcParam, 352 CbcSolver, 388 down CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcCutBranchingObject, 242 CbcCutBranchingObject, 254 CbcRounding, 359 downArray CbcHeuristicDive, 166 downBounds CbcIrree, 166 downBounds CbcIrree, 166 downDamicPseudoCost CbcSimpleIntegerDynamicPseudoCost, 373 ewSolver CbcGeream, 316 dwsSolver CbcBranchingObject, 241 CbcCirree, 419 CbcCirreeVariable, 427 endingInfeasibility	CbcModel, 307	DummyBranchObj
doNothingParam	doImportParam	CbcBranchingObject.hpp, 512
CbcGenParamUtils, 21 doOneNode CbcHeuristicDW, 186 CbcModel, 274 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam ECbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doversionParam CbcGenParamUtils, 22 doubleArray_ CbcHeuristicDW, 186 doubleArrays CbcHeuristicDW, 185 doubleParameter CbcParam, 351 doubleParameter CbcParam, 351 doubleValue CbcParam, 352 CbcSolver, 388 down_ CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcChauristicDive, 186 downArray_ CbcHeuristicDive, 186 downArray_ CbcHeuristicDive, 186 downArray_ CbcSolver, 388 down_ CbcCutBranchingObject, 242 CbcLotsizeBranchingObject, 254 CbcCutBranchingObject, 254 CbcRounding, 359 downArray_ CbcHeuristicDive, 166 downBounds CbcItree, 419 CbcCitreeVariable, 427 cbcTireeLocal, 424 CbcTireeVariable, 427 endingInfeasibility	CbcGenParamUtils, 21	dwBlock_
doOneNode CbcModel, 274 doPrintMaskParam CbcGenParamUtils, 21 doSolutionParam CbcGenParamUtils, 22 doUnimplementedParam CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doUversionParam CbcGenParamUtils, 22 doUbleArray_ CbcHeuristicDW, 186 doubleArrays CbcHeuristicDW, 185 doubleParameter CbcParam, 351 doubleValue CbcParam, 352 CbcParam, 352 CbcSolver, 388 down_ CbcCutBranchingObject, 79 CbcLottsizeBranchingObject, 242 CbcCottounding, 359 downBounds CbcHeuristicDive, 166 downBounds CbcHeuristicDive, 166 downBounds CbcHeuristicDive, 166 downBounds CbcHeuristicDive, 241 downDynamicPseudoCost, 373 endingInfeasibility CbcTreeVariable, 427 endingInfeasibility endingInfeasibility	doNothingParam	CbcHeuristicDW, 187
CbcModel, 274 doPrintMaskParam	CbcGenParamUtils, 21	dwSolver_
CbcModel, 274 doPrintMaskParam	doOneNode	CbcHeuristicDW, 186
doPrintMaskParam	CbcModel, 274	
CbcGenParamUtils, 21 doSolutionParam		· ·
doSolutionParam CbcGenParamUtils, 22 BERRORSALLOWED CbcGenParam, 141 CbcGenParamUtils, 22 EXIT CbcGenParamUtils, 22 EXPORT CbcGenParam, 141 CbcGenParamUtils, 22 EXPORT CbcGenParam, 141 CbcGenParamUtils, 22 EXPORT CbcGenParam, 141 CbcHeuristicDW, 186 doubleArray_		осо-тапонтуров при
CbcGenParamUtils, 22 doUnimplementedParam		F
doUnimplementedParam		
CbcGenParamUtils, 22 doVersionParam CbcGenParamUtils, 22 doubleArray_ CbcHeuristicDW, 186 doubleArrays CbcHeuristicDW, 185 doubleParameter CbcParam, 351 doubleValue CbcParam, 352 CbcSolver, 388 down_ CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcHouristicDW, 254 CbcHouristicDW, 186 downArray_ CbcCutBranchingObject, 254 CbcLotsizeBranchingObject, 254 CbcClotsizeBranchingObject, 254 CbcCheuristicDive, 166 downBounds CbcTree, 419 CbcCIrreeVariable, 427 CbcIntegerBranchingObject, 241 CbcCheuristicDive, 166 CbcDIntegerBranchingObject, 241 CbcClntegerBranchingObject, 241 CbcClntegerBranchingObject, 241 CbcClntegerBranchingObject, 241 CbcCheuristicDive, 166 CbcDIntegerBranchingObject, 241 CbcCrreeVariable, 427 CbcTreeVariable, 427 CbcTreeVariable, 427 CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility		
doVersionParam	•	
CbcGenParamUtils, 22 doubleArray CbcGenParam, 141 CbcHeuristicDW, 186 doubleArrays CbcEventHandler, 103 CbcHeuristicDW, 185 doubleParameter CbcEventHandler, 100 CbcParam, 351 doubleValue ampl_info, 25 CbcSolver, 388 CbcTree, 418 down CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcRounding, 359 downArray CbcHeuristicDive, 166 downBounds CbcIrree, 419 CbcIrreeVariable, 427 CbcIntegerBranchingObject, 241 CbcTree, 419 CbcTreeVariable, 427 CbcTree, 419 CbcTreeVariable, 427 CbcTree, 419 CbcTreeVariable, 427 CbcTreeVariable, 427 CbcTree, 419 CbcTreeVariable, 427 CbcTreeVariable, 427 CbcTreeVariable, 427 CbcTree, 419 CbcTreeVariable, 427		
doubleArray_CbcGenParam, 141CbcHeuristicDW, 186eaMap_doubleArraysCbcEventHandler, 103CbcHeuristicDW, 185eaMapPairdoubleParameterCbcEventHandler, 100CbcParam, 351elementsdoubleValueampl_info, 25CbcParam, 352emptyCbcSolver, 388CbcTree, 418down_CbcTreeLocal, 424CbcCutBranchingObject, 79CbcTreeVariable, 427CbcIntegerBranchingObject, 242endSearchCbcLotsizeBranchingObject, 254CbcEventHandler, 101CbcRounding, 359endOfBranchdownArray_CbcStatistics, 398CbcHeuristicDive, 166endSearchdownBoundsCbcTree, 419CbcIntegerBranchingObject, 241CbcTreeLocal, 424downDynamicPseudoCostCbcTreeVariable, 427CbcSimpleIntegerDynamicPseudoCost, 373endingInfeasibility		
CbcHeuristicDW, 186 doubleArrays CbcHeuristicDW, 185 doubleParameter CbcEventHandler, 100 CbcParam, 351 doubleValue CbcParam, 352 CbcSolver, 388 CbcTree, 418 down_ CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcRounding, 359 downArray_ CbcHeuristicDive, 166 downBounds CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 254 CbcTree, 418 CbcEventHandler, 427 CbcEventHandler, 101 CbcRounding, 359 CbcHeuristicDive, 166 comBounds CbcTree, 419 CbcIntegerBranchingObject, 241 CbcTreeLocal, 424 CbcTreeLocal, 424 CbcTreeLocal, 424 CbcTreeLocal, 424 CbcTreeLocal, 424 CbcTreeVariable, 427 CbcTreeVariable, 427 CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility		
doubleArrays CbcHeuristicDW, 185 eaMapPair doubleParameter CbcParam, 351 doubleValue CbcParam, 352 CbcSolver, 388 down_ CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcRounding, 359 CbcHeuristicDive, 166 downBounds CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 241 CbcSimpleIntegerDynamicPseudoCost, 373 CbcTreeVariable, 103 CampleIntegerDynamicPseudoCost, 373 CbcEventHandler, 100 CbcEventHandler, 101 CbcTreeVariable, 427	•	•
CbcHeuristicDW, 185 doubleParameter CbcParam, 351 doubleValue CbcParam, 352 CbcSolver, 388 down_ CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcRounding, 359 downArray_ CbcHeuristicDive, 166 downBounds CbcIreeBranchingObject, 241 downDynamicPseudoCost CbcSimpleIntegerDynamicPseudoCost, 373 eaMapPair CbcEventHandler, 100 CbcEventtHandler, 100 elements ampl_info, 25 empty CbcTree, 418 CbcTreeLocal, 424 CbcTreeLocal, 424 CbcTreeVariable, 427 CbcTreeVariable, 427 CbcEventHandler, 101 endOfBranch CbcStatistics, 398 endSearch CbcTree, 419 CbcTreeLocal, 424 CbcTreeVariable, 427 endingInfeasibility		· -
double ParameterCbc Event Handler, 100CbcParam, 351elementsdouble Valueampl_info, 25CbcParam, 352emptyCbcSolver, 388CbcTree, 418down_CbcTreeLocal, 424CbcCutBranching Object, 79CbcTree Variable, 427CbcInteger Branching Object, 242end SearchCbcLotsize Branching Object, 254Cbc Event Handler, 101CbcRounding, 359end Of Branchdown Array_Cbc Statistics, 398Cbc Heuristic Dive, 166end Searchdown BoundsCbc Tree, 419Cbc Integer Branching Object, 241Cbc Tree Local, 424down Dynamic Pseudo CostCbc Tree Variable, 427Cbc Simple Integer Dynamic Pseudo Cost, 373ending Infeasibility	•	
CbcParam, 351 doubleValue CbcParam, 352 CbcSolver, 388 down_ CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcRounding, 359 downArray_ CbcHeuristicDive, 166 downBounds CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 254 CbcTreeVariable, 427 CbcStatistics, 398 endOfBranch CbcStatistics, 398 endSearch CbcTree, 419 CbcTree, 419 CbcTreeLocal, 424 downDynamicPseudoCost CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility		•
doubleValue ampl_info, 25 CbcParam, 352 empty CbcSolver, 388 CbcTree, 418 down_ CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcLotsizeBranchingObject, 254 CbcRounding, 359 CbcRounding, 359 CbcHeuristicDive, 166 cwnBounds CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 241 CbcSimpleIntegerDynamicPseudoCost, 373 ampl_info, 25 empty CbcTree, 418 CbcTree, 418 CbcTreeLocal, 424 CbcTreeVariable, 427 endSearch CbcEventHandler, 101 endOfBranch CbcEventHandler, 101 CbcStatistics, 398 endSearch CbcTree, 419 CbcTreeLocal, 424 CbcTreeVariable, 427 endingInfeasibility		CbcEventHandler, 100
CbcParam, 352 CbcSolver, 388 CbcTree, 418 CbcTreeLocal, 424 CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcLotsizeBranchingObject, 254 CbcRounding, 359 CbcHeuristicDive, 166 downBounds CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 241 CbcSimpleIntegerDynamicPseudoCost, 373 empty CbcTree, 418 CbcTreeLocal, 424 CbcTreeVariable, 427 endSearch CbcEventHandler, 101 CbcEventHandler,	CbcParam, 351	elements
CbcSolver, 388 down	doubleValue	ampl_info, 25
down CbcTreeLocal, 424 CbcCutBranchingObject, 79 CbcTreeVariable, 427 CbcIntegerBranchingObject, 242 endSearch CbcLotsizeBranchingObject, 254 CbcEventHandler, 101 CbcRounding, 359 endOfBranch downArray_ CbcStatistics, 398 CbcHeuristicDive, 166 endSearch downBounds CbcTree, 419 CbcIntegerBranchingObject, 241 CbcTreeLocal, 424 downDynamicPseudoCost CbcTreeVariable, 427 CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility	CbcParam, 352	empty
CbcCutBranchingObject, 79 CbcIntegerBranchingObject, 242 CbcLotsizeBranchingObject, 254 CbcRounding, 359 CbcRounding, 359 CbcHeuristicDive, 166 CbcHeuristicDive, 166 CbcIntegerBranchingObject, 241 CbcIntegerBranchingObject, 241 CbcSimpleIntegerDynamicPseudoCost, 373 CbcTreeVariable, 427 CbcSimpleIntegerDynamicPseudoCost, 373 CbcTreeVariable, 427 CbcTreeVariable, 427 CbcIntegerBranchingObject, 373 CbcTreeVariable, 427 CbcTreeVariable, 427 CbcTreeVariable, 427	CbcSolver, 388	CbcTree, 418
CbcIntegerBranchingObject, 242 CbcLotsizeBranchingObject, 254 CbcRounding, 359 CbcRounding, 359 CbcHeuristicDive, 166 cownBounds CbcIntegerBranchingObject, 241 CbcSimpleIntegerDynamicPseudoCost, 373 CbcIntegerBranchingObject, 373 CbcIntegerBranchingObject, 373 CbcSimpleIntegerDynamicPseudoCost, 373 CbcSimpleIntegerDynamicPseudoCost, 373 CbcSimpleIntegerDynamicPseudoCost, 373 CbcEventHandler, 101 CbcEventHandler, 101 CbcStatistics, 398 endOfBranch CbcStatistics, 398 endSearch CbcStatistics, 398 CbcTree, 419 CbcTreeLocal, 424 CbcTreeVariable, 427 endingInfeasibility	down_	CbcTreeLocal, 424
CbcLotsizeBranchingObject, 254 CbcEventHandler, 101 CbcRounding, 359 endOfBranch CbcStatistics, 398 CbcHeuristicDive, 166 endSearch downBounds CbcIntegerBranchingObject, 241 CbcTree, 419 CbcTreeLocal, 424 downDynamicPseudoCost CbcTreeVariable, 427 CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility	CbcCutBranchingObject, 79	CbcTreeVariable, 427
CbcRounding, 359 endOfBranch CbcStatistics, 398 CbcHeuristicDive, 166 endSearch downBounds CbcIrree, 419 CbcIntegerBranchingObject, 241 CbcTreeLocal, 424 downDynamicPseudoCost CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility	CbcIntegerBranchingObject, 242	endSearch
CbcRounding, 359 endOfBranch CbcStatistics, 398 CbcHeuristicDive, 166 endSearch downBounds CbcIrree, 419 CbcIntegerBranchingObject, 241 CbcTreeLocal, 424 downDynamicPseudoCost CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility	CbcLotsizeBranchingObject, 254	CbcEventHandler, 101
downArray CbcStatistics, 398 CbcHeuristicDive, 166 endSearch downBounds CbcTree, 419 CbcIntegerBranchingObject, 241 CbcTreeLocal, 424 downDynamicPseudoCost CbcTreeVariable, 427 CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility		
CbcHeuristicDive, 166 downBounds CbcIree, 419 CbcIntegerBranchingObject, 241 CbcTreeLocal, 424 downDynamicPseudoCost CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility		
downBounds CbcTree, 419 CbcIntegerBranchingObject, 241 CbcTreeLocal, 424 downDynamicPseudoCost CbcTreeVariable, 427 CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility		
CbcIntegerBranchingObject, 241 CbcTreeLocal, 424 downDynamicPseudoCost CbcTreeVariable, 427 CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility		
downDynamicPseudoCost CbcTreeVariable, 427 CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility		
CbcSimpleIntegerDynamicPseudoCost, 373 endingInfeasibility		
COMMITANTALING SCHOOLOST CONSTRUCTS 399	· · · · · · · · · · · · · · · · · · ·	- · · · · · · · · · · · · · · · · · · ·
CbcSimpleIntegerDynamicPseudoCost. 378 endingInfeasibility	-	

CbcStatistics, 400	CbcHeuristic, 153
endingObjective	feasible
CbcStatistics, 399	CbcFeasibilityBase, 111
endingObjective_	feasibleRegion
CbcStatistics, 399	CbcBranchCut, 31
equal_	CbcClique, 56
CbcRounding, 359	CbcFollowOn, 117
equalityTest	CbcGeneral, 138
CbcCompareBase, 64	CbcIdiotBranch, 238
eraseRowCut	CbcLotsize, 249
CbcRowCuts, 360	CbcNWay, 328
event	CbcObject, 335
CbcEventHandler, 102	CbcSimpleInteger, 364, 365
every1000Nodes	CbcSOS, 392
CbcCompareBase, 63	OsiBiLinear, 445
CbcCompareDefault, 67	OsiLink, 477
exitNow	OsiOldLink, 482
CbcHeuristic, 149	OsiUsesBiLinear, 503
expandKnapsack	feasibleSolution
CbcSolverExpandKnapsack.hpp, 541	CbcModel, 289
exportData	fillCreateBranch
CbcUser, 430	CbcSimpleInteger, 365
exportSolution	fillInformation
CbcUser, 430	CbcUser, 430
extraRow	fillParameters
OsiBiLinear, 451	CbcSolver, 387
Colbinition, 101	fillPart
F	CbcDynamicPseudoCostBranchingObject, 98
FAKEBOUND	CbcIntegerBranchingObject, 241
CbcOsiParam, 343	fillPseudoCosts
FLOWCUTS	CbcModel, 307
CbcGenParam, 141	fillStrongInfo
FPUMP	CbcBranchingObject, 43
CbcGenParam, 141	CbcDynamicPseudoCostBranchingObject, 98
FPUMPITS	fillValuesInSolver
CbcGenParam, 141	CbcSolver, 387
FULLGENERALQUERY	findCliques
CbcGenParam, 141	CbcModel, 274
fakeCutoff	findIntegers
CbcHeuristicFPump, 196	CbcModel, 276
fakeCutoff	findRange
CbcHeuristicFPump, 199	CbcLotsize, 250
fastNodeDepth	fingerPrint_
CbcModel, 309	CbcHeuristicDW, 188
fathom	finishedDown
CbcFathom, 104	CbcStrongInfo, 413
CbcFathomDynamicProgramming, 107	finishedUp
CbcHeuristicDive, 164	CbcStrongInfo, 413
OsiSolverLink, 495	first_
feasibilityPump_	CbcGenCtlBlk::cbcParamsInfo_struct, 353
CbcHeuristicProximity, 225	CbcGenCtlBlk::genParamsInfo_struct, 441
feasibilityPumpOptions	CbcGenCtlBlk::osiParamsInfo_struct, 486
CbcHeuristic, 150	firstLambda
feasibilityPumpOptions_	OsiBiLinear, 447

firstLambda_	CbcStrategy, 405
OsiBiLinear, 450	fullScan
firstOdd_	CbcCompareBase, 63
CbcCutSubsetModifier, 93	function_
fix	OsiOneLink, 485
CbcBranchingObject, 44	functionPointer_
CbcIntegerBranchingObject, 241	CbcHeuristicDW, 186
CbcSOSBranchingObject, 396	
CbcStrongInfo, 414	G
fixOnReducedCosts	GAMMA
CbcHeuristicFPump, 198	CbcOsiParam, 343
fixOnReducedCosts_	GAPRATIO
CbcHeuristicFPump, 200	CbcCbcParam, 52
fixOtherVariables	GENERALQUERY
CbcHeuristicDive, 165	CbcGenParam, 140
CbcHeuristicDivePseudoCost, 174	GOMORYCUTS
fixPriority_	CbcGenParam, 141
CbcHeuristicPartial, 221	GREEDY
fixTop	CbcGenParam, 141
CbcTree, 419	genParams_
fixVariables_	CbcGenCtlBlk, 135
OsiSolverLink, 500	GeneralDepthBranchObj
fixVubs	CbcBranchingObject.hpp, 512
CbcSolverHeuristics.hpp, 542	generateCpp
fixedDj	CbcBranchDecision, 35
CbcHeuristicDW, 183	CbcCompareBase, 63
fixedDj_	CbcCompareDefault, 67
CbcHeuristicDW, 186	CbcCompareDepth, 70
flipModel	CbcCompareEstimate, 71
CbcModel, 276	CbcCompareObjective, 72
floorCeiling	CbcCutModifier, 91
CbcLotsize, 250	CbcCutSubsetModifier, 93
CbcObject, 336	CbcHeuristic, 150, 151
FollowOnBranchObj	CbcHeuristicCrossover, 156
CbcBranchingObject.hpp, 512	CbcHeuristicDINS, 159
fraction	CbcHeuristicDive, 163
CbcHeuristicGreedyEquality, 206	CbcHeuristicDiveCoefficient, 168
fraction_	CbcHeuristicDiveFractional, 169
CbcHeuristicGreedyEquality, 206	CbcHeuristicDiveGuided, 171
fractionFixed_	CbcHeuristicDiveLineSearch, 172
CbcBranchToFixLots, 49	CbcHeuristicDivePseudoCost, 174
fractionSmall	CbcHeuristicDiveVectorLength, 176
CbcHeuristic, 150	CbcHeuristicDW, 181
fractionSmall_	CbcHeuristicFPump, 195
CbcHeuristic, 153	CbcHeuristicGreedyCover, 202
freeArgs	CbcHeuristicGreedyEquality, 205
Cbc_ampl.h, 504	CbcHeuristicGreedySOS, 208
freeArrays1	CbcHeuristicJustOne, 211
Cbc_ampl.h, 504	CbcHeuristicLocal, 214
freeArrays2	CbcHeuristicNaive, 216
Cbc_ampl.h, 504	CbcHeuristicPartial, 220
fullDWEverySoOften_	CbcHeuristicPivotAndFix, 222
CbcHeuristicDW, 188	CbcHeuristicProximity, 224
fullNodeInfo	CbcHeuristicRandRound, 227
	,

CbcHeuristicRINS, 231	OsiBiLinear, 449
CbcHeuristicVND, 234	getColLower
CbcModel, 310	CbcModel, 286
CbcRounding, 358	OsiCbcSolverInterface, 463
CbcSerendipity, 361	getColName
CbcStrategy, 405	OsiCbcSolverInterface, 466
CbcStrategyDefault, 407	getColNames
CbcTree, 418	OsiCbcSolverInterface, 466
CbcTreeLocal, 423	getColSolution
CbcTreeVariable, 427	CbcModel, 290
generateCuts	OsiCbcSolverInterface, 465
CbcCutGenerator, 83	getColUpper
CglTemporary, 432	CbcModel, 286
generateTuning	OsiCbcSolverInterface, 463
CbcCutGenerator, 83	getCombine
generator	CbcGenCtlBlk, 132
CbcCutGenerator, 86	getContinuousInfeasibilities
getAllowableFractionGap	CbcModel, 292
CbcModel, 279	getContinuousObjective
getAllowableGap	CbcModel, 292
CbcModel, 279	getCurrentMinimizationObjValue
getAllowablePercentageGap	CbcModel, 290
CbcModel, 279	getCurrentNumberNeeded
getApplicationData	CbcHeuristicDW, 184
CbcModel, 298	getCurrentNumberNodes
getBestCriterion	CbcHeuristicDW, 184
CbcBranchDecision, 35	getCurrentObjValue
CbcBranchDefaultDecision, 37	CbcModel, 290
CbcBranchDynamicDecision, 39	getCurrentPassNumber
getBestPossible	CbcModel, 280
CbcCompareDefault, 67	getCurrentSeconds
getBestPossibleObjValue	CbcModel, 278
CbcModel, 290	getCutDepth
getBestPossibleObjective	CbcGenCtlBlk, 130
CbcTree, 419	getCutoff
getCbcColLower	CbcCompareDefault, 67
CbcModel, 288	CbcModel, 277
getCbcColSolution	OsiCbcSolverInterface, 471
-	
CbcModel, 288	getCutoffIncrement
CbcModel, 288 getCbcColUpper	getCutoffIncrement CbcModel, 280
CbcModel, 288 getCbcColUpper CbcModel, 288	getCutoffIncrement CbcModel, 280 getDblParam
CbcModel, 288 getCbcColUpper CbcModel, 288 getCbcReducedCost	getCutoffIncrement CbcModel, 280 getDblParam CbcModel, 277
CbcModel, 288 getCbcColUpper CbcModel, 288 getCbcReducedCost CbcModel, 288	getCutoffIncrement CbcModel, 280 getDblParam CbcModel, 277 OsiCbcSolverInterface, 462
CbcModel, 288 getCbcColUpper CbcModel, 288 getCbcReducedCost CbcModel, 288 getCbcRowActivity	getCutoffIncrement CbcModel, 280 getDblParam CbcModel, 277 OsiCbcSolverInterface, 462 getDualRays
CbcModel, 288 getCbcColUpper CbcModel, 288 getCbcReducedCost CbcModel, 288 getCbcRowActivity CbcModel, 288	getCutoffIncrement CbcModel, 280 getDblParam CbcModel, 277 OsiCbcSolverInterface, 462 getDualRays OsiCbcSolverInterface, 465
CbcModel, 288 getCbcColUpper CbcModel, 288 getCbcReducedCost CbcModel, 288 getCbcRowActivity CbcModel, 288 getCbcRowLower	getCutoffIncrement CbcModel, 280 getDblParam CbcModel, 277 OsiCbcSolverInterface, 462 getDualRays OsiCbcSolverInterface, 465 getEmptyBasis
CbcModel, 288 getCbcColUpper CbcModel, 288 getCbcReducedCost CbcModel, 288 getCbcRowActivity CbcModel, 288 getCbcRowLower CbcModel, 288	getCutoffIncrement CbcModel, 280 getDblParam CbcModel, 277 OsiCbcSolverInterface, 462 getDualRays OsiCbcSolverInterface, 465 getEmptyBasis CbcModel, 306
CbcModel, 288 getCbcColUpper CbcModel, 288 getCbcReducedCost CbcModel, 288 getCbcRowActivity CbcModel, 288 getCbcRowLower CbcModel, 288 getCbcRowLower	getCutoffIncrement CbcModel, 280 getDblParam CbcModel, 277 OsiCbcSolverInterface, 462 getDualRays OsiCbcSolverInterface, 465 getEmptyBasis CbcModel, 306 getEmptyWarmStart
CbcModel, 288 getCbcColUpper CbcModel, 288 getCbcReducedCost CbcModel, 288 getCbcRowActivity CbcModel, 288 getCbcRowLower CbcModel, 288 getCbcRowLower CbcModel, 288 getCbcRowPrice CbcModel, 288	getCutoffIncrement CbcModel, 280 getDblParam CbcModel, 277 OsiCbcSolverInterface, 462 getDualRays OsiCbcSolverInterface, 465 getEmptyBasis CbcModel, 306 getEmptyWarmStart OsiCbcSolverInterface, 463
CbcModel, 288 getCbcColUpper CbcModel, 288 getCbcReducedCost CbcModel, 288 getCbcRowActivity CbcModel, 288 getCbcRowLower CbcModel, 288 getCbcRowPrice CbcModel, 288 getCbcRowPrice CbcModel, 288 getCbcRowUpper	getCutoffIncrement CbcModel, 280 getDblParam CbcModel, 277 OsiCbcSolverInterface, 462 getDualRays OsiCbcSolverInterface, 465 getEmptyBasis CbcModel, 306 getEmptyWarmStart OsiCbcSolverInterface, 463 getEventHandler
CbcModel, 288 getCbcColUpper CbcModel, 288 getCbcReducedCost CbcModel, 288 getCbcRowActivity CbcModel, 288 getCbcRowLower CbcModel, 288 getCbcRowPrice CbcModel, 288 getCbcRowPrice CbcModel, 288 getCbcRowUpper CbcModel, 288	getCutoffIncrement CbcModel, 280 getDblParam CbcModel, 277 OsiCbcSolverInterface, 462 getDualRays OsiCbcSolverInterface, 465 getEmptyBasis CbcModel, 306 getEmptyWarmStart OsiCbcSolverInterface, 463 getEventHandler CbcModel, 298
CbcModel, 288 getCbcColUpper CbcModel, 288 getCbcReducedCost CbcModel, 288 getCbcRowActivity CbcModel, 288 getCbcRowLower CbcModel, 288 getCbcRowPrice CbcModel, 288 getCbcRowUpper CbcModel, 288 getCbcRowUpper CbcModel, 288	getCutoffIncrement CbcModel, 280 getDblParam CbcModel, 277 OsiCbcSolverInterface, 462 getDualRays OsiCbcSolverInterface, 465 getEmptyBasis CbcModel, 306 getEmptyWarmStart OsiCbcSolverInterface, 463 getEventHandler CbcModel, 298 getExtraNodeCount
CbcModel, 288 getCbcColUpper CbcModel, 288 getCbcReducedCost CbcModel, 288 getCbcRowActivity CbcModel, 288 getCbcRowLower CbcModel, 288 getCbcRowPrice CbcModel, 288 getCbcRowPrice CbcModel, 288 getCbcRowUpper CbcModel, 288	getCutoffIncrement CbcModel, 280 getDblParam CbcModel, 277 OsiCbcSolverInterface, 462 getDualRays OsiCbcSolverInterface, 465 getEmptyBasis CbcModel, 306 getEmptyWarmStart OsiCbcSolverInterface, 463 getEventHandler CbcModel, 298

CbcGenCtlBlk, 131	getMaximumSolutions
getFlow	CbcModel, 277
CbcGenCtlBlk, 130	OsiCbcSolverInterface, 472
getGomory	getMinimizationObjValue
CbcGenCtlBlk, 131	CbcModel, 290
getGreedyCover	getMinimumDrop
CbcGenCtlBlk, 132	CbcModel, 280
getGreedyEquality	getMir
CbcGenCtlBlk, 132	CbcGenCtlBlk, 131
getHeuristicFractionGap	getModel
CbcModel, 279	CbcEventHandler, 102
getHeuristicGap	getModelPtr
CbcModel, 279	OsiCbcSolverInterface, 471
getHintParam	getMovement
OsiCbcSolverInterface, 462	OsiBiLinear, 449
getIPPAction	getMultipleRootTries
CbcGenCtlBlk, 130	CbcModel, 300
getInfeasibilityWeight	getNested
CbcModel, 278	CbcStrategy, 404
getInfinity	getNodeCount
CbcModel, 288	CbcModel, 284
OsiCbcSolverInterface, 465	OsiCbcSolverInterface, 472
getIntParam	getNodeCount2
CbcModel, 277	CbcModel, 305
OsiCbcSolverInterface, 462	getNumCols
getIntegerInformation	CbcModel, 285
CbcModel.hpp, 532	OsiCbcSolverInterface, 463
getIntegerTolerance	getNumElements
CbcModel, 278	CbcModel, 285
getIterationCount	OsiCbcSolverInterface, 463
CbcModel, 284	getNumRows
OsiCbcSolverInterface, 465	CbcModel, 285
getKnapsack	OsiCbcSolverInterface, 463
CbcGenCtlBlk, 131	getNumberBranching
getMIPStart	CbcTree, 420
CbcModel, 310	getNumberHeuristicSolutions
getMatrixByCol	CbcModel, 292
CbcModel, 287	getNumberNeeded
OsiCbcSolverInterface, 465	CbcHeuristicDW, 183
getMatrixByRow	getNumberNodes
CbcModel, 287	CbcHeuristicDW, 184
OsiCbcSolverInterface, 464	getNumberThreads
getMaximumBranching	CbcModel, 304
CbcTree, 420	getObjCoefficients
getMaximumCutPasses	CbcModel, 287
CbcModel, 280	OsiCbcSolverInterface, 464
getMaximumCutPassesAtRoot	getObjName
CbcModel, 280	OsiCbcSolverInterface, 466
getMaximumNodes	getObjSense
CbcModel, 277	CbcModel, 287
OsiCbcSolverInterface, 471	OsiCbcSolverInterface, 464
getMaximumSeconds	getObjValue
CbcModel, 278	CbcModel, 290
OsiCbcSolverInterface, 472	OsiCbcSolverInterface, 465

getPreferredWay	getStopNumberIterations
CbcModel, 281	CbcModel, 293
getPrimalRays	getStrParam
OsiCbcSolverInterface, 465	OsiCbcSolverInterface, 462
getPrintingMode	getThreadMode
CbcModel, 278	CbcModel, 304
getProbing	getTreeLocal
CbcGenCtlBlk, 130	CbcGenCtlBlk, 132
getPseudoShadow	getTwomir
OsiBiLinear, 449	CbcGenCtlBlk, 131
getRandomSeed	getWarmStart
CbcModel, 300	OsiCbcSolverInterface, 463
getRealSolverPtr	getWeight
OsiCbcSolverInterface, 471	CbcCompareDefault, 67
getRedSplit	globalCuts
CbcGenCtlBlk, 131	CbcCutGenerator, 89
getReducedCost	CbcModel, 308
CbcModel, 290	globalCutsAtRoot
OsiCbcSolverInterface, 465	CbcCutGenerator, 89
getRightHandSide	goToDantzig
CbcModel, 286	CbcModel, 302
OsiCbcSolverInterface, 464	goodModel_
getRounding	CbcGenCtlBlk, 136
CbcGenCtlBlk, 132	gradient
getRowActivity	ClpAmplObjective, 435
CbcModel, 290	ClpConstraintAmpl, 438
OsiCbcSolverInterface, 465	guessedObjectiveValue
getRowLower	CbcNode, 316
CbcModel, 286	gutsOfConstructor
OsiCbcSolverInterface, 464	CbcHeuristicGreedyCover, 203
getRowName	
•	CbcHeuristicGreedyEquality, 206
OsiCbcSolverInterface, 466	CbcHeuristicGreedySOS, 209
getRowNames	gutsOfCopy ChaMadal 202
OsiCbcSolverInterface, 466	CbcModel, 303
getRowPrice	OsiSolverLink, 498
CbcModel, 290	gutsOfDestructor
OsiCbcSolverInterface, 465	CbcModel, 303
getRowRange	OsiSolverLink, 498
CbcModel, 286	gutsOfDestructor2
OsiCbcSolverInterface, 464	CbcModel, 303
getRowSense	gutsOfFollowOn
CbcModel, 286	CbcFollowOn, 117
OsiCbcSolverInterface, 464	
getRowUpper	H
CbcModel, 287	HELP
OsiCbcSolverInterface, 464	CbcGenParam, 141
getSeed	HEURISTICSTRATEGY
CbcHeuristic, 151	CbcGenParam, 141
getSolutionCount	haveAnswer_
CbcModel, 291	CbcGenCtlBlk::babState_struct, 27
getSolverObjValue	haveMultiThreadSupport
CbcModel, 291	CbcModel, 304
getState	heuristic
CbcNode, 317	CbcModel, 297

heuristicPass	IPPOn
CbcEventHandler, 101	CbcGenCtlBlk, 126
heuristicSolution	IPPSOS
CbcEventHandler, 101	CbcGenCtlBlk, 126
heuristic_	IPPSave
CbcHeuristicJustOne, 212	CbcGenCtlBlk, 126
heuristicCallBack	IPPStrategy
CbcHeuristicDW, 181	CbcGenCtlBlk, 127
heuristicModel	IPPTrySOS
CbcModel, 293	CbcGenCtlBlk, 127
heuristicName	INFEAS
CbcHeuristic, 151	CbcSimpleIntegerDynamicPseudoCost.hpp, 539
heuristicName_	IPPControl
CbcHeuristic, 153	CbcGenCtlBlk, 126
heuristicSolution	id
OsiSolverLink, 495	CbcObject, 337
hotstartPriorities	id_
CbcModel, 307	CbcObject, 338
hotstartSolution	CbcStatistics, 400
CbcModel, 307	importData
howOften	CbcUser, 430
CbcCutGenerator, 83	improvement
howOften	OsiBiLinearEquality, 454
CbcHeuristic, 153	inaccuracy
CbcHeuristicDINS, 160	CbcCutGenerator, 84
CbcHeuristicDW, 188	increaseSpace
CbcHeuristicRINS, 232	CbcTree, 420
CbcHeuristicVND, 235	increment
howOftenGlobalScan	CbcCountRowCut, 75
CbcModel, 283	CbcNodeInfo, 322
howOftenInSub	increment
CbcCutGenerator, 84	CbcHeuristicProximity, 225
howOftenShallow_	incrementCuts
CbcHeuristic, 154	CbcNodeInfo, 324
	incrementExtra
1	CbcModel, 309
IDIOT	incrementIterationCount
CbcOsiParam, 343	CbcModel, 284
IMPORT	incrementNodeCount
CbcGenParam, 141	CbcModel, 284
INCREMENT	incrementNumberBeforeTrust
CbcCbcParam, 52	CbcSimpleIntegerDynamicPseudoCost, 377
INFEASIBILITYWEIGHT	incrementNumberColumnCuts
CbcCbcParam, 52	CbcCutGenerator, 87
INTEGERTOLERANCE	incrementNumberCutsActive
CbcCbcParam, 52	CbcCutGenerator, 87
INTPRINT	incrementNumberCutsInTotal
CbcGenParam, 141	CbcCutGenerator, 86
IPPEqual	incrementNumberElementsInTotal
CbcGenCtlBlk, 126	CbcCutGenerator, 86
IPPEqualAll	incrementNumberPointingToThis
·	-
CbcGenCtlBlk, 127 IPPOff	CbcNodeInfo, 323 incrementNumberSolutionsFound
CbcGenCtlBlk, 126	CbcHeuristic, 150

incrementNumberTimesDown	OsiCbcSolverInterface, 462
CbcSimpleIntegerDynamicPseudoCost, 376	OsiSolverLinearizedQuadratic, 490
incrementNumberTimesDownInfeasible	OsiSolverLink, 495
CbcSimpleIntegerDynamicPseudoCost, 376	initialUpper
incrementNumberTimesEntered	CbcHeuristicDW, 185
CbcCutGenerator, 86	initialWeight
incrementNumberTimesUp	CbcHeuristicFPump, 197
CbcSimpleIntegerDynamicPseudoCost, 376	initialWeight_
incrementNumberTimesUpInfeasible	CbcHeuristicFPump, 199
CbcSimpleIntegerDynamicPseudoCost, 377	initialize
incrementParentCuts	CbcBranchDecision, 34
CbcNodeInfo, 324	CbcBranchDefaultDecision, 37
incrementStrongInfo	CbcBranchDynamicDecision, 39
CbcModel, 309	initializeData
incrementSubTreeStopped	CbcHeuristicDive, 165
CbcModel, 294	CbcHeuristicDivePseudoCost, 174
incrementTimeInCutGenerator	initializeForBranching
CbcCutGenerator, 85	CbcldiotBranch, 238
incrementUsed	CbcObject, 338
CbcModel, 289	initializeInfo
index	CbcNode, 315
CoinHashLink, 439	CbcNodeInfo, 322
indexNumber	inputSolution_
CbcParam, 353	CbcHeuristic, 155
indices_	intArray_
CbcFathomDynamicProgramming, 109	CbcHeuristicDW, 186
ineffectualCuts	intArrays
CbcCutGenerator, 88	CbcHeuristicDW, 185
infeasibility	intDecrease_
CbcBranchAllDifferent, 29	CbcObjectUpdateData, 340
CbcBranchCut, 31	intParameter
CbcBranchToFixLots, 49	CbcParam, 351
CbcClique, 56	intValue
CbcFollowOn, 117	CbcParam, 352
CbcGeneral, 138	CbcSolver, 387
CbcldiotBranch, 238	integerPresolve
CbcLotsize, 249	CbcModel, 275
CbcNWay, 328	integerPresolveThisModel
CbcObject, 335	CbcModel, 275
CbcSimpleInteger, 364	integerPriority
CbcSimpleIntegerDynamicPseudoCost, 372	OsiSolverLink, 497
CbcSimpleIntegerPseudoCost, 383	integerPriority_
CbcSOS, 392	OsiSolverLink, 500
OsiBiLinear, 445	integerType
OsiLink, 477	CbcModel, 285, 286
OsiOldLink, 482	integerVariable
OsiSimpleFixedInteger, 488	CbcModel, 285
OsiUsesBiLinear, 502	intsInBlock
info_	CbcHeuristicDW, 185
OsiSolverLink, 499	intsInBlock_
initialLower	CbcHeuristicDW, 188
CbcHeuristicDW, 184	isAbandoned
initialSolve	CbcModel, 283
CbcModel, 273	OsiCbcSolverInterface, 462

isBinary	CbcOsiParam, 343
CbcModel, 287	KKT
isContinuous	CbcOsiParam, 343
CbcModel, 287	KNAPSACKCUTS
OsiCbcSolverInterface, 464	CbcGenParam, 141
isContinuousUnbounded	k_
CbcModel, 283	CbcHeuristicVND, 236
isDualObjectiveLimitReached	keepContinuous_
OsiCbcSolverInterface, 463	CbcHeuristicDW, 189
isFreeBinary	killSolution
CbcModel, 287	CbcEventHandler, 101
isInitialSolveAbandoned	kmax_
CbcModel, 285	CbcHeuristicVND, 236
isInitialSolveProvenDualInfeasible	
CbcModel, 285	L
isInitialSolveProvenOptimal	LOCALTREE
CbcModel, 285	CbcGenParam, 141
isInitialSolveProvenPrimalInfeasible	LOGLEVEL
CbcModel, 285	CbcCbcParam, 52
isInteger	CbcGenParam, 141
CbcModel, 287	large_
isIntegerNonBinary	CbcHeuristicNaive, 217
CbcModel, 287	largeValue
isIterationLimitReached	CbcHeuristicNaive, 217
OsiCbcSolverInterface, 463	last_
isLocked	CbcGenCtlBlk::cbcParamsInfo_struct, 353
CbcModel, 304	CbcGenCtlBlk::genParamsInfo_struct, 441
isNodeLimitReached	CbcGenCtlBlk::osiParamsInfo_struct, 486
CbcModel, 283	lastDepth
OsiCbcSolverInterface, 472	CbcTree, 420
isPrimalObjectiveLimitReached	lastDepth_
OsiCbcSolverInterface, 462	CbcTree, 421
isProvenDualInfeasible	lastDownCost_
CbcModel, 283	CbcSimpleIntegerDynamicPseudoCost, 379
OsiCbcSolverInterface, 462	lastDownDecrease_
isProvenInfeasible	CbcSimpleIntegerDynamicPseudoCost, 379
CbcModel, 283	lastHeuristic
isProvenOptimal	CbcModel, 297
CbcModel, 283	lastMpsIn_
OsiCbcSolverInterface, 462	CbcGenCtlBlk, 134
isProvenPrimalInfeasible	lastNode_
OsiCbcSolverInterface, 462	CbcHeuristicRINS, 232
isSecondsLimitReached	CbcHeuristicVND, 235
CbcModel, 284	lastObjective
isSolutionLimitReached	CbcTree, 420
CbcModel, 284	lastObjective_
OsiCbcSolverInterface, 472	CbcHeuristicDW, 186
iterationRatio	CbcTree, 421
CbcHeuristicFPump, 197	lastRunDeep_
iterationRatio_	CbcHeuristic, 154
CbcHeuristicFPump, 200	lastSolnOut_
•	CbcGenCtlBlk, 135
K	lastUnsatisfied
KEEPNAMES	CbcTree, 420

lastUnsatisfied_	MIPOPTIONS
CbcTree, 421	CbcCbcParam, 52
lastUpCost_	MIXEDCUTS
CbcSimpleIntegerDynamicPseudoCost, 379	CbcGenParam, 141
lastUpDecrease_	MOREMIPOPTIONS
CbcSimpleIntegerDynamicPseudoCost, 379	CbcCbcParam, 52
linearObjective	MINIMUM_MOVEMENT
ClpAmplObjective, 436	CbcSimpleIntegerDynamicPseudoCost.hpp, 539
linearizedBAB	MOD_SHADOW
OsiSolverLink, 495	CbcSimpleIntegerDynamicPseudoCost.hpp, 539
load	majorStatus_
OsiSolverLink, 495	CbcGenCtlBlk::babState_struct, 27
loadCbcParamObj	makeGlobalCut
CbcCbcParamUtils, 20	CbcModel, 274
loadGenParamObj	makeGlobalCuts
CbcGenParamUtils, 21	CbcModel, 274
loadOsiParamObj	makePartialCut
CbcOsiParamUtils, 22	CbcModel, 274
loadProblem	mark
OsiCbcSolverInterface, 469, 470	CbcNodeInfo, 325
localSpace_	mark_
CbcHeuristicDINS, 161	CbcBranchToFixLots, 49
lockThread	markHotStart
CbcModel, 304	OsiCbcSolverInterface, 463
logLevel	markNonlinear
ampl_info, 26	ClpAmplObjective, 436
CbcGenCtlBlk, 134	ClpConstraintAmpl, 438
CbcModel, 299	markNonzero
LongCliqueBranchObj	ClpConstraintAmpl, 438
CbcBranchingObject.hpp, 512	marked
lookup_	CbcNodeInfo, 325
CbcFathomDynamicProgramming, 109	masterThread
LotsizeBranchObj	CbcModel, 304
CbcBranchingObject.hpp, 512	matchName
lower	CbcParam, 351
CbcFullNodeInfo, 120	matches
	CbcParam, 352
lower_ CbcFullNodeInfo, 121	,
GDCFulliNodelillo, 121	matrix_ CheFollowOp_117
M	CbcFollowOn, 117
MAXHOTITS	CbcHeuristicCive, 165
	CbcHeuristicGreedyCover, 203
CbcOsiParam, 343	CbcHeuristicGreedyEquality, 206
MAXIMIZE	CbcHeuristicGreedySOS, 209
CbcCbcParam, 52	CbcHeuristicLocal, 214
MAXITERATION	CbcRounding, 359
CbcOsiParam, 343	OsiSolverLink, 498
MAXNODES 50	matrixByRow_
CbcCbcParam, 52	CbcBranchToFixLots, 49
MESSAGES	CbcFollowOn, 117
CbcGenParam, 141	CbcHeuristicDive, 165
MINIMIZE	CbcRounding, 359
CbcCbcParam, 52	maxDiversification
MIPLIB	CbcTreeLocal, 424
CbcGenParam, 141	CbcTreeVariable, 428

	Q1 14 1 1 2 2 2 2
maxIterations_	CbcModel, 305
CbcHeuristicDive, 166	message
maxSimplexIterations	CbcGenCtlBlk, 133
CbcHeuristicDive, 164	messageHandler
maxSimplexIterations_	CbcGenCtlBlk, 134
CbcHeuristicDive, 166	CbcModel, 299
maxSimplexIterationsAtRoot_	messages
CbcHeuristicDive, 166	CbcModel, 299
maxTime_	messagesPointer
CbcHeuristicDive, 166	CbcModel, 299
maximumBranching_	method
CbcTree, 421	CbcSimpleIntegerDynamicPseudoCost, 377
maximumDW_	CbcSimpleIntegerPseudoCost, 383
CbcHeuristicDW, 189	method_
maximumKeepSolutions_	CbcSimpleIntegerDynamicPseudoCost, 380
CbcHeuristicDINS, 160	CbcSimpleIntegerPseudoCost, 384
maximumNodeNumber	minDistance
CbcTree, 419	CbcHeuristicNode, 218
maximumNodeNumber_	minDistanceIsSmall
CbcTree, 421	CbcHeuristicNode, 218
maximumNumberIterations	minDistanceToRun_
CbcModel, 308	CbcHeuristic, 154
maximumPasses	minorStatus_
CbcHeuristicFPump, 198	CbcGenCtlBlk::babState_struct, 27
maximumPasses_	model
CbcHeuristicFPump, 200	CbcBranchingObject, 45
maximumRetries	CbcObject, 338
CbcHeuristicFPump, 198	CbcSolver, 388
maximumRetries_	model_
CbcHeuristicFPump, 200	CbcBranchDecision, 35
maximumRows	CbcBranchingObject, 46
CbcModel, 293	CbcEventHandler, 102
maximumSavedSolutions	CbcFathom, 104
CbcModel, 291	CbcGenCtlBlk, 136
maximumSecondsReached	CbcHeuristic, 152
CbcModel, 278	CbcObject, 338
maximumSize	modelOwnsSolver
CbcFathomDynamicProgramming, 107	CbcModel, 302
maximumSizeAllowed_	modelPtr_
CbcFathomDynamicProgramming, 109	OsiCbcSolverInterface, 473
maximumTime	modelSequence
CbcHeuristicFPump, 196	CbcLotsize, 250
maximumTime_	modifiableBranchingObject
CbcHeuristicFPump, 199	CbcNode, 317
maximumTries	modifiableObject
CbcCutGenerator, 84	CbcModel, 276
members	modify
CbcClique, 57	CbcCutModifier, 91
CbcNWay, 329	CbcCutSubsetModifier, 93
CbcSOS, 393	moreSpecialOptions
members_	CbcModel, 301
CbcClique, 57	moreSpecialOptions2
CbcNWay, 329	CbcModel, 301
mergeModels	moveInfo

21.11.11.22	
CbcModel, 303	CbcTree, 421
moveToModel	newBounds
CbcModel, 305	CbcPartialNodeInfo, 356
multiplier_	CbcTree, 420
OsiBiLinear, 451	OsiBiLinear, 448
mustCallAgain	newBounds_
CbcCutGenerator, 87	CbcPartialNodeInfo, 356
mutableLower	newGrid
CbcFullNodeInfo, 120	OsiBiLinearEquality, 454
mutableMembers	newLanguage
CbcSOS, 394	CbcModel, 299
mutableOwner	OsiCbcSolverInterface, 471
CbcNodeInfo, 324	newSolution
mutableStrongInfo	CbcCompareBase, 63
CbcModel, 309	CbcCompareDefault, 67
mutableUpper	newXValues
CbcFullNodeInfo, 121	ClpAmplObjective, 436
mutableWeights	ClpConstraintAmpl, 438
CbcSOS, 394	next
N	CoinHashLink, 439
N NET ID DADDIED	noAction
NETLIB_BARRIER	CbcEventHandler, 101
CbcOsiParam, 343	node
NETLIB_DUAL	CbcEventHandler, 101
CbcOsiParam, 343	CbcHeuristicNodeList, 219
NETLIB_PRIMAL	CbcStatistics, 399
CbcOsiParam, 343	nodeComparison
NETWORK	CbcModel, 294
CbcOsiParam, 343	nodeInfo
NUMBERANALYZE	CbcNode, 315
CbcCbcParam, 52	nodeLimit
NUMBERBEFORE	CbcTreeLocal, 425
CbcCbcParam, 52	CbcTreeVariable, 428
NUMBERMINI	nodeNumber
CbcCbcParam, 52	CbcNode, 317
NWayBranchObj	CbcNodeInfo, 324
CbcBranchingObject.hpp, 512	nodeNumber_
nDifferent_	CbcNodeInfo, 326
CbcHeuristicVND, 236	nodePointer
nNeeded_	CbcTree, 419
CbcHeuristicDW, 190	nodes_
nNeededBase_	CbcTree, 421
CbcHeuristicDW, 190	nonLinear
nNodes_	ampl_info, 26
CbcHeuristicDW, 190	nonlinearSLP
nNodesBase_	OsiSolverLink, 495
CbcHeuristicDW, 190	normal
name	CbcCutGenerator, 85
CbcParam, 350	normalSolver
CbcUser, 431	CbcModel, 300
needsOptimalBasis	normalizeProbabilities
CbcCutGenerator, 87	CbcHeuristicJustOne, 212
newBound_	notPreferredNewFeasible
CbcFixVariable, 115	CbcBranchCut, 32

CbcLotsize, 250	CbcStrategyDefaultSubTree, 410
CbcObject, 336	numberBiLinear_
nullNodeInfo	OsiUsesBiLinear, 503
CbcNode, 315	numberBinary
nullOwner	ampl_info, 24
CbcNodeInfo, 324	numberBits
nullParent	CbcFathomDynamicProgramming, 109
CbcNodeInfo, 323	numberBlocks
numBeforeTrust_	CbcHeuristicDW, 182
CbcGenCtlBlk::chooseStrongCtl_struct, 433	numberBlocks
numCols	CbcHeuristicDW, 189
CbcGenCtlBlk::debugSolInfo struct, 440	numberBranches
numCouldRun	CbcNode, 316
CbcHeuristic, 152	CbcNWayBranchingObject, 331
numCouldRun	numberBranchesLeft
CbcHeuristic, 154	CbcNodeInfo, 322
numIntInfeasDown	numberBranchesLeft
CbcStrongInfo, 413	CbcNodeInfo, 326
numIntInfeasUp	
•	numberBranching_
CbcStrongInfo, 413	CbcTree, 421
numInvocationsInDeep_	numberChangedBounds
CbcHeuristic, 154	CbcPartialNodeInfo, 356
numInvocationsInShallow_	numberChangedBounds_
CbcHeuristic, 154	CbcPartialNodeInfo, 356
numltersDown	numberClean_
CbcStrongInfo, 414	CbcBranchToFixLots, 50
numltersUp	numberCoefficients
CbcStrongInfo, 413	ClpConstraintAmpl, 438
numObjInfeasDown	numberColumnCuts
CbcStrongInfo, 413	CbcCutGenerator, 86
numObjInfeasUp	numberColumns
CbcStrongInfo, 413	ampl_info, 23
numRuns	numberColumnsDW
CbcHeuristic, 152	CbcHeuristicDW, 182, 183
numRuns_	numberColumnsDW_
CbcHeuristic, 154	CbcHeuristicDW, 187
numStrong_	numberCutGenerators
CbcGenCtlBlk::chooseStrongCtl_struct, 433	CbcModel, 296
numberActive_	CbcSolver, 389
CbcFathomDynamicProgramming, 109	numberCuts
numberActiveCutsAtRoot	CbcNodeInfo, 324
CbcCutGenerator, 89	CbcRowCuts, 360
numberAnalyzeIterations	numberCuts_
CbcModel, 282	CbcNodeInfo, 326
numberArguments	numberCutsActive
ampl_info, 24	CbcCutGenerator, 87
numberBadPasses	numberCutsAtRoot
CbcHeuristicDW, 190	CbcCutGenerator, 88
numberBeforeTrust	numberCutsInTotal
CbcModel, 281	CbcCutGenerator, 86
CbcSimpleIntegerDynamicPseudoCost, 377	numberDW_
numberBeforeTrust	CbcHeuristicDW, 189
CbcSimpleIntegerDynamicPseudoCost, 380	numberDWTimes
CbcStrategyDefault, 408	CbcHeuristicDW, 183
\ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \	

L DWT	
numberDWTimes_	numberNonOne_
CbcHeuristicDW, 189	CbcFathomDynamicProgramming, 110
numberElements	numberNonSOSMembers
ampl_info, 24	CbcClique, 56
numberElementsInTotal	numberNonSOSMembers_
CbcCutGenerator, 86	CbcClique, 57
numberExtralterations	numberObjects
CbcModel, 309	CbcModel, 276
numberExtraRows_	numberObjectsToUse
OsiBiLinear, 451	OsiChooseStrongSubset, 475
numberFix_	numberObjectsToUse_
OsiSolverLink, 500	OsiChooseStrongSubset, 475
numberGlobalViolations	numberPasses_
CbcModel, 293	CbcHeuristicDW, 188
numberHeuristics	numberPenalties
CbcModel, 297	CbcModel, 282
numberHeuristics_	numberPointingToThis
CbcHeuristicJustOne, 212	CbcCountRowCut, 76
numberInSet_	CbcNodeInfo, 323
CbcBranchAllDifferent, 29	numberPointingToThis_
numberIntegers	CbcNodeInfo, 325
ampl_info, 24	numberPoints
CbcModel, 285	OsiBiLinearEquality, 454
numberIntegers_	numberRanges
CbcFullNodeInfo, 121	CbcLotsize, 251
CbcHeuristicDINS, 161	numberRows
numberIterations	ampl_info, 23
CbcStatistics, 399	numberRows_
numberIterations_	CbcNodeInfo, 326
CbcStatistics, 400	numberRowsAtContinuous
numberKeptSolutions_	CbcModel, 285
CbcHeuristicDINS, 160	numberSavedSolutions
numberLinks	CbcModel, 291
OsiLink, 477	numberShortCutsAtRoot
OsiOldLink, 482	CbcCutGenerator, 89
numberMasterColumns	numberSolutions_
CbcHeuristicDW, 189	CbcCompareDefault, 68
numberMasterRows	CbcHeuristicCrossover, 157
CbcHeuristicDW, 189	CbcHeuristicDINS, 160
numberMembers	CbcHeuristicLocal, 214
CbcClique, 56	CbcHeuristicProximity, 225
CbcNWay, 329	CbcHeuristicRINS, 232
CbcSOS, 393	CbcHeuristicVND, 235
numberMembers_	numberSolutionsFound
CbcClique, 57	CbcHeuristic, 150
CbcNWay, 329	numberSolutionsFound
numberNodes	CbcHeuristic, 155
CbcHeuristic, 149	numberSos
numberNodes	ampl_info, 24
CbcHeuristic, 153	numberStates
numberNodesDone	CbcFixVariable, 115
CbcHeuristic, 155	numberStoppedSubTrees
numberNonLinearRows	CbcModel, 294
-	
OsiSolverLink, 498	numberStrong

CbcModel, 281	CbcNode, 316
numberStrong_	numberUserFunctions
CbcStrategyDefault, 408	CbcSolver, 388
CbcStrategyDefaultSubTree, 410	numberVariables
numberStrongIterations	OsiSolverLink, 499
CbcModel, 308	
numberSuccesses	0
CbcHeuristicDINS, 160	OBJSCALE
CbcHeuristicRINS, 232	CbcOsiParam, 343
CbcHeuristicVND, 235	ODDHOLECUTS
numberTimes	CbcGenParam, 141
CbcHeuristicGreedyCover, 203	OUTDUPROWS
CbcHeuristicGreedyEquality, 206	CbcGenParam, 141
CbcHeuristicGreedySOS, 209	OUTPUTFORMAT
numberTimes_	CbcGenParam, 141
Challes visite Cready Fauglity 206	obj
CbcHeuristicGreedyEquality, 206	CbcCbcParam, 53
CbcHeuristicGreedySOS, 209	CbcGenParam, 143
numberTimesDown	CbcOsiParam, 345
CbcSimpleIntegerDynamicPseudoCost, 375	objValue
CbcSOS, 393	ampl_info, 24
numberTimesDown_	object
CbcSimpleIntegerDynamicPseudoCost, 379	CbcBranchingObject, 45
numberTimesDownInfeasible	CbcDynamicPseudoCostBranchingObject, 98
CbcSimpleIntegerDynamicPseudoCost, 376	CbcModel, 276
numberTimesDownInfeasible_	object_
CbcSimpleIntegerDynamicPseudoCost, 379	CbcBranchDecision, 35
numberTimesDownLocalFixed_	CbcDynamicPseudoCostBranchingObject, 99
CbcSimpleIntegerDynamicPseudoCost, 380	CbcObjectUpdateData, 340
numberTimesDownTotalFixed_	objectNumber
CbcSimpleIntegerDynamicPseudoCost, 380	CbcStrongInfo, 414
numberTimesEntered	objectNumber_
CbcCutGenerator, 86	CbcObjectUpdateData, 340
numberTimesProbingTotal_	objective
CbcSimpleIntegerDynamicPseudoCost, 380	ampl_info, 24
numberTimesUp	objectiveDW
CbcSimpleIntegerDynamicPseudoCost, 376	CbcHeuristicDW, 183
CbcSOS, 394	objectiveDW_
numberTimesUp_	CbcHeuristicDW, 187
CbcSimpleIntegerDynamicPseudoCost, 379	objectiveRow_
numberTimesUpInfeasible	OsiSolverLink, 499
CbcSimpleIntegerDynamicPseudoCost, 376	objectiveValue
numberTimesUpInfeasible_	CbcHeuristicDW, 185
CbcSimpleIntegerDynamicPseudoCost, 380	CbcNode, 316
numberTimesUpLocalFixed_	ClpAmplObjective, 435
CbcSimpleIntegerDynamicPseudoCost, 380	objectiveValueWhen
numberTimesUpTotalFixed_	CbcHeuristicDW, 182
CbcSimpleIntegerDynamicPseudoCost, 380	objectiveVariable
numberTries	OsiSolverLink, 497
CbcHeuristicDINS, 160	objectiveVariable_
CbcHeuristicRENS, 229	OsiSolverLink, 499
CbcHeuristicRINS, 232	objects
CbcHeuristicVND, 235	CbcModel, 276
numberUnsatisfied	objects

OsiUsesBiLinear, 503	CbcHeuristicNaive, 216
offset	CbcHeuristicNodeList, 218
ampl_info, 24	CbcHeuristicPartial, 220
onTree	CbcHeuristicPivotAndFix, 222
CbcNode, 317	CbcHeuristicProximity, 224
OneGeneralBranchingObj	CbcHeuristicRandRound, 226
CbcBranchingObject.hpp, 512	CbcHeuristicRENS, 228
operator()	CbcHeuristicRINS, 231
CbcCompare, 61	CbcHeuristicVND, 234
CbcCompareBase, 64	CbcldiotBranch, 238
operator=	CbcIntegerBranchingObject, 241
CbcBranchAllDifferent, 29	CbcIntegerPseudoCostBranchingObject, 244
CbcBranchCut, 31	CbcLongCliqueBranchingObject, 247
CbcBranchingObject, 43	CbcLotsize, 249
CbcBranchToFixLots, 48	CbcLotsizeBranchingObject, 253
CbcCbcParam, 53	CbcModel, 302
CbcClique, 56	CbcNode, 313
CbcCliqueBranchingObject, 59	CbcNWay, 328
CbcCompareBase, 63	CbcNWayBranchingObject, 331
•	CbcObject, 335
CbcCompareDefault, 66 CbcCompareDepth, 70	CbcObjectUpdateData, 340
• • •	
CbcCompareEstimate, 71	CbcOsiParam, 345
CbcCompareObjective, 72	CbcOsiSolver, 347
CbcConsequence, 73	ChePayading 250
CbcCutBranchingObject, 78	CbcRounding, 358
CbcCutGenerator, 83	CbcRowCuts, 360
CbcCutModifier, 91	CbcSerendipity, 361
CbcCutSubsetModifier, 92	CbcSimpleInteger, 364
CbcDummyBranchingObject, 94	CbcSimpleIntegerDynamicPseudoCost, 372
CbcDynamicPseudoCostBranchingObject, 97	CbcSimpleIntegerPseudoCost, 382
CbcEventHandler, 102	CbcSolver, 387
CbcFeasibilityBase, 111	CbcSOS, 392
CbcFixingBranchingObject, 112	CbcSOSBranchingObject, 396
CbcFixVariable, 114	CbcStatistics, 398
CbcFollowOn, 117	CbcStopNow, 402
CbcGeneral, 138	CbcTree, 418
CbcGenParam, 143	CbcTreeLocal, 423
CbcHeuristic, 148	CbcTreeVariable, 426
CbcHeuristicCrossover, 156	CbcUser, 431
CbcHeuristicDINS, 159	CglTemporary, 433
CbcHeuristicDive, 163	ClpAmplObjective, 436
CbcHeuristicDiveCoefficient, 167	ClpConstraintAmpl, 438
CbcHeuristicDiveFractional, 169	OsiBiLinear, 445
CbcHeuristicDiveGuided, 171	OsiBiLinearBranchingObject, 452
CbcHeuristicDiveLineSearch, 172	OsiBiLinearEquality, 454
CbcHeuristicDivePseudoCost, 174	OsiCbcSolverInterface, 473
CbcHeuristicDiveVectorLength, 176	OsiChooseStrongSubset, 475
CbcHeuristicDW, 181	OsiLink, 477
CbcHeuristicFPump, 195	OsiLinkBranchingObject, 478
CbcHeuristicGreedyCover, 202	OsiLinkedBound, 480
CbcHeuristicGreedyEquality, 205	OsiOldLink, 482
CbcHeuristicGreedySOS, 208	OsiOldLinkBranchingObject, 484
CbcHeuristicJustOne, 211	OsiOneLink, 485
CbcHeuristicLocal, 213	OsiSimpleFixedInteger, 488

OsiSolverLinearizedQuadratic, 490	extraRow_, 451
OsiSolverLink, 495	feasibleRegion, 445
OsiUsesBiLinear, 502	firstLambda, 447
optionalObject	firstLambda_, 450
CbcObject, 337	getCoefficients, 449
originalCbcObject_	getMovement, 449
CbcBranchingObject, 46	getPseudoShadow, 449
originalCoinModel	infeasibility, 445
CbcSolver, 388	multiplier_, 451
originalColumns	newBounds, 448
CbcModel, 283	numberExtraRows_, 451
originalLower_	operator=, 445
CbcSimpleInteger, 366	OsiBiLinear, 445
originalLowerBound	OsiBiLinear, 445
CbcLotsize, 250	resetSequenceEtc, 446
CbcSimpleInteger, 365	setBoundType, 448
originalModel	setBranchingStrategy, 448
CbcModel, 275	setCoefficient, 447
originalNumberRows_	setMeshSizes, 448
CbcHeuristicGreedyCover, 203	setXMeshSize, 448
CbcHeuristicGreedyEquality, 206	setXOtherSatisfied, 447
CbcHeuristicGreedySOS, 209	setXSatisfied, 447
originalObjective_	setXYSatisfied, 448
CbcObjectUpdateData, 341	setYMeshSize, 448
originalRhs_	setYOtherSatisfied, 447
CbcHeuristicGreedySOS, 209	setYSatisfied, 447
originalRowCopy	updateCoefficients, 448
OsiSolverLink, 496	xColumn, 446
originalRowCopy_	xColumn , 450
OsiSolverLink, 498	xMeshSize, 447
originalSolver	xMeshSize_, 449
CbcSolver, 388	xOtherSatisfied, 447
originalUpper_	xOtherSatisfied , 450
CbcSimpleInteger, 366	xRow, 446
originalUpperBound	xRow_, 451
CbcLotsize, 251	xSatisfied, 447
CbcSimpleInteger, 365	xSatisfied , 449
OsiBiLinear, 441	xyBranchValue_, 450
~OsiBiLinear, 445	xyCoefficient, 449
addExtraRow, 449	xyRow, 446
boundBranch, 446	xyRow_, 451
boundType, 448	xySatisfied, 448
boundType_, 450	xySatisfied_, 450
branchingStrategy, 448	yColumn, 446
branchingStrategy_, 450	yColumn_, 450
canDoHeuristics, 446	yMeshSize, 448
	yMeshSize , 449
checkInfeasibility, 446	yOtherSatisfied, 447
chosen_, 451	•
clone, 445	yOtherSatisfied_, 450
coefficient, 446	yRow, 446
coefficient_, 449	yRow_, 451
computeLambdas, 449	ySatisfied, 447
convexity_, 451	ySatisfied_, 450
createBranch, 446	OsiBiLinearBranchingObject, 452

~OsiBiLinearBranchingObject, 452	getMaximumNodes, 471
boundBranch, 453	getMaximumSeconds, 472
branch, 453	getMaximumSolutions, 472
clone, 452	getModelPtr, 471
operator=, 452	getNodeCount, 472
OsiBiLinearBranchingObject, 452	getNumCols, 463
OsiBiLinearBranchingObject, 452	getNumElements, 463
print, 453	getNumRows, 463
OsiBiLinearEquality, 453	getObjCoefficients, 464
~OsiBiLinearEquality, 454	getObjName, 466
clone, 454	getObjSense, 464
improvement, 454	getObjValue, 465
newGrid, 454	getPrimalRays, 465
numberPoints, 454	getRealSolverPtr, 471
operator=, 454	getReducedCost, 465
•	•
OsiBiLinearEquality, 454	getRightHandSide, 464
OsiBiLinearEquality, 454	getRowActivity, 465
setNumberPoints, 454	getRowLower, 464
OsiCbcHasNDEBUG	getRowName, 466
OsiCbcSolverInterface.hpp, 546	getRowNames, 466
OsiCbcInfinity	getRowPrice, 465
OsiCbcSolverInterface.hpp, 546	getRowRange, 464
OsiCbcSolverInterface, 455	getRowSense, 464
~OsiCbcSolverInterface, 461	getRowUpper, 464
addCol, 469	getStrParam, 462
addCols, 469	getWarmStart, 463
addRow, 469	initialSolve, 462
addRows, 469	isAbandoned, 462
applyColCut, 473	isContinuous, 464
applyRowCut, 473	isDualObjectiveLimitReached, 463
applyRowCuts, 469	isIterationLimitReached, 463
assignProblem, 470	isNodeLimitReached, 472
branchAndBound, 462	isPrimalObjectiveLimitReached, 462
clone, 472	isProvenDualInfeasible, 462
deleteColNames, 467	isProvenOptimal, 462
deleteCols, 469	isProvenPrimalInfeasible, 462
deleteRowNames, 466	isSolutionLimitReached, 472
deleteRows, 469	loadProblem, 469, 470
dfltRowColName, 466	markHotStart, 463
getColLower, 463	modelPtr_, 473
getColName, 466	newLanguage, 471
getColNames, 466	operator=, 473
-	•
getColSolution, 465	OsiCbcSolverInterface, 461
getColUpper, 463	OsiCbcSolverInterfaceUnitTest, 473
getCutoff, 471	OsiCbcSolverInterface, 461
getDblParam, 462	passInMessageHandler, 472
getDualRays, 465	readMps, 470
getEmptyWarmStart, 463	resolve, 462
getHintParam, 462	setColBounds, 467
getInfinity, 465	setColLower, 467
getIntParam, 462	setColName, 466
getIterationCount, 465	setColNames, 466
getMatrixByCol, 465	setColSetBounds, 467
getMatrixByRow, 464	setColSolution, 468

setColUpper, 467	feasibleRegion, 477
setContinuous, 468	infeasibility, 477
setCutoff, 471	numberLinks, 477
setDblParam, 462	operator=, 477
setHintParam, 462	OsiLink, 477
setIntParam, 462	OsiLink, 477
setInteger, 468	resetSequenceEtc, 477
setLanguage, 471	OsiLinkBranchingObject, 478
setMaximumNodes, 471	\sim OsiLinkBranchingObject, 478
setMaximumSeconds, 472	branch, 479
setMaximumSolutions, 472	clone, 479
setObjCoeff, 467	operator=, 478
setObjName, 466	OsiLinkBranchingObject, 478
setObjSense, 468	OsiLinkBranchingObject, 478
setRowBounds, 467	print, 479
setRowLower, 467	OsiLinkedBound, 479
setRowName, 466	\sim OsiLinkedBound, 480
setRowNames, 466	addBoundModifier, 480
setRowPrice, 469	operator=, 480
setRowSetBounds, 468	OsiLinkedBound, 480
setRowSetTypes, 468	OsiLinkedBound, 480
setRowType, 467	updateBounds, 480
setRowUpper, 467	variable, 480
setStrParam, 462	osiObject
setWarmStart, 463	CbcSimpleInteger, 364
solveFromHotStart, 463	CbcSOS, 393
status, 472	OsiOldLink, 480
unmarkHotStart, 463	\sim OsiOldLink, 482
writeMps, 471	boundBranch, 483
writeMpsNative, 471	canDoHeuristics, 482
OsiCbcSolverInterface.hpp	clone, 482
OsiCbcHasNDEBUG, 546	createBranch, 482
OsiCbcInfinity, 546	feasibleRegion, 482
OsiCbcSolverInterfaceUnitTest, 546	infeasibility, 482
OsiCbcSolverInterfaceUnitTest	numberLinks, 482
OsiCbcSolverInterface, 473	operator=, 482
OsiCbcSolverInterface.hpp, 546	OsiOldLink, 481, 482
OsiChooseStrongSubset, 473	OsiOldLink, 481, 482
\sim OsiChooseStrongSubset, 474	resetSequenceEtc, 482
chooseVariable, 475	OsiOldLinkBranchingObject, 483
clone, 475	~OsiOldLinkBranchingObject, 484
numberObjectsToUse, 475	branch, 484
numberObjectsToUse_, 475	clone, 484
operator=, 475	operator=, 484
OsiChooseStrongSubset, 474	OsiOldLinkBranchingObject, 484
OsiChooseStrongSubset, 474	OsiOldLinkBranchingObject, 484
setNumberObjectsToUse, 475	print, 484
setupList, 475	OsiOneLink, 484
OsiLink, 476	\sim OsiOneLink, 485
∼OsiLink, 477	function_, 485
boundBranch, 477	operator=, 485
canDoHeuristics, 477	OsiOneLink, 485
clone, 477	OsiOneLink, 485
createBranch, 477	xColumn_, 485

D 405	. (
xRow_, 485	info_, 499
xyRow, 485	initialSolve, 495
osiParams_	integerPriority, 497
CbcGenCtlBlk, 135	integerPriority_, 500
OsiSimpleFixedInteger, 486	linearizedBAB, 495
~OsiSimpleFixedInteger, 487	load, 495
clone, 488	matrix_, 498
createBranch, 488	nonlinearSLP, 495
infeasibility, 488	numberFix_, 500
operator=, 488	numberNonLinearRows_, 498
OsiSimpleFixedInteger, 487	numberVariables_, 499
OsiSimpleFixedInteger, 487	objectiveRow_, 499
OsiSolverLinearizedQuadratic, 488	objectiveVariable, 497
\sim OsiSolverLinearizedQuadratic, 489	objectiveVariable_, 499
bestObjectiveValue, 490	operator=, 495
bestObjectiveValue_, 490	originalRowCopy, 496
bestSolution, 490	originalRowCopy_, 498
bestSolution_, 491	OsiSolverLink, 494
clone, 490	OsiSolverLink, 494
initialSolve, 490	quadraticModel, 497
operator=, 490	quadraticModel_, 498
OsiSolverLinearizedQuadratic, 489	quadraticRow, 497
OsiSolverLinearizedQuadratic, 489	resolve, 495
quadraticModel, 490	rowNonLinear , 499
quadraticModel , 490	sayConvex, 496
setSpecialOptions3, 490	setBestObjectiveValue, 496
specialOptions3, 490	setBestSolution, 496
specialOptions3_, 491	setBiLinearPriorities, 498
OsiSolverLink, 491	setBiLinearPriority, 497
~OsiSolverLink, 495	setBranchingStrategyOnVariables, 498
addBoundModifier, 495	setDefaultBound, 497
addTighterConstraints, 496	setDefaultMeshSize, 497
analyzeObjects, 496	setFixedPriority, 498
bestObjectiveValue, 496	setIntegerPriority, 497
bestObjectiveValue, 500	setMeshSizes, 498
bestSolution, 496	setSpecialOptions2, 496
bestSolution_, 500	specialOptions2, 496
biLinearPriority, 497	specialOptions2, 499
biLinearPriority_, 500	startNonLinear_, 499
•	
cleanMatrix, 496	updateCoefficients, 496 whichNonLinear , 499
clone, 495	-
coinModel, 498	OsiUsesBiLinear, 500
coinModel_, 499	~OsiUsesBiLinear, 502
convex_, 499	addBiLinearObjects, 503
defaultBound, 497	clone, 502
defaultBound_, 500	createBranch, 502
defaultMeshSize, 497	feasibleRegion, 503
defaultMeshSize_, 500	infeasibility, 502
doAOCuts, 495	numberBiLinear_, 503
fathom, 495	objects_, 503
fixVariables_, 500	operator=, 502
gutsOfCopy, 498	OsiUsesBiLinear, 502
gutsOfDestructor, 498	OsiUsesBiLinear, 502
heuristicSolution, 495	type_, 503

ownObjects	parent_
CbcModel, 302	CbcNodeInfo, 325
owner	parentBranch
CbcNodeInfo, 324	CbcNodeInfo, 325
owner_	parentBranch_
CbcNodeInfo, 325	CbcNodeInfo, 325
	parentId_
Р	CbcStatistics, 400
PERTURBATION	parentModel
CbcOsiParam, 343	CbcModel, 297
PERTVALUE	parentModel_
CbcOsiParam, 344	CbcStrategyDefaultSubTree, 410
PFI	parentNode
CbcOsiParam, 344	CbcStatistics, 399
PLUSMINUS	partialNodeInfo
CbcOsiParam, 344	CbcStrategy, 405
PREPROCESS	pass
CbcGenParam, 141	•
PRESOLVE	CbcHeuristicDW, 185
	pass_
CbcOsiParam, 344	CbcHeuristicDW, 189
PRESOLVEOPTIONS	passInContinuousSolution
CbcOsiParam, 344	CbcHeuristicDW, 182
PRESOLVEPASS	passInEventHandler
CbcOsiParam, 344	CbcModel, 298
PRIMALPIVOT	passInMessageHandler
CbcOsiParam, 344	CbcGenCtlBlk, 133
PRIMALSIMPLEX	CbcModel, 298
CbcOsiParam, 344	OsiCbcSolverInterface, 472
PRIMALTOLERANCE	passInPriorities
CbcOsiParam, 344	CbcModel, 298
PRINTMASK	passInSolution
CbcGenParam, 141	CbcHeuristicDW, 182
PRINTOPTIONS	CbcTreeLocal, 424
CbcGenParam, 141	CbcTreeVariable, 427
PRINTVERSION	passInSolverCharacteristics
CbcGenParam, 141	CbcModel, 298
PRIORITYIN	passInSubTreeModel
CbcGenParam, 141	CbcModel, 294
PROBINGCUTS	passInTreeHandler
CbcGenParam, 141	CbcModel, 294
parallelMode	penaltyScaleFactor
CbcModel, 304	CbcModel, 282
paramCode	percentageToFix_
CbcCbcParam, 53	CbcHeuristicDive, 166
CbcGenParam, 143	phase
CbcOsiParam, 345	CbcHeuristicDW, 185
paramVec_	
CbcGenCtlBlk, 135	CbcModel, 292
	phase_
parameterOption	CbcHeuristicDW, 189
CbcParam, 351	pop
paramsProcessed_	CbcTree, 418
CbcGenCtlBlk, 135	CbcTreeLocal, 423
parent	CbcTreeVariable, 427
CbcNodeInfo, 323	position

CbcObject, 337	printDistanceToNodes
position_	•
•	CbcHeuristic, 152
CbcObject, 338	printFrequency
possible Chaffathara 104	CbcModel, 283
CbcFathom, 104	printLevel_
possible_	CbcStrategyDefault, 408
CbcFathom, 105	CbcStrategyDefaultSubTree, 410
possibleBranch	printLongHelp
CbcStrongInfo, 413	CbcParam, 353
preProcessPasses	printMask_
CbcStrategyDefault, 407	CbcGenCtlBlk, 135
preProcessPasses_	printMode_
CbcStrategyDefault, 408	CbcGenCtlBlk, 135
preProcessState	printOpt_
CbcStrategy, 404	CbcGenCtlBlk, 134
preProcessState_	printOptions
CbcStrategy, 405	CbcParam, 352
preferredNewFeasible	printString
CbcBranchCut, 32	CbcParam, 353
CbcLotsize, 250	priorities
CbcObject, 336	ampl_info, 25
preferredWay	priorities_
CbcObject, 338	CbcSolverUsefulData, 390
preferredWay_	priority
CbcObject, 338	CbcModel, 298
CbcSimpleInteger, 366	priorityAction_
previousBounds	CbcGenCtlBlk, 137
CbcModel, 306	probabilities_
previousBranch	CbcHeuristicJustOne, 212
CbcBranchingObject, 44	, and the second se
- ·	probingInfo
CbcSOSBranchingObject, 396	CbcModel, 308
primalSolution	problemFeasibility
ampl_info, 25	CbcModel, 294
primalSolution_	problemStatus
CbcSolverUsefulData, 390	ampl_info, 24
print	problemType
CbcBranchingObject, 45	CbcModel, 282
CbcCliqueBranchingObject, 60	process
CbcCutBranchingObject, 78	CbcStrategy, 404
CbcDummyBranchingObject, 95	process_
CbcFixingBranchingObject, 112	CbcStrategy, 405
CbcIntegerBranchingObject, 241	pseudoDown
CbcLongCliqueBranchingObject, 247	ampl_info, 25
CbcLotsizeBranchingObject, 253	pseudoDown_
CbcNode, 318	CbcSolverUsefulData, 390
CbcNWayBranchingObject, 331	pseudoRedCost
CbcSimpleIntegerDynamicPseudoCost, 378	PseudoReducedCost, 503
CbcSOSBranchingObject, 396	PseudoReducedCost, 503
CbcStatistics, 398	pseudoRedCost, 503
OsiBiLinearBranchingObject, 453	var, 503
OsiLinkBranchingObject, 479	pseudoShadow
OsiOldLinkBranchingObject, 473	CbcModel, 307
printBaBStatus	pseudoUp
•	•
CbcGenCtlBlk, 133	ampl_info, <mark>25</mark>

	0
pseudoUp_	CbcHeuristicCrossover, 157
CbcSolverUsefulData, 390	CbcHeuristicDW, 187
push	randomNumberGenerator
CbcTree, 418	CbcModel, 308
CbcTreeLocal, 423	randomNumberGenerator_
CbcTreeVariable, 427	CbcHeuristic, 153
pushCbcCbcDbl	CbcldiotBranch, 238
CbcCbcParamUtils, 21	range
pushCbcCbcInt	CbcTreeLocal, 424
CbcCbcParamUtils, 21	CbcTreeVariable, 427
pushCbcGenCutParam	rangeType
CbcGenParamUtils, 22	CbcLotsize, 251
pushCbcGenDblParam	readAmpl
CbcGenParamUtils, 22	Cbc_ampl.h, 504
pushCbcGenIntParam	readMIPStart
CbcGenParamUtils, 22	CbcMipStartIO.hpp, 531
pushCbcGenKwdParam	readMps
CbcGenParamUtils, 22	OsiCbcSolverInterface, 470
pushCbcGenStrParam	readSolution
CbcGenParamUtils, 22	CbcGenParamUtils, 21
pushCbcOsiDbl	reallyScale
CbcOsiParamUtils, 22	-
pushCbcOsiHint	ClpAmplObjective, 436
CbcOsiParamUtils, 22	ClpConstraintAmpl, 438
pushCbcOsiInt	realpop
CbcOsiParamUtils, 22	CbcTree, 419
pushCbcOsiKwd	realpush
•	CbcTree, 419
CbcOsiParamUtils, 22	rebuild
pushCbcOsiLogLevel	CbcTree, 418
CbcOsiParamUtils, 22	redoSequenceEtc
Q	CbcBranchToFixLots, 49
guadraticModel	CbcClique, 57
OsiSolverLinearizedQuadratic, 490	CbcGeneral, 138
	CbcNWay, 329
OsiSolverLink, 497	CbcObject, 338
quadraticModel_	CbcSOS, 393
OsiSolverLinearizedQuadratic, 490	redoWalkBack
OsiSolverLink, 498	CbcModel, 310
quadraticRow	reducedCostFix
OsiSolverLink, 497	CbcHeuristicDive, 165
В	CbcModel, 305
REALLY_SCALE	reducedCostMultiplier
	CbcHeuristicFPump, 199
CbcOsiParam, 344	reducedCostMultiplier_
REDSPLITCUTS	CbcHeuristicFPump, 200
CbcGenParam, 141	•
RESTORE	reducedGradient
CbcOsiParam, 344	ClpAmplObjective, 435
REVERSE	referenceSolver
CbcOsiParam, 344	CbcModel, 303
RHSSCALE	refine
CbcOsiParam, 344	CbcTreeLocal, 425
ROUNDING	CbcTreeVariable, 428
CbcGenParam, 141	refreshModel
random_	CbcCutGenerator, 83

relativeIncrement	CbcModel, 274, 305
CbcHeuristicFPump, 196	OsiCbcSolverInterface, 462
relativeIncrement_	OsiSolverLink, 495
CbcHeuristicFPump, 199	resolveAfterTakeOffCuts
rensType_	CbcModel, 293
CbcHeuristicRENS, 229	restart
reserveCurrentSolution	CbcEventHandler, 101
CbcModel, 290	restartRoot
resetBounds	CbcEventHandler, 101
CbcBranchCut, 32	reverseCut
CbcLotsize, 250	CbcTreeLocal, 424
CbcObject, 336	CbcTreeVariable, 427
CbcSimpleInteger, 365	rhs
resetModel	CbcFathomDynamicProgramming, 109
CbcFathom, 104	CbcFollowOn, 117
CbcFathomDynamicProgramming, 107	rootObjectiveAfterCuts
CbcHeuristic, 148	CbcModel, 292
CbcHeuristicCrossover, 156	roundExpensive_
	· —
CbcHeuristicDINS, 159	CbcHeuristicFPump, 200
CbcHeuristicDive, 163	rowCutPtr
CbcHeuristicDW, 181	CbcRowCuts, 360
CbcHeuristicDynamic3, 192	rowLower
CbcHeuristicFPump, 195	ampl_info, 24
CbcHeuristicGreedyCover, 202	rowNonLinear_
CbcHeuristicGreedyEquality, 205	OsiSolverLink, 499
CbcHeuristicGreedySOS, 209	rowStatus
CbcHeuristicJustOne, 211	ampl_info, 25
CbcHeuristicLocal, 214	rowUpper
CbcHeuristicNaive, 216	ampl_info, 24
CbcHeuristicPartial, 220	rows
CbcHeuristicPivotAndFix, 222	ampl_info, 25
CbcHeuristicProximity, 224	rowsInBlock_
CbcHeuristicRandRound, 227	CbcHeuristicDW, 188
CbcHeuristicRENS, 228	runNodes
CbcHeuristicRINS, 231	CbcHeuristic, 154
CbcHeuristicVND, 234	
CbcModel, 303	S
CbcRounding, 358	SAVE
CbcSerendipity, 362	CbcOsiParam, 344
resetNodeNumbers	SCALING
CbcTree, 419	CbcOsiParam, 344
resetNumberBranchesLeft	SHOWUNIMP
CbcBranchingObject, 44	CbcGenParam, 142
resetSequenceEtc	SLPVALUE
CbcSimpleInteger, 365	CbcOsiParam, 344
OsiBiLinear, 446	SOLUTION
OsiLink, 477	CbcGenParam, 142
OsiOldLink, 482	SOLVECONTINUOUS
resetToReferenceSolver	CbcGenParam, 142
CbcModel, 303	SOLVER
resize	CbcGenParam, 142
ClpAmplObjective, 435	SOLVERLOGLEVEL
ClpConstraintAmpl, 438	CbcOsiParam, 344
resolve	SOS

CbcGenParam, 142	searchStrategy
SPARSEFACTOR	CbcModel, 295
CbcOsiParam, 344	secondaryStatus
SPECIALOPTIONS	CbcModel, 284
CbcOsiParam, 344	seed_
SPRINT	CbcRounding, 359
CbcOsiParam, 344	selectBinaryVariables
STDIN	CbcHeuristicDive, 164
CbcGenParam, 142	selectVariableToBranch
STRENGTHEN	CbcHeuristicDive, 165
CbcGenParam, 142	CbcHeuristicDiveCoefficient, 168
STRONGBRANCHING	CbcHeuristicDiveFractional, 169
CbcCbcParam, 52	CbcHeuristicDiveGuided, 171
SCANCUTS	CbcHeuristicDiveLineSearch, 172
CbcCutGenerator.hpp, 516	CbcHeuristicDivePseudoCost, 174
SCANCUTS_PROBING	CbcHeuristicDiveVectorLength, 176
CbcCutGenerator.hpp, 516	CbcHeuristicJustOne, 211
same	sequence_
CbcSimpleIntegerDynamicPseudoCost, 378	CbcStatistics, 400
saveBestSolution	setAbsoluteIncrement
CbcModel, 305	CbcHeuristicFPump, 196
saveBranchingObject	setAccumulate
CbcBranchDecision, 34	CbcHeuristicFPump, 198
CbcBranchDynamicDecision, 40	setAction
saveExtraSolution	CbcEventHandler, 102
CbcModel, 305	setActive
saveLower_	CbcNode, 317
CbcHeuristicDW, 187	setAlgorithm
saveModel	CbcFathomDynamicProgramming, 108
CbcModel, 275	CbcHeuristicGreedyCover, 203
saveReferenceSolver	CbcHeuristicGreedyEquality, 206
CbcModel, 303	CbcHeuristicGreedySOS, 209
saveSolution	setAllowableFractionGap
CbcGenParamUtils, 21	CbcModel, 279
saveUpper_	setAllowableGap
CbcHeuristicDW, 187	CbcModel, 278
saveWeight_	setAllowablePercentageGap
CbcCompareDefault, 68	CbcModel, 279
savedRandomNumberGenerator_	setApplicationData
CbcldiotBranch, 238	CbcModel, 298
savedSolution	setArtificialCost
CbcModel, 291	CbcHeuristicFPump, 197
savedSolutionObjective	setAtSolution
CbcModel, 292	CbcCutGenerator, 85
sayConvex	setBaBStatus
OsiSolverLink, 496	CbcGenCtlBlk, 133
sayEventHappened	setBestCriterion
CbcModel, 300	CbcBranchDecision, 35
sayInfeasible	CbcBranchDefaultDecision, 37
CbcStatistics, 398	CbcBranchDynamicDecision, 39
sayThreaded	setBestObjectiveValue
CbcCompareBase, 64	CbcModel, 289
scaleBackStatistics	OsiSolverLink, 496
CbcCutGenerator, 89	setBestPossible

CbcCompareDefault, 67	OsiCbcSolverInterface, 467
setBestSolution	setColumnNumber
CbcModel, 289, 291	CbcSimpleInteger, 365
OsiSolverLink, 496	setCombineAction
setBestSolutionBasis	CbcGenCtlBlk, 132
CbcModel, 310	setComparison
setBiLinearPriorities	CbcTree, 418
OsiSolverLink, 498	setConsequence
setBiLinearPriority	CbcNWay, 328
OsiSolverLink, 497	setConstraint
setBoundType	CbcHeuristicDINS, 160
OsiBiLinear, 448	setContinuous
setBranchingMethod	OsiCbcSolverInterface, 468
CbcModel, 295	setContinuousInfeasibilities
setBranchingObject	CbcModel, 292
CbcNode, 317	setContinuousObjective
setBranchingStrategy	CbcModel, 292
OsiBiLinear, 448	setContinuousPriority
	CbcModel, 309
setBranchingStrategyOnVariables	•
OsiSolverLink, 498	setCurrentNumberNeeded
setBreadthDepth	CbcHeuristicDW, 183
CbcCompareDefault, 67	setCurrentNumberNodes
setBreakEven	CbcHeuristicDW, 184
CbcSimpleInteger, 366	setCurrentOption
setByUser_	CbcParam, 352
CbcGenCtlBlk, 136	setCurrentPassNumber
setCbcModel	CbcModel, 281
CbcOsiSolver, 347	setCutAndHeuristicOptions
setCbcModelDefaults	CbcModel.hpp, 532
CbcCbcParamUtils, 20	setCutDepth
setChangeInGuessed	CbcGenCtlBlk, 130
CbcDynamicPseudoCostBranchingObject, 98	setCutModifier
CbcIntegerPseudoCostBranchingObject, 245	CbcModel, 295
setChooseMethod	setCutoff
CbcBranchDecision, 35	CbcCompareDefault, 67
setCliqueAction	CbcModel, 277
CbcGenCtlBlk, 130	OsiCbcSolverInterface, 471
setCoefficient	setCutoffAsConstraint
OsiBiLinear, 447	CbcModel, 301
setColBounds	setCutoffIncrement
OsiCbcSolverInterface, 467	CbcModel, 279
setColLower	setDblParam
CbcFullNodeInfo, 120	CbcModel, 277
OsiCbcSolverInterface, 467	OsiCbcSolverInterface, 462
setColName	setDecayFactor
OsiCbcSolverInterface, 466	CbcHeuristic, 151
setColNames	setDefaultBound
OsiCbcSolverInterface, 466	OsiSolverLink, 497
setColSetBounds	setDefaultHandler
OsiCbcSolverInterface, 467	CbcModel, 299
setColSolution	setDefaultMeshSize
OsiCbcSolverInterface, 468	OsiSolverLink, 497
setColUpper	setDefaultRounding
CbcFullNodeInfo, 121	CbcHeuristicFPump, 196

setDepth	CbcModel, 279
CbcNode, 316	setHeuristicModel
setDfltAction	CbcModel, 294
CbcEventHandler, 102	setHeuristicName
setDoubleParameter	CbcHeuristic, 151
CbcParam, 350, 351	setHintParam
setDoubleValue	OsiCbcSolverInterface, 462
CbcParam, 352	setHotstartSolution
CbcSolver, 388	CbcModel, 280
setDownBounds	setHowOften
CbcIntegerBranchingObject, 241	CbcCutGenerator, 83
setDownDynamicPseudoCost	CbcHeuristicDINS, 160
CbcSimpleIntegerDynamicPseudoCost, 373 setDownInformation	CbcHeuristicDW, 184
	CbcHeuristicRINS, 231
CbcSimpleIntegerDynamicPseudoCost, 377	CbcHeuristicVND, 235
setDownPseudoCost	setHowOftenGlobalScan
CbcSimpleIntegerPseudoCost, 383 setDownShadowPrice	CbcModel, 282
	setHowOftenShallow
CbcSimpleIntegerDynamicPseudoCost, 373	CbcHeuristic, 152 setIPPAction
setFPumpAction	
CbcGenCtlBlk, 131	CbcGenCtlBlk, 130
setFakeCutoff	setId
CbcHeuristicFPump, 196	CbcObject, 337
setFastNodeDepth	setInaccuracy
CbcModel, 309	CbcCutGenerator, 84
setFeasibilityPumpOptions CbcHeuristic, 150	setIncrement
setFixOnReducedCosts	CbcHeuristicProximity, 225 setIneffectualCuts
CbcHeuristicFPump, 198	CbcCutGenerator, 88
setFixPriority	setInfeasibilityWeight
CbcHeuristicPartial, 221	CbcModel, 278
setFixedPriority	setInfo
OsiSolverLink, 498	CbcCountRowCut, 76
setFlowAction	setInfoInChild
CbcGenCtlBlk, 130	CbcModel, 305
setFraction	setInitialWeight
CbcHeuristicGreedyEquality, 206	CbcHeuristicFPump, 197
setFractionSmall	setInputSolution
CbcHeuristic, 150	CbcHeuristic, 151
setGlobalCuts	setIntParam
CbcCutGenerator, 89	CbcModel, 277
setGlobalCutsAtRoot	OsiCbcSolverInterface, 462
CbcCutGenerator, 89	setIntParameter
setGomoryAction	CbcParam, 351
CbcGenCtlBlk, 131	setIntValue
setGreedyCoverAction	CbcParam, 352
CbcGenCtlBlk, 132	CbcSolver, 388
setGreedyEqualityAction	setInteger
CbcGenCtlBlk, 132	OsiCbcSolverInterface, 468
setGuessedObjectiveValue	setIntegerPriority
CbcNode, 316	OsiSolverLink, 497
setHeuristicFractionGap	setIntegerTolerance
CbcModel, 279	CbcModel, 278
setHeuristicGap	setIntegerValued
33. 10ti 34p	SSERIES SOLVER

CbcSOS, 394	setMaximumSize
setIterationRatio	CbcFathomDynamicProgramming, 108
CbcHeuristicFPump, 197	setMaximumSolutions
setKnapsackAction	CbcModel, 277
CbcGenCtlBlk, 131	OsiCbcSolverInterface, 472
setLanguage	setMaximumTime
CbcModel, 299	CbcHeuristicFPump, 196
OsiCbcSolverInterface, 471	setMaximumTries
setLargeValue	CbcCutGenerator, 84
CbcHeuristicNaive, 217	setMeshSizes
setLastHeuristic	OsiBiLinear, 448
CbcModel, 297	OsiSolverLink, 498
setLastNode	setMessages
CbcHeuristicRINS, 232	CbcGenCtlBlk, 134
setLogLevel	setMethod
CbcGenCtlBlk, 134	CbcSimpleIntegerDynamicPseudoCost, 377
CbcModel, 299	CbcSimpleIntegerPseudoCost, 384
setLonghelp	setMinDistanceToRun
CbcParam, 353	CbcHeuristic, 152
setMIPStart	setMinimizationObjValue
CbcModel, 310	CbcModel, 290
setMaxDiversification	setMinimumDrop
CbcTreeLocal, 424	CbcModel, 280
CbcTreeVariable, 428	setMirAction
setMaxIterations	CbcGenCtlBlk, 131
CbcHeuristicDive, 164	setModel
setMaxSimplexIterations	CbcBranchingObject, 45
CbcHeuristicDive, 164	CbcCutGenerator, 89
setMaxSimplexIterationsAtRoot	CbcEventHandler, 102
CbcHeuristicDive, 165 setMaxTime	CbcFathom, 104
	CbcFathomDynamicProgramming, 107
CbcHeuristicDive, 165	CbcHeuristic, 148
setMaximumBranching	CbcHeuristicCrossover, 157
CbcTree, 420	CbcHeuristicDINS, 159
setMaximumCutPasses	CbcHeuristicDive, 164
CbcModel, 280	CbcHeuristicDW, 182
setMaximumCutPassesAtRoot	CbcHeuristicDynamic3, 191
CbcModel, 280	CbcHeuristicFPump, 195
setMaximumKeep	CbcHeuristicGreedyCover, 202
CbcHeuristicDINS, 160	CbcHeuristicGreedyEquality, 205
setMaximumNodes	CbcHeuristicGreedySOS, 208
CbcModel, 277	CbcHeuristicJustOne, 211
OsiCbcSolverInterface, 471	CbcHeuristicLocal, 214
setMaximumNumberIterations	CbcHeuristicNaive, 216
CbcModel, 309	CbcHeuristicPartial, 220
setMaximumPasses	CbcHeuristicPivotAndFix, 222
CbcHeuristicFPump, 197	CbcHeuristicProximity, 224
setMaximumRetries	CbcHeuristicRandRound, 227
CbcHeuristicFPump, 198	CbcHeuristicRENS, 228
setMaximumSavedSolutions	CbcHeuristicRINS, 231
CbcModel, 291	CbcHeuristicVND, 235
setMaximumSeconds	CbcObject, 337
CbcModel, 278	CbcRounding, 358
OsiCbcSolverInterface, 472	CbcSerendipity, 361

	Obs Out Osus sustant OO
setModelOnly	CbcCutGenerator, 86
CbcHeuristic, 150	setNumberElementsInTotal
setModelOwnsSolver	CbcCutGenerator, 86
CbcModel, 302	setNumberHeuristicSolutions
setModelSequence	CbcModel, 292
CbcLotsize, 250	setNumberHeuristics
setMoreSpecialOptions	CbcModel, 297
CbcModel, 300	setNumberMembers
setMoreSpecialOptions2	CbcSOS, 394
CbcModel, 301	setNumberNeeded
setMultipleRootTries	CbcHeuristicDW, 183
CbcModel, 300	setNumberNodes
setMustCallAgain	CbcHeuristic, 149
CbcCutGenerator, 87	CbcHeuristicDW, 184
setNeedsOptimalBasis	setNumberObjects
CbcCutGenerator, 87	CbcModel, 276
setNested	setNumberObjectsToUse
CbcStrategy, 404	OsiChooseStrongSubset, 475
setNextRowCut	setNumberPasses
CbcModel, 308	CbcHeuristicDW, 183
setNodeComparison	setNumberPenalties
CbcModel, 294	CbcModel, 282
setNodeLimit	setNumberPointingToThis
CbcTreeLocal, 425	CbcNodeInfo, 323
CbcTreeVariable, 428	setNumberPoints
setNodeNumber	OsiBiLinearEquality, 454
CbcNode, 317	setNumberShortCutsAtRoot
CbcNodeInfo, 324	CbcCutGenerator, 89
setNormal	setNumberSolutions
CbcCutGenerator, 85	CbcHeuristicCrossover, 157
setNumberActiveCutsAtRoot	setNumberStrong
CbcCutGenerator, 89	CbcModel, 281
setNumberAnalyzeIterations	setNumberStrongIterations
CbcModel, 282	CbcModel, 308
setNumberBadPasses	setNumberThreads
CbcHeuristicDW, 183	CbcModel, 304
setNumberBeforeTrust	setNumberTimes
CbcModel, 281	CbcHeuristicGreedyCover, 203
CbcSimpleIntegerDynamicPseudoCost, 377	CbcHeuristicGreedyEquality, 206
setNumberBranches	CbcHeuristicGreedySOS, 209
CbcBranchingObject, 44	setNumberTimesDown
setNumberBranchesLeft	CbcSimpleIntegerDynamicPseudoCost, 376
CbcNodeInfo, 322	setNumberTimesDownInfeasible
setNumberBranching	CbcSimpleIntegerDynamicPseudoCost, 376
CbcTree, 419	setNumberTimesEntered
setNumberColumnCuts	CbcCutGenerator, 86
CbcCutGenerator, 86	setNumberTimesUp
setNumberCuts	CbcSimpleIntegerDynamicPseudoCost, 376
CbcNodeInfo, 324	setNumberTimesUpInfeasible
setNumberCutsActive	CbcSimpleIntegerDynamicPseudoCost, 376
CbcCutGenerator, 87	setNumberUnsatisfied
setNumberCutsAtRoot	CbcNode, 316
CbcCutGenerator, 88	setObj
setNumberCutsInTotal	CbcCbcParam, 53
	•

CbcGenParam, 143	CbcModel, 283
CbcOsiParam, 345	setPrinting
setObjCoeff	CbcSolver, 389
OsiCbcSolverInterface, 467	setPrintingMode
setObjName	CbcModel, 278
-	
OsiCbcSolverInterface, 466	setProbingAction
setObjSense	CbcGenCtlBlk, 130
CbcModel, 292	setProbingInformation
OsiCbcSolverInterface, 468	CbcSimpleIntegerDynamicPseudoCost, 377
setObjValue	setProblemFeasibility
CbcModel, 291	CbcModel, 294
setObject	setProblemStatus
CbcDynamicPseudoCostBranchingObject, 98	CbcModel, 284
setObjectiveValue	setProblemType
CbcModel, 307	CbcModel, 282
CbcNode, 316	setProposalActions
setOnTree	CbcHeuristicDW, 182
CbcNode, 317	setRandomSeed
setOptionalInteger	CbcModel, 300
CbcModel, 276	setRange
setOriginalCoinModel	CbcTreeLocal, 424
CbcSolver, 388	CbcTreeVariable, 427
setOriginalColumns	setReadMode
CbcModel, 283	CbcSolver, 389
setOriginalLowerBound	setRedSplitAction
CbcSimpleInteger, 365	CbcGenCtlBlk, 131
setOriginalObject	setReducedCostMultiplier
CbcBranchingObject, 45	CbcHeuristicFPump, 198
setOriginalSolver	setRefine
CbcSolver, 388	CbcTreeLocal, 425
setOriginalUpperBound	CbcTreeVariable, 428
CbcSimpleInteger, 365	setRelativeIncrement
setOsiSolverInterfaceDefaults	CbcHeuristicFPump, 196
CbcOsiParamUtils, 22	setRensType
setParamCode	
	CbcHeuristicRENS, 229
CbcCbcParam, 53	setResolveAfterTakeOffCuts
CbcGenParam, 143	CbcModel, 293
CbcOsiParam, 345	setRoundingAction
setParentModel	CbcGenCtlBlk, 132
CbcModel, 297	setRowBounds
setPenaltyScaleFactor	OsiCbcSolverInterface, 467
CbcModel, 282	setRowLower
setPercentageToFix	OsiCbcSolverInterface, 467
CbcHeuristicDive, 164	setRowName
setPointers	OsiCbcSolverInterface, 466
CbcModel, 305	setRowNames
setPosition	OsiCbcSolverInterface, 466
CbcObject, 337	setRowPrice
setPreProcessState	OsiCbcSolverInterface, 469
CbcStrategy, 404	setRowSetBounds
setPreferredWay	OsiCbcSolverInterface, 468
CbcModel, 281	setRowSetTypes
CbcObject, 338	OsiCbcSolverInterface, 468
setPrintFrequency	setRowType

0-10-0-10-1-1-1-1-1-1-1-1-1-1-1-1-1-1-1	010
OsiCbcSolverInterface, 467	CbcCutGenerator, 87
setRowUpper	setSwitchedOff
OsiCbcSolverInterface, 467	CbcCutGenerator, 87
setSearchStrategy	setSwitches
CbcModel, 296	CbcHeuristic, 149
setSearchType	setTarget
CbcHeuristicLocal, 214	CbcFathomDynamicProgramming, 108
setSecondaryStatus	setTargetObjective
CbcModel, 285	CbcHeuristicDW, 184
setSeed	setTemporaryPointer
CbcHeuristic, 151	CbcModel, 301
CbcRounding, 358	setTestSolution
setShallowDepth	CbcModel, 289
CbcHeuristic, 151	setThreadMode
setSolutionCount	CbcModel, 304
CbcHeuristicRINS, 232	setTimeLimit
CbcModel, 291	CbcTreeLocal, 425
setSpecialOptions	CbcTreeVariable, 428
CbcModel, 299	setTiming
setSpecialOptions2	CbcCutGenerator, 85
OsiSolverLink, 496	setTreeLocalAction
setSpecialOptions3	CbcGenCtlBlk, 133
OsiSolverLinearizedQuadratic, 490	setTwomirAction
setState	CbcGenCtlBlk, 131
CbcNode, 317	setTypeCuts
setStateOfSearch	CbcTreeLocal, 424
CbcModel, 295	CbcTreeVariable, 428
setStopNumberIterations	setTypePresolve
CbcModel, 293	CbcModel, 295
setStoredRowCuts	setUpBounds
CbcModel, 310	CbcIntegerBranchingObject, 242
setStrParam	setUpDownSeparator
OsiCbcSolverInterface, 462	CbcSimpleIntegerDynamicPseudoCost, 374
setStrategy	CbcSimpleIntegerPseudoCost, 383
CbcModel, 297	setUpDynamicPseudoCost
setStringValue	CbcSimpleIntegerDynamicPseudoCost, 373
CbcParam, 352	setUpInformation
setStrongStrategy	CbcSimpleIntegerDynamicPseudoCost, 377
CbcModel, 296	setUpPseudoCost
setSumDownChange	CbcSimpleIntegerPseudoCost, 383
CbcSimpleIntegerDynamicPseudoCost, 374	setUpShadowPrice
setSumDownCost	CbcSimpleIntegerDynamicPseudoCost, 373
CbcSimpleIntegerDynamicPseudoCost, 374	setUseElapsedTime
setSumDownDecrease	CbcModel, 301
CbcSimpleIntegerDynamicPseudoCost, 375	setUserCallBack
setSumInfeasibilities	CbcSolver, 387
CbcNode, 316	setWarmStart
setSumUpChange	OsiCbcSolverInterface, 463
CbcSimpleIntegerDynamicPseudoCost, 375	setWeight 67
setSumUpCost	CbcCompareDefault, 67
CbcSimpleIntegerDynamicPseudoCost, 374	setWeightFactor
setSumUpDecrease	CbcHeuristicFPump, 197
CbcSimpleIntegerDynamicPseudoCost, 375	setWhatDepth
setSwitchOfflfLessThan	CbcCutGenerator, 84

setWhatDepthInSub	CbcStrategyDefaultSubTree, 410
CbcCutGenerator, 84	CbcStrategyNull, 412
setWhen	shadowPriceMode_
CbcHeuristic, 149	CbcGenCtlBlk::chooseStrongCtl_struct, 433
setWhenCuts	shallWe
CbcModel, 281	CbcBranchToFixLots, 49
setWhenInfeasible	shallowDepth_
CbcCutGenerator, 85	CbcHeuristic, 154
setWhereFrom	shortHelp
CbcHeuristic, 151	CbcParam, 350
setWhetherCallAtEnd	shouldHeurRun
CbcCutGenerator, 88	CbcHeuristic, 152
setWhetherInMustCallAgainMode	CbcHeuristicPartial, 221
CbcCutGenerator, 88	shouldHeurRun_randomChoice
setWhetherToUse	CbcHeuristic, 152
CbcCutGenerator, 88	SimpleIntegerBranchObj
setXMeshSize	CbcBranchingObject.hpp, 512
OsiBiLinear, 448	SimpleIntegerDynamicPseudoCostBranchObj
setXOtherSatisfied	CbcBranchingObject.hpp, 512
OsiBiLinear, 447	size
setXSatisfied	CbcHeuristicNodeList, 219
OsiBiLinear, 447	CbcTree, 418
setXYSatisfied	
	SizeChaFathamDynamiaDragramming_100
OsiBiLinear, 448	CbcFathomDynamicProgramming, 108
setYMeshSize	sizeFingerPrint_
OsiBiLinear, 448	CbcHeuristicDW, 189
setYOtherSatisfied	sizeRowCuts
OsiBiLinear, 447	CbcRowCuts, 360
setYSatisfied	slack_
OsiBiLinear, 447	CbcClique, 58
setupCutGenerators	smallBranchAndBound
CbcStrategy, 404	CbcEventHandler, 101
CbcStrategyDefault, 407	smallBranchAndBound
CbcStrategyDefaultSubTree, 409	CbcHeuristic, 150
CbcStrategyNull, 411	SoSBranchObj
setupForDiving_	CbcBranchingObject.hpp, 512
CbcCompareDefault, 69	solution
setupHeuristics	CbcEventHandler, 101
CbcStrategy, 404	CbcHeuristic, 148
CbcStrategyDefault, 407	CbcHeuristicCrossover, 157
CbcStrategyDefaultSubTree, 409	CbcHeuristicDINS, 159
CbcStrategyNull, 411	CbcHeuristicDive, 164
setupList	CbcHeuristicDW, 182
OsiChooseStrongSubset, 475	CbcHeuristicDynamic3, 191
setupOther	CbcHeuristicFPump, 195
CbcStrategy, 404	CbcHeuristicGreedyCover, 202
CbcStrategyDefault, 407	CbcHeuristicGreedyEquality, 205
CbcStrategyDefaultSubTree, 410	CbcHeuristicGreedySOS, 208
CbcStrategyNull, 412	CbcHeuristicJustOne, 211
setupPreProcessing	CbcHeuristicLocal, 214
CbcStrategyDefault, 407	CbcHeuristicNaive, 216
setupPrinting	CbcHeuristicPartial, 220
CbcStrategy, 404	CbcHeuristicPivotAndFix, 223
CbcStrategyDefault, 407	CbcHeuristicProximity, 224

CbcHeuristicRandRound, 227	OsiSolverLinearizedQuadratic, 490
CbcHeuristicRENS, 229	specialOptions3_
CbcHeuristicRINS, 231	OsiSolverLinearizedQuadratic, 491
CbcHeuristicVND, 235	splitModel
CbcRounding, 358	CbcModel, 305
CbcSerendipity, 362	startBit_
solution2	CbcFathomDynamicProgramming, 109
CbcHeuristic, 148	startColumnBlock
solutionFix	CbcHeuristicDW, 185
CbcHeuristicDINS, 160	startColumnBlock_
CbcHeuristicLocal, 214	CbcHeuristicDW, 188
CbcHeuristicRINS, 231	startDive
CbcHeuristicVND, 235	CbcCompareDefault, 68
solve	startLower_
CbcSolver, 387	CbcFixVariable, 115
CbcUser, 431	startNodeNumber
solveFromHotStart	CbcCompareDefault, 68
OsiCbcSolverInterface, 463	startNonLinear
solveState	OsiSolverLink, 499
CbcHeuristicDW, 190	startRowBlock
solver	CbcHeuristicDW, 188
CbcHeuristicDW, 182	startSplitModel
CbcModel, 302	CbcModel, 305
solver	startTime
CbcHeuristicDW, 186	CbcSolver, 389
solverBranch	startTime
CbcObject, 336	CbcHeuristicFPump, 199
CbcSimpleInteger, 365	startUpper_
CbcSimpleIntegerDynamicPseudoCost, 372	CbcFixVariable, 115
CbcSOS, 393	startingInfeasibility
solverCharacteristics	CbcStatistics, 399
CbcModel, 298	
sosIndices	startingInfeasibility_ CbcStatistics, 400
	•
ampl_info, 26	startingObjective
sosPriority	CbcStatistics, 399
ampl_info, 25	startingObjective_
sosPriority_	CbcStatistics, 399
CbcSolverUsefulData, 390	starts
sosReference	ampl_info, 25
ampl_info, 26	stateOfFixing_
sosStart	CbcHeuristicRINS, 232
ampl_info, 25	stateOfSearch
sosType	CbcModel, 295
ampl_info, 25	states_
CbcSOS, 393	CbcFixVariable, 115
special	status
ampl_info, 26	CbcModel, 284
specialOptions	CbcStrategy, 405
CbcModel, 300	OsiCbcSolverInterface, 472
specialOptions2	status_
OsiSolverLink, 496	CbcObjectUpdateData, 340
specialOptions2_	stepLength
OsiSolverLink, 499	ClpAmplObjective, 435
specialOptions3	stepSize

CbcHeuristicVND, 236	CbcCutGenerator, 84
stop	CbcHeuristic, 149
CbcEventHandler, 101	switches
storedRowCuts	CbcHeuristic, 153
CbcModel, 309	synchronizeHandlers
strategy	CbcModel, 305
CbcModel, 296	synchronizeModel
stringValue	CbcModel, 276
CbcParam, 352	synchronizeNumberBeforeTrust
strongInfo	CbcModel, 307
CbcModel, 309	3333., 33.
strongStrategy	Т
CbcModel, 296	TIGHTEN
stuff	CbcOsiParam, 344
CbcUser, 430	TIGHTENFACTOR
subTreeModel	CbcGenParam, 142
CbcModel, 294	TIMELIMIT_BAB
sumChangeObjective	CbcCbcParam, 52
CbcModel, 293	TWOMIRCUTS
sumDownChange	CbcGenParam, 142
CbcSimpleIntegerDynamicPseudoCost, 374	TYPE2
sumDownChange_	CbcSimpleIntegerDynamicPseudoCost.hpp, 539
CbcSimpleIntegerDynamicPseudoCost, 378	TYPERATIO
sumDownCost	CbcSimpleIntegerDynamicPseudoCost.hpp, 539
CbcSimpleIntegerDynamicPseudoCost, 374	takeAction
sumDownCost	CbcEventHandler, 101
CbcSimpleIntegerDynamicPseudoCost, 378	takeOffCuts
sumDownDecrease	CbcModel, 306
CbcSimpleIntegerDynamicPseudoCost, 375	
sumDownDecrease	target CbcFathomDynamicProgramming, 108
CbcSimpleIntegerDynamicPseudoCost, 379	
sumInfeasibilities	target_ CbcFathomDynamicProgramming, 109
CbcNode, 316	targetObjective_
sumUpChange	CbcHeuristicDW, 185
CbcSimpleIntegerDynamicPseudoCost, 375	temporaryPointer
sumUpChange_	CbcModel, 301
• • -	
CbcSimpleIntegerDynamicPseudoCost, 378	CheCompareRess 64
sumUpCost CbcSimpleIntegerDynamicPseudoCost, 374	CbcCompareBase, 64
	CbcCompareDefault, 67 CbcCompareDepth, 70
sumUpCostCheSimpleIntegerDynamieRegudeCost_278	CbcCompareDepth, 70 CbcCompareEstimate, 71
CbcSimpleIntegerDynamicPseudoCost, 378	CbcCompareEstimate, 71 CbcCompareObjective, 72
sumUpDecrease CheSimpleIntegerDynamicBeaudeCest 275	•
CbcSimpleIntegerDynamicPseudoCost, 375	testChaCampara_61
sumUpDecrease_	CbcCompare, 61
CbcSimpleIntegerDynamicPseudoCost, 379	CbcCompareBase, 64
Swap_	testSolution
CbcHeuristicLocal, 214	CbcModel, 289
swapSolver	threaded_
CbcModel, 302	CbcCompareBase, 64
switchOffIfLessThan	threshold_ Chacanati Bilandi Eivat Latruat 440
CbcCutGenerator, 87	CbcGenCtlBlk::djFixCtl_struct, 440
switchedOff ChcCutCongrator 87	throwAway CheNodoInfo 323
CbcCutGenerator, 87	CbcNodeInfo, 323
switches	tighten

CbcBranchingObject, 44	CbcTreeVariable, 428
CbcIntegerBranchingObject, 241	typePresolve
tightenVubs	CbcModel, 294
CbcModel, 275	
timeInCutGenerator	U
CbcCutGenerator, 85	UNITTEST
timeLimit	CbcGenParam, 142
CbcTreeLocal, 424	USERCBC
CbcTreeVariable, 428	CbcGenParam, 142
timing	USESOLUTION
CbcCutGenerator, 85	CbcGenParam, 142
top	unlockThread
CbcTree, 418	CbcModel, 304
CbcTreeLocal, 423	unmark
CbcTreeVariable, 427	CbcNodeInfo, 325
topOfTree	unmarkHotStart
CbcModel, 282	OsiCbcSolverInterface, 463
totalTime	unsetParentBasedData
CbcGenCtlBlk, 136	CbcNodeInfo, 325
translateMajor	up_
CbcGenCtlBlk, 133	CbcCutBranchingObject, 79
translateMinor	CbcIntegerBranchingObject, 242
CbcGenCtlBlk, 133	CbcLotsizeBranchingObject, 254
tree	CbcRounding, 359
CbcModel, 294	upArray_
treeStatus	CbcHeuristicDive, 166
CbcEventHandler, 101	upBounds
treeSize	CbcIntegerBranchingObject, 241
CbcCompareDefault, 68	upDownSeparator
tryColumn	CbcSimpleIntegerDynamicPseudoCost, 373
CbcFathomDynamicProgramming, 108	CbcSimpleIntegerPseudoCost, 383
twoWay	upDownSeparator_
CbcNWayBranchingObject, 331	CbcSimpleIntegerDynamicPseudoCost, 378
type CbcBranchingObject, 46	CbcSimpleIntegerPseudoCost, 384
	upDynamicPseudoCost
CbcClique, 57	CbcSimpleIntegerDynamicPseudoCost, 373
CbcCliqueBranchingObject, 60	upDynamicPseudoCost_
CbcCutBranchingObject, 78	CbcSimpleIntegerDynamicPseudoCost, 378
CbcDummyBranchingObject, 95	upEstimate
CbcDynamicPseudoCostBranchingObject, 98	CbcSimpleIntegerDynamicPseudoCost, 377
CbcFixingBranchingObject, 112	CbcSimpleIntegerPseudoCost, 383
CbcIntegerBranchingObject, 242	upLocks_
CbcIntegerPseudoCostBranchingObject, 245	CbcHeuristicDive, 166
CbcLongCliqueBranchingObject, 247	upMovement
CbcLotsizeBranchingObject, 253	CbcStrongInfo, 413
CbcNWayBranchingObject, 331	upPseudoCost
CbcParam, 352	CbcSimpleIntegerPseudoCost, 383
CbcSOSBranchingObject, 396	upPseudoCost_
type_	CbcSimpleIntegerPseudoCost, 384
CbcClique, 57	upShadowPrice
CbcFathomDynamicProgramming, 108	CbcSimpleIntegerDynamicPseudoCost, 373
OsiUsesBiLinear, 503	upShadowPrice_
typeCuts	CbcSimpleIntegerDynamicPseudoCost, 379
CbcTreeLocal, 424	updateAfter

ChaCiman la luta da VD. va a maia Da a vala Ca at 1970	validata
CbcSimpleIntegerDynamicPseudoCost, 372	validate
updateAfterMini	CbcHeuristic, 149
CbcSimpleIntegerDynamicPseudoCost, 372	CbcHeuristicDive, 164
updateBefore	CbcHeuristicGreedyCover, 202
CbcSimpleIntegerDynamicPseudoCost, 372	CbcHeuristicGreedyEquality, 205
updateBounds	CbcHeuristicGreedySOS, 208
OsiLinkedBound, 480	CbcHeuristicJustOne, 212
updateCoefficients	CbcHeuristicPartial, 221
OsiBiLinear, 448	CbcRounding, 358
OsiSolverLink, 496	value
updateDownDynamicPseudoCost	CbcStatistics, 399
CbcSimpleIntegerDynamicPseudoCost, 373	value_
updateInfeasibility	CbcStatistics, 399
CbcStatistics, 398	values_
updateInformation	CbcGenCtlBlk::debugSolInfo_struct, 440
CbcBranchDecision, 35	CbcHeuristicDINS, 161
CbcBranchDynamicDecision, 40	var
CbcObject, 337	PseudoReducedCost, 503
CbcSimpleIntegerDynamicPseudoCost, 372	variable
CbcSOS, 393	CbcBranchingObject, 45
updateModel	OsiLinkedBound, 480
CbcSolver, 387	variable
updateUpDynamicPseudoCost	CbcBranchingObject, 46
CbcSimpleIntegerDynamicPseudoCost, 373	CbcFixVariable, 115
	variables
upper CbcFullNodeInfo, 120	
	CbcPartialNodeInfo, 355
upper_	variables_
CbcFullNodeInfo, 121	CbcPartialNodeInfo, 356
useElapsedTime	vbRowIndex_
CbcModel, 301	CbcHeuristicDive, 166
useNumber_	verbose_
CbcHeuristicCrossover, 157	CbcGenCtlBlk, 135
used	version_
CbcHeuristicLocal, 214	CbcGenCtlBlk, 134
CbcHeuristicProximity, 225	virginCutGenerator
CbcHeuristicRINS, 231	CbcModel, 296
used_	
CbcHeuristicLocal, 215	W
CbcHeuristicProximity, 225	WEIGHT_AFTER
CbcHeuristicRINS, 232	CbcSimpleIntegerDynamicPseudoCost.hpp, 539
usedInSolution	WEIGHT_BEFORE
CbcModel, 289	CbcSimpleIntegerDynamicPseudoCost.hpp, 540
usefulInformation	WEIGHT PRODUCT
CbcModel, 310	CbcSimpleIntegerDynamicPseudoCost.hpp, 540
userFunction	waitingForMiniBranchAndBound
CbcSolver, 388	CbcModel, 300
userFunctionArray	walkback
CbcSolver, 388	CbcModel, 304
userName_	way
CbcUser, 431	CbcBranchingObject, 45
3500001, 10 1	CbcNode, 316
V	CbcStatistics, 399
V VERBOSE	
	Way_ ChePrenchingOhiost 46
CbcGenParam, 142	CbcBranchingObject, 46

	OL 11
CbcObjectUpdateData, 340	CbcHeuristicDW, 187
CbcStatistics, 400	workingBasis
weight_	CbcModel, 293
CbcCompareDefault, 68	writeAmpl Cbc ampl.h, 504
weightFactor	<u> </u>
CbcHeuristicFPump, 197	writeMps
weightFactor_	OsiCbcSolverInterface, 471
CbcHeuristicFPump, 199	writeMpsNative OsiCbcSolverInterface, 471
weights	OSIODOSOIVEIIIIteriace, 471
CbcSOS, 394	X
weights_	xColumn
CbcHeuristicDW, 187	OsiBiLinear, 446
whatDepth	xColumn
CbcCutGenerator, 84	OsiBiLinear, 450
whatDepthInSub	OsiOneLink, 485
CbcCutGenerator, 84	xMeshSize
when	OsiBiLinear, 447
CbcHeuristic, 149	xMeshSize
when_	OsiBiLinear, 449
CbcHeuristic, 153	xOtherSatisfied
whenCuts	OsiBiLinear, 447
CbcModel, 281	xOtherSatisfied
whenInfeasible	OsiBiLinear, 450
CbcCutGenerator, 85	xRow
where_	OsiBiLinear, 446
CbcGenCtlBlk::babState_struct, 27	xRow_
whereFrom	OsiBiLinear, 451
CbcHeuristic, 151	OsiOneLink, 485
whereFrom_	xSatisfied
CbcHeuristic, 153	OsiBiLinear, 447
whetherCallAtEnd	xSatisfied
CbcCutGenerator, 88	OsiBiLinear, 449
whetherInMustCallAgainMode	xyBranchValue_
CbcCutGenerator, 88	OsiBiLinear, 450
whetherToUse	xyCoefficient
CbcCutGenerator, 88	OsiBiLinear, 449
which_	xyRow
CbcBranchAllDifferent, 29	OsiBiLinear, 446
whichColumnBlock	OsiOneLink, 485
CbcHeuristicDW, 184	xyRow_
whichColumnBlock_	OsiBiLinear, 451
CbcHeuristicDW, 187	xySatisfied
whichCutGenerator	OsiBiLinear, 448
CbcCountRowCut, 76	xySatisfied_
whichGenerator	OsiBiLinear, 450
CbcModel, 274	22 227, 22
whichMethod	Υ
CbcBranchDecision, 34	yColumn
CbcBranchDynamicDecision, 40	OsiBiLinear, 446
whichNonLinear_	yColumn_
OsiSolverLink, 499	OsiBiLinear, 450
whichRowBlock	yMeshSize
CbcHeuristicDW, 184	OsiBiLinear, 448
whichRowBlock_	yMeshSize_

OsiBiLinear, 449 yOtherSatisfied OsiBiLinear, 447 yOtherSatisfied_ OsiBiLinear, 450 yRow OsiBiLinear, 446 yRow_ OsiBiLinear, 451 ySatisfied OsiBiLinear, 447 ySatisfied_ OsiBiLinear, 450 Ζ zapIntegerInformation CbcModel, 307