

ERTPS INSTALLATION MANUAL

DOCUMENT INFORMATION			
Name	eProsima – RTPS Installation Manual		
Product	Documentation		
Author	Gonzalo Rodríguez Canosa		
Distribution	R 0.5.1		
Version	1		
Date	25-Jul-2014		
Status	Release		
Contact	gonzalorodriguez@eprosima.com		
Document Code			

eProsima

Proyectos y Sistemas de Mantenimiento SL

Ronda del poniente 2 – 1ºG 28760 Tres Cantos Madrid

Tel: + 34 91 804 34 48

<u>info@eProsima.com</u> – <u>www.eProsima.com</u>

Trademarks

eProsima is a trademark of *Proyectos y Sistemas de Mantenimiento SL*. All other trademarks used in this document are the property of their respective owners.

License

eProsima RTPS is licensed under the terms described in the EPROSIMARTPS_LIBRARY_LICENSE.txt file included in this distribution.

Technical Support

Phone: +34 91 804 34 48

• email: support@eProsima.com

Revision history

Date	Author	Description	
16-May-2014	Gonzalo Rodriguez (gonzalorodriguez@eprosima.com)	Version 1.1: First version.	
10-Jun-2014	Gonzalo Rodríguez	Changed for release 0.4	
27-Jul-2014	Gonzalo Rodríguez	Changed for release 0.5.0	

Contents

1	. Basic Requirements	1
	1.1. Boost 1.53	
	1.2. Windows 7 32-bit and 64-bit	
	1.2.1. Visual C++ 2010 Redistributable package installation	1
	1.3. Ubuntu 12.04 64-bit	1
2	. Installation	2
	2.1. Windows 7 32-bit and 64-bit	2
	2.2. Ubuntu 12.04 64-bit	. 2

1 Basic Requirements

1.1 Boost 1.53

eProsima RTPS requires the Boost distribution, so the user should install version **1.53** (newer versions should also work).

Follow the instructions included with the boost distribution for installation.

The user could choose to install just the used libraries: boost-thread, boost-asio and boost-system.

1.2 Windows 7 32-bit and 64-bit

1.2.1 Visual C++ 2010 Redistributable package installation.

eProsima RTPS requires Visual C++ Redistributable package. The user is responsible for its installation if its not already present.

1.3 Ubuntu 12.04 64-bit

No special requirements are needed for linux systems except the normal development tools and compilers.

1.4 QT GUI development tools

The QT graphic library is needed only to build and execute the Shapes Demo included in this version.

2 Installation

This section describes how to install eProsima RTPS in several operating systems. Follow the steps described under your preferred operating system.

2.1 Windows 7 32-bit and 64-bit

Download the installation package:

Execute the installer and follow the instructions. You should make sure that at least one component (i86 or x64 libraries) is selected in the Choose Components step. The corresponding environment variables should be selected in the next page ("Environment variables setting page").

Ubuntu 12.04 64-bit

Download the installation package:

Extract the contents in your installation destination.

Copy the contents of the include directory to /usr/local/include:

Copy the library files to /usr/local/lib: