Interfaces between crates

Items each consumer imports from each provider

user v provider →	a2a-worker provides	a2a-client provides	a2a-core provides	a2a-security provides	a2a-audit provides	bus-api provides	bus-nats provides
a2ad uses →	- Worker, WorkerBuilder, FileStore - backend traits, DelegationConfig - Publication, CardSigning, WorkspaceBinding	- allowed, not used	- Allowance, Metering - Clock, SystemClock	- Kid, Signer, storage	- Pipeline, PipelineConfig, Publisher - Redactor, EmitterIdentity, Metrics	- Bus, BusError, Headers	- NatsBus, connect, provision - layout, permissions
a2a-cli uses →	- allowed, not used	- Client, Config, SendReply - ApprovalError, ClientError, SigningHook	- SystemClock - WireError, LocalError	- Signer, storage keys - TrustStore	- verify_paths, CheckpointVerifier	- Bus, BusError	- NatsConfig, Seed
a2a-tui uses →	- allowed, not used	- Event, PendingApproval - signing envelope_hook	- ALLOW_ONCE_ID, REJECT_ONCE_ID - SystemClock	- Signer, TrustStore - storage	- allowed, not used	- Bus, Consumer, StartPosition	- NatsConfig, Seed, layout
gateway-http uses →	- allowed, not used	- Client, Directory, EventStream - CallOptions, Outbound, SendReply	- Allowance, Clock - WireError, BUS_DOMAIN, LocalError	- allowed, not used	- allowed, not used	- Bus, BusError	- allowed, not used
driver-acp uses →	- backend traits - check_turn_stream	- allowed, not used	- DEFAULT_EXPIRY_MS	- allowed, not used	- allowed, not used	- allowed, not used	- allowed, not used
driver-a2a-http uses →	- backend traits	- allowed, not used	- allowed, not used	- allowed, not used	- allowed, not used	- allowed, not used	- allowed, not used
a2a-worker uses →	-	- Client, CallOptions, Directory - Outbound, SendReply, budget	- approval: ALLOW_ONCE_ID, Tier, MAX_OPEN_PER_TASK - budget, task::TaskStore, envelope	- card sign and verify, frame - redact, Signer, TrustStore	- EventBuilder, Pipeline, AuditError	- Bus, RequestStream	- allowed, not used
a2a-client uses →	- allowed, not used	-	- envelope, errors, headers, subject - approval, DelegationRefused	- Ed25519Signer, Signer - verify_card, sign_envelope, TrustStore	- allowed, not used	- Bus, Consumer, Watch - Headers, Reply	- allowed, not used
a2a-core uses →	never: upward edge	x would point upwards	-	- allowed, not used	- allowed, not used	- Headers, Reply, ReplyHandle - InvalidName, Principal, Subject	- allowed, not used

Rule

- Each cell lists the items the row imports from the column (read from use lines).
- Red-outlined cells mark a dependency the layer rule forbids; none is present.

Scope

- Rows are the consumers this page covers; a2a-mcp and a2a-workspace are not drawn.