Customize swapping

How-to: Set slippage tolerance or stop limit on swaps

Copy page

Set a slippage or stop limit to protect against rate changes

Set a slippage tolerance or stop limit to avoid receiving less than expected on a swap due to market fluctuations:

- A **slippage tolerance** lets you set the maximum percentage difference you're willing to accept between the estimated and actual swap amount, expressed in bps (for example, 100 bps = 1%).
- A **stop limit** lets you set the exact minimum amount you want to receive.

If both are configured, the stop limit takes precedence.

Prerequisites

Before you begin, ensure that you've:

- **Installed App Kit**
- **Configured an adapter**

These are required so any example below runs with a valid `kit` and `adapter`.

Set slippage tolerance

This example sets a slippage tolerance of 100 bps (1%):

TypeScript

```
const output = await kit.swap({
  from: { adapter, chain: "Arc_Testnet" },
  tokenIn: "USDC",
  amountIn: "1.00",
  tokenOut: "EURC",
  config: {
    // Set the slippage tolerance to 100 bps
    slippageBps: 100,
  },
});
```

With `slippageBps` as `100` as in the example, you'll receive at least 99% of the estimated amount. Meaning if the swap rate is 1 USDC to 1 EURC, you'll receive at least 0.99 EURC.

> The `slippageBps` default is 300 bps. `0` represents no tolerance, which increases transaction failure rates.

Set stop limit

`stopLimit` defines the minimum amount of the token type specified in `tokenOut` that you'll receive on a swap.

This example sets a stop limit of 0.95 EURC, meaning you won't receive any less than that on a swap:

TypeScript

```
const output = await kit.swap({
  from: { adapter, chain: "Arc_Testnet" },
  tokenIn: "USDC",
  amountIn: "1.00",
  tokenOut: "EURC",
  config: {
    // Set stop limit to 0.95 EURC
    stopLimit: "0.95",
  },
});
```

Was this page helpful? Yes No

Estimate swap rate

How swap fees work

Links

Network status

Blog

Community

Arc homepage

Resources

Terms of service

Privacy policy

Cookie policy

Powered by mintlify

By using the Arc Network Testnet, you agree to the Terms of Service and Privacy Policy.