

Table Of Contents

- Building the Client Library
- Running the Client Examples
- Configuring Logging

Building the Client Library

To build the C++ Client library, please follow the instructions in GRIDGAIN_HOME/examples/clients/cpp/readme.md file.

Running the Client Examples

After you have built the C++ client library and installed it in your system, you can build the examples by going into the GRIDGAIN_HOME/examples/clients/cpp directory and executing the following commands:

./configure make

On Windows you can use the provided Visual Studio solution (in the vsproject/ directory) to compile the examples code. Please note that you will have to adjust include and library directories in relevant projects to match your environment configuration.

Before you can run the examples, you must ensure that the org.gridgain.examples.client package are available on the GridGain node's classpath. One way to achieve that is to build the jar containing the examples code and drop it to the <code>GRIDGAIN_HOME/libs</code> directory. You can build <code>gridgain-examples.jar</code> by running <code>mvn</code> <code>package</code> in <code>GRIDGAIN_HOME/examples</code> folder. After that <code>@code gridgain-examples.jar</code> will be generated by Maven in <code>GRIDGAIN_HOME/examples/target</code> folder. When the <code>ggstart</code> script runs it automatically picks up the jars from that directory.

Before starting nodes you also need to enable <code>gridgain-rest-tcp</code> module. Simply move <code>libs/optional/gridgain-rest-tcp</code> folder to <code>libs</code> folder so that the module is added to classpath.

Now you can start a GridGain node as follows:

\$GRIDGAIN_HOME/bin/ggstart.{sh,bat} examples/config/example-cache.xml

Alternatively you can run an instance of ClientExampleNodeStartup or ClientCacheExampleNodeStartup Java class, which will start up a GridGain node with proper configuration. You can do this from your favourite IDE.

Once the GridGain node is up and running you can run the examples:

```
./gridgain-compute-example
./gridgain-data-example
```

If you just compiled the client library make sure that you ran <code>ldconfig</code> to update library cache before running the example.

You can also start multiple nodes.

Feel free to modify the example source code to change communication protocol from TCP (default) to HTTP, use multiple hosts and try other options.

Configuring Logging

You can control the client's log level by setting the GRIDGAIN_CPP_CLIENT_LOG_LEVEL environment variable to one of the following values:

- 1. (error),
- 2. (warning),
- 3. (info), and
- 4. (debug).

By default, the log level is 3. The client sends all its log messages to stdout.