

ENG 101 Module #4 MATLAB Input/Output

Dr. Emil Jovanov Electrical and Computer Engineering University of Alabama in Huntsville emil.jovanov@uah.edu http://www.ece.uah.edu/~jovanov

User Input/Output



- ▶ Asking user for input
 - Processing based on user input
 - ▶ Interactive change of parameters
- ▶ Formatting output
 - Describe the result
 - ▶ Prepare for reports and documentation

Ĭ.



Prompting for Numerical Input

- variable_name = input('message prompt ')
- ▶ Example (go to MATLAB editor):
- byear = input('Enter your year of birth ')
- cyear = input('Enter the current year ')
- Your Age = cyear-byear

Prompting for String Input



- name = input('message prompt', 's')
- ▶ Example (go to MATLAB):
- name = input('Enter your name:','s')

...



Prompting for Publishing

- ▶ Regular Input statement generates error during publishing
- Use Input Dialog (inputdlg)

```
var = inputdlg('message prompt ')
```

- ▶ Pay attention to format!!!
 - ▶ Cell > String > Numeric input
- speed=str2num(cell2mat(inputdlg('Enter speed in [mph]: ')));



Displaying Output

- I. We can simply type the variable and hit enter.
- 2. We can use the disp command:

```
disp(variable_name) or
disp('string') or
disp(' ')
```

3. We can use the fprintf command:

```
fprintf('string') or
fprintf('some text %f more text', var)
```



Using disp

num=10; str='Pick a number';

disp(num)
disp(str)

disp(' ')

disp(4+num)

disp('the end')

- ▶ Notes on disp:
- Automatically starts a new line
- Cannot combine multiple elements

_

Using fprintf

▶ %xy.zC

- x can be a minus sign (left-justifies the number within the field), plus sign (prints a sign character in front of the number), or a zero (adds zeros to fill the field)
- y is the field width
- .z is the precision (number of digits to be displayed to the right of the decimal)
- C is the conversion character which determine the number format (f=fixed point notation, e/E is exponential notation, g/G is the shorter of e/E or f notations, s is for string data)
- %s print a string
- ▶ %g print a compact number
- %e print a scientific number
- %f print a floating point number
- \n print a new line (go to the next line to continue printing)
- ▶ \t print a tab
- ▶ \\ print a slash
- > %% print a percent sign

K

THE UNIVERSITY OF ALABAMA IN HUNTSVILL

fprintf

- ▶ Means file print formatted
 - formatted text is text that can be read by people
 - unformatted text looks random to people but computers can read it
- ▶ Can write to screen or to a file
- ▶ Can mix numbers and text in output
- ▶ Have full control of output display
- ▶ Complicated to use

9

THE UNIVERSITY OF ALABAMA IN HUNTSVILLE

Using fprintf

```
%Basketball stats
```

p_name='Sam';
games=100;

ppg=14.1738;

reb=10.9;

assists=4.359;

Fprintf('Over %g games, %s scored an average of %f points per game.', games, p_name, ppg)



To make the next thing that MATLAB writes (after a use of fprintf) appear on the start of a new line, put the two characters "\n" at the end of the fprintf text

```
>> fprintf( 'My text\n' )
My text
>>
```



Can also use \n in middle of text to make MATLAB display remainder of text on next line

```
>> fprintf('1st line\n2nd line\n3rd ...\n')
1st line
2nd line
3rd ...
>>
```



\n is an escape character, a special combination of two characters that makes fprintf do something instead of print the two characters

 \n – makes following text come out at start of next line

\t − horizontal tab

There are a few more

fprintf(format, nl, n2, n3)

Conversion specifier

>> fprintf('Joe weighs %6.2f kilos', nl)

Format string



```
>> fprintf( 'Joe weighs %6.2f kilos', n1 )
```

Format string

- May contain text and/or conversion specifiers
- Must be enclosed in SINGLE quotes, not double quotes, aka quotation marks (" ")

15

```
THE UNIVERSITY OF
```

```
>> fprintf( 'Joe is %d weighs %f kilos', age, weight )
```

Arguments

- Number of arguments and conversion specifiers must be the same
- Leftmost conversion specifier formats leftmost argument, 2nd to left specifier formats 2nd to left argument, etc.



Conversion specifier

>> fprintf('Joe weighs %f kilos', n1)

Common conversion specifiers

- %f fixed point (decimal always between 1's and 0.1's place,
 e.g., 3.14, 56.8
- > %e scientific notation, e.g, 2.99e+008
- %d integers (no decimal point shown)
- %s string of characters

17



Conversion specifier -

>> fprintf('Joe weighs %6.2f kilos', n1)

To control display in fixed or scientific, use %w.pf or %w.pe

- w = width: the minimum number of characters to be displayed
- ▶ p = "precision": the number of digits to the right of the decimal point



If you omit "w", MATLAB will display correct precision and just the right length

g



```
>> e = exp( 1 );
>> fprintf( 'e is about %4.1f\n', e )
e is about 2.7
>> fprintf( 'e is about %10.8f\n', e )
e is about 2.71828183
>> fprintf( 'e is about %10.8e', e )
e is about 2.71828183e+000
>> fprintf( 'e is about %10.2e', e )
e is about 2.72e+000
>> fprintf( 'e is about %f\n', e )
e is about 2.718282
```



Use escape characters to display characters used in conversion specifiers

- ▶ To display a percent sign, use %% in the text
- To display a single quote, use '' in the text (two sequential single quotes)
- To display a backslash, use \\ in the text (two sequential backslashes)



Make the following strings

- ▶ Mom's apple 3.14
- Mom's apple 3.1415926
- Mom's apple 3.1e+000

```
>> fprintf( 'Mom''s apple %.2f\n', pi )
Mom's apple 3.14
>> fprintf( 'Mom''s apple %.7f\n', pi )
Mom's apple 3.1415927
>> fprintf( 'Mom''s apple %.1e\n', pi )
Mom's apple 3.1e+000
```

THE UNIVERSITY OF ALABAMA IN HUNTSVILLE

Format strings are often long. Can break a string by

- Put an open square bracket ([) in front of first single quote
- 2. Put a second single quote where you want to stop the line
- 3. Follow that quote with an ellipsis (three periods)
- 4. Press ENTER, which moves cursor to next line
- 5. Type in remaining text in single quotes
- 6. Put a close square bracket (1)
- 7. Put in the rest of the fprintf command



Example

```
>> weight = 178.3;
>> age = 17;
>> fprintf( ['Tim weighs %.1f lbs'...
' and is %d years old'], weight, age )
Tim weighs 178.3 lbs and is 17 years old
```

>



fprintf is vectorized, i.e., when vector or matrix in arguments, command repeats until all elements displayed

Uses matrix data column by column



When this script file is executed the display in the Command Window is:

```
1.0000
                        3,0000
                                  4.0000
              2.0000
                                             5.0000
                                                      The 2 \times 5 matrix T.
    1.0000
              1.4142
                        1.7321
                                  2.0000
                                             2.2361
                                                      The fprintf
If the number is: 1, its square root is: 1.000000
                                                      command repeats 5
If the number is: 2, its square root is: 1.414214
                                                      times, using the
If the number is: 3, its square root is: 1.732051
                                                      numbers from the
If the number is: 4, its square root is: 2.000000
                                                      matrix T column
                                                      after column.
If the number is: 5, its square root is: 2.236068
```

Using the fprintf command to save output to a file



Takes three steps to write to a file

Step I:- open file

fid=fopen('file_name','permission')

fid - file identifier, lets fprintf know what file
to write its output in

permission — tells how file will be used, e.g., for reading, writing, both, etc.



Some common permissions

- r open file for reading
- ▶ w open file for writing. If file exists, content deleted. If file doesn't exist, new file created
- ▶ a same as w except if file exists the written data is appended to the end of the file
- If no permission code specified, fopen uses r

See Help on fopen for all permission codes

27

Step 2:



Write to file with fprintf. Use it exactly as before but insert fid before the format string, i.e.,

fprintf(fid,'format string',variables)

The passed fid is how fprintf knows to write to the file instead of display on the screen



Step 3:

When you're done writing to the file, close it with the command fclose(fid)

Once you close it, you can't use that fid anymore until you get a new one by calling fopen

Make sure to close every file you open. Too many open files makes problems for MATLAB



29

Miscellaneous



- If the file name you give to fopen has no path, MATLAB writes it to the current directory, also called **the working directory**
- You can have multiple files open simultaneously and use fprintf to write to all of them just by passing it different fids
- You can read the files you make with fprintf in any text editor, e.g., MATLAB's Editor window or Notepad



Use save command to save workspace or data

Use load command to retrieve stored workspace or data

Can use both to exchange data with non-MATLAB programs

31



Use save command to save some or all workspace variables to hard drive

Two forms

```
save file_name
save('file_name')
```

Either one saves all workspace variables, including their name, type, size, value



To only save specific variables, list variables after file name. For example, to save two variables named var1 and var2

```
save file_name var1 var2
save('file_name','var1','var2')
```

33



All forms store variables in file called "file_name.mat"

- ▶ Called "mat" file
- ▶ Unformatted (binary) file
 - Only MATLAB can read mat file, not other programs
 - Can't read file in text editor, or MATLAB Editor Window



To save as formatted text (also called ASCII text)

save file_name -ascii

IMPORTANT – only saves <u>values</u> of variables, no other info, even their names!

- ▶ Can also just save certain variables, as before
- ▶ Usually just use to save value of one variable

35



To load data in a mat file into workspace

load file_name
load('file_name')

To load only specific variables from mat file, e.g., var I and var 2

load file_name var1 var2
load('file_name','var1','var2')

If variable already exists in workspace, it is overwritten (its value is replaced by value in file)



To load data in a text file into workspace

load file_name

variable = load('file_name')

- ▶ In first form, creates variable called file_name and stores all file data in it
- If all rows in file don't have same number of columns, MATLAB displays an error
- ▶ Even if data created from multiple variables all with same number of columns, load still reads all data into one variable
 - Not very useful in this case





- MATLAB often used to analyze data collected by other programs
- Sometimes need to transfer MATLAB data to other programs
- In this section will only discuss numerical data
 - MATLAB has commands to load and save data from a number of other programs
 - Can also tell MATLAB what format data is in