

CSARCH Lecture Series: Binary Data Organization

Sensei RL Uy
College of Computer Studies
De La Salle University
Manila, Philippines





Copyright Notice

This lecture contains copyrighted materials and is use solely for instructional purposes only, and not for redistribution.

Do not edit, alter, transform, republish or distribute the contents without obtaining express written permission from the author.

Overview

Reflect on the following questions:

- What is bit, byte, nibble or word?
- What does least significant and most significant mean?
- What does endianness mean?

Overview

- This sub-module discusses the various binary data organization
- The objectives are as follows:
 - ✓ Explain the different levels of binary data organization
 - ✓ Explain the difference between little endian and big endian

• Binary digits (also known as bits) can be group to form various organizations:

Organization	Number of bits	Usage
Bit (binary digit)	2 cells – 0 or 1	Basic unit
Crumb	2 bits	*largely defunct term. rarely used
Nibble	4 bits	Hex digit, BCD digit
Byte	8 bits	Smallest addressable data unit
Half word	16 bits	Definition of word is architecture-dependent
Word	32 bits	A 32-bit architecture considers 1 word as 32-bit
Double word	64 bits	
Quad word	128 bits	

- Given a byte, bit 7 is the most significant bit (MSb) while bit 0 is the least significant bit (LSb)
- Bit is abbreviated as lowercase b while byte is abbreviated as capital B
- Computer architecture convention states that numbering starts at 0 (not 1)

7	6	5	4	3	2	1	0
MSb*							LSb*

- Example: 10010110₂
- 0 is the least significant bit (LSb) (i.e.,bit 0) while 1 is the most significant bit (MSb) (i.e., bit 7)

- Least significant and most significant can be extended to nibble, byte, word or any binary data organization
- Example: 10010110₂ or 96₁₆
- 0110_2 or 6_{16} is the least significant nibble while 1001_2 or 9_{16} is the most significant nibble
- Example: 123ACAFE₁₆
- FE_{16} is the least significant byte (LSB) while 12_{16} is the most significant byte (MSB)



- Given 12AB3456CAFE5678₁₆
 - What is the least significant bit?
 - What is the most significant bit?
 - What is the least significant byte?
 - What is the most significant byte?
 - What is the least significant word?
 - What is the most significant word?

Try

→ Pause your video first before answering

- Given 12AB3456CAFE5678₁₆
 - What is the least significant bit?
 - What is the most significant bit?
 - What is the least significant byte? 78
 - What is the most significant byte? 12
 - What is the least significant word? CAFE5678
 - What is the most significant word? 12AB3456

Byte Ordering System - Endianness

- Endianness refers to the convention used to interpret the byte ordering of multibyte stored in the computer memory.
- Two types: Big endian and Little endian
- Coined by Danny Cohen based on his paper "On Holy Wars and a Plea for Peace" (published in IEEE Computer, October 1981 issue).
- Based on Jonathan Swift's novel "Gulliver's Travel".
- Tension between Lilliput and Blefuscu on which side to crack the soft boiled egg small end or big end?

Little Endian Byte Ordering System

- Multi-byte stores the least-significant byte at the lowest memory byte address, followed by the other bytes in ascending order of their significance
- The address of the multi-byte is the address of the least-significant byte.

Address	Data (hex)
0003	55
0002	44
0001	33
0000	22

- Example: address 0000 contains 16-bit data 3322
- Example: address 0000 contains 32-bit data 55443322

Big Endian Byte Ordering System

- Multi-byte stores the most-significant byte at the lowest memory byte address, followed by the other bytes in ascending order of their significance
- The address of the multi-byte is the address of the most-significant byte.

Address	Data (hex)
0003	55
0002	44
0001	33
0000	22

- Example: address 0000 contains 16-bit data 2233
- Example: address 0000 contains 32-bit data 22334455

To recall...

- What we have learned:
 - ✓ Explain the different levels of binary data organization
 - ✓ Explain the difference between little endian and big endian