

Ready to install!

Note for mac users: If you are using a Mac computer, note that all of these steps will be completely different so you should [follow our guide on installing on a mac computer](#).

Hopefully you are now armed with a Linux DVD or USB stick that's good to go. If the DVD was ejected from the CD player, pop it back in the drive and Restart your computer. Most PCs will automatically try to start the computer from the CD drive or USB, so hopefully you will be presented with a Ubuntu welcome screen after a minute or so.

Step 1: Getting your PC to start from USB/CD.

If you don't see an option to start from USB/CD, or if your PC started up in Windows instead then make sure your PC is set to boot from CD (or USB) before the hard disk. You can change this setting in something called the BIOS or Boot Order setup. Here's how to do that:

- Often when you start a PC you will see the logo of the manufacturer flash up briefly before it starts up Windows. You may see a message like 'Press F12 for Boot Options'. If you don't see any message like that, try pressing ESC or F2 whilst the logo screen is up. This may reveal which key you need to press. You may have to stop and restart your computer a number of times to do this as the logo disappears pretty quickly!
- If you managed to get to the Boot Options, you will be presented with an option to boot from CD or USB/External media. Select the option you need with the up/down keys and hit return. That should be all you need. The below screenshot is the typical look of this menu

If you don't see anything like 'Boot Options' but you see something like 'Press F2 For Setup' then hit that key and enter the BIOS setup utility. In there, have a look around the menus using the arrow keys. You should be able to change the boot order to something like CD/DVD or External USB Media first (as opposed to hard drive first). Save the settings from there and then restart once again.

The below images shows a typical 'BIOS' Setup screen. It shows the process involved in making sure USB (or CD) is the primary boot option, hard drive secondary.

- Go to the Boot tab in the BIOS setup
- Select to Change the boot priorities
- Note the boot priority is for a Toshiba hard drive to boot first
- Re-order it so that boot option 1 is the USB/UEFI media (in this case it's a Kingston USB stick)
- Boot option 2 is now set as the hard drive (Toshiba), Option 1 is the USB stick
- Make sure you save the changes and exit