
TELNET:



```
Router>enable
Router#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #interface termial FAO/0
% Invalid input detected at '^' marker.
Router(config)#interface termial fa0/0
% Invalid input detected at '^' marker.
Router(config)#interface fa0/0
Router(config-if) #ip address 10.0.0.1 255.0.0.0
Router(config-if) #no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if) #exit
Router(config) #hostname rl
rl(config) #enable secret pl
rl(config)#interface fastethernet 0/0
rl(config-if)#ip address 10.0.0.1 255.0.0.0
rl(config-if)#no shutdown
rl(config-if)#
rl(config-if)#line vty 0 5
rl(config-line)#login
% Login disabled on line 132, until 'password' is set
% Login disabled on line 133, until 'password' is set
% Login disabled on line 134, until 'password' is set
% Login disabled on line 135, until 'password' is set
% Login disabled on line 136, until 'password' is set
% Login disabled on line 137, until 'password' is set
rl(config-line)#password p0
rl(config-line)#
rl(config-line)#exit
rl(config)#exit
rl#
%SYS-5-CONFIG I: Configured from console by console
rl#wr
Building configuration...
[OK]
rl#
```

Command Prompt

```
Packet Tracer PC Command Line 1.0 PC>ping 10.0.0.1
Pinging 10.0.0.1 with 32 bytes of data:
Reply from 10.0.0.1: bytes=32 time=0ms TTL=255
Ping statistics for 10.0.0.1:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 0ms, Average = 0ms
PC>telnet 10.0.0.1
Trying 10.0.0.1 ...Open
User Access Verification
Password:
Password:
Password:
[Connection to 10.0.0.1 closed by foreign host] PC>telnet 10.0.0.1
Trying 10.0.0.1 ...Open
User Access Verification
rl>enable
Password:
Password:
rl#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
          D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, o - ODR
           P - periodic downloaded static route
Gateway of last resort is not set
        10.0.0.0/8 is directly connected, FastEthernet0/0
rl#
```