

Презентация по лабораторной работе №2.

Предварительная настройка оборудования Cisco.

Поляков Г. С.

22 февраля 2025

Российский университет дружбы народов, Москва, Россия

Информация

- Поляков Глеб Сергеевич
- студент
- Российский университет дружбы народов

Порядок выполнения работы



Настройка PC0 и PC1

PC0

Physical **Config** Desktop Programming Attributes

GLOBAL

Settings

Algorithm Settings

INTERFACE

FastEthernet0

Bluetooth

FastEthernet0

Port Status ☒ On

Bandwidth ☐ 100 Mbps ☐ 10 Mbps ☒ Auto

Duplex ☐ Half Duplex ☐ Full Duplex ☒ Auto

MAC Address 00E0.F7D5.78C0

IP Configuration

☐ DHCP

☒ Static

IPv4 Address 192.168.1.10

Subnet Mask 255.255.255.0

IPv6 Configuration

☐ Automatic

☒ Static

IPv6 Address /

Link Local Address: FE80::2E0:F7FF:FED5:78C0

☐ Top

Настройка маршрутизатора

```
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname
Router(config)#hostname ms
Router(config)#hostname msk-gspolyakov-gw-1
msk-gspolyakov-gw-1(config)#inte
msk-gspolyakov-gw-1(config)#interface f0
msk-gspolyakov-gw-1(config)#interface f0/0
msk-gspolyakov-gw-1(config-if)#no shutdown

msk-gspolyakov-gw-1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
ip
% Incomplete command.
msk-gspolyakov-gw-1(config-if)#ip add
msk-gspolyakov-gw-1(config-if)#ip address 192.168.1.254 255.255.255.0
msk-gspolyakov-gw-1(config-if)#exit
msk-gspolyakov-gw-1(config)#line vty 0 4
msk-gspolyakov-gw-1(config-line)#password cisco
msk-gspolyakov-gw-1(config-line)#login
msk-gspolyakov-gw-1(config-line)#exit
msk-gspolyakov-gw-1(config)#line console 0
msk-gspolyakov-gw-1(config-line)#password cisco
msk-gspolyakov-gw-1(config-line)#login
msk-gspolyakov-gw-1(config-line)#exit
msk-gspolyakov-gw-1(config)#enab
msk-gspolyakov-gw-1(config)#enable secr
msk-gspolyakov-gw-1(config)#enable secret cis
msk-gspolyakov-gw-1(config)#enable secret cisc
msk-gspolyakov-gw-1(config)#enable secret cisco
msk-gspolyakov-gw-1(config)#ser
msk-gspolyakov-gw-1(config)#service pass
msk-gspolyakov-gw-1(config)#service password-encryption
msk-gspolyakov-gw-1(config)#user
msk-gspolyakov-gw-1(config)#username ad
msk-gspolyakov-gw-1(config)#username admin pr
msk-gspolyakov-gw-1(config)#username admin privilege 1 secret cisco
msk-gspolyakov-gw-1(config)#ip domain donskaya.rudn.edu
```

Настройка коммутатора

```
Switch#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#inter
Switch(config)#hostname msk-gspolyakov-sw-1
msk-gspolyakov-sw-1(config)#interface v1
msk-gspolyakov-sw-1(config)#interface vlan2
msk-gspolyakov-sw-1(config-if)#no shu
msk-gspolyakov-sw-1(config-if)#no shutdown
msk-gspolyakov-sw-1(config-if)#ip ad
msk-gspolyakov-sw-1(config-if)#ip address 192.168.2.1 255.255.255.0
msk-gspolyakov-sw-1(config-if)#exit
msk-gspolyakov-sw-1(config)#int
msk-gspolyakov-sw-1(config)#interface f0/1
msk-gspolyakov-sw-1(config-if)#swi
msk-gspolyakov-sw-1(config-if)#switchport mo
msk-gspolyakov-sw-1(config-if)#switchport mode acc
msk-gspolyakov-sw-1(config-if)#switchport mode access
msk-gspolyakov-sw-1(config-if)#swi
msk-gspolyakov-sw-1(config-if)#switchport ac
msk-gspolyakov-sw-1(config-if)#switchport access v1
msk-gspolyakov-sw-1(config-if)#switchport access vlan2
^
% Invalid input detected at '^' marker.

msk-gspolyakov-sw-1(config-if)#switchport access vlan 2
% Access VLAN does not exist. Creating vlan 2
msk-gspolyakov-sw-1(config-if)#
%LINK-5-CHANGED: Interface Vlan2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan2, changed state to up

msk-gspolyakov-sw-1(config-if)#exit
msk-gspolyakov-sw-1(config)#ip def
msk-gspolyakov-sw-1(config)#ip default-gateway 192.168.2.254
msk-gspolyakov-sw-1(config)#line vty 0 4
msk-gspolyakov-sw-1(config-line)#password cisco
msk-gspolyakov-sw-1(config-line)#login
msk-gspolyakov-sw-1(config-line)#exit
msk-gspolyakov-sw-1(config)#line con
msk-gspolyakov-sw-1(config)#line console 0
msk-gspolyakov-sw-1(config-line)#password cisco
msk-gspolyakov-sw-1(config-line)#login
msk-gspolyakov-sw-1(config-line)#exit
msk-gspolyakov-sw-1(config)#enab
msk-gspolyakov-sw-1(config)#enable se
msk-gspolyakov-sw-1(config)#enable secret cisco
msk-gspolyakov-sw-1(config)#ser
msk-gspolyakov-sw-1(config)#service pass
msk-gspolyakov-sw-1(config)#service password-encryption
msk-gspolyakov-sw-1(config)#username I
```

Проверка соединения через ping

```
msk-gspolyakov-gw-1#ping 192.168.1.10
```

```
Type escape sequence to abort.
```

```
Sending 5, 100-byte ICMP Echos to 192.168.1.10, timeout is 2 seconds:
```

```
.!!!!
```

```
Success rate is 80 percent (4/5), round-trip min/avg/max = 0/0/0 ms
```

```
msk-gspolyakov-gw-1#
```

```
msk-gspolyakov-sw-1#ping 192.168.2.10
```

```
Type escape sequence to abort.
```

```
Sending 5, 100-byte ICMP Echos to 192.168.2.10, timeout is 2 seconds:
```

```
.!!!!
```

```
Success rate is 80 percent (4/5), round-trip min/avg/max = 0/0/0 ms
```

```
msk-gspolyakov-sw-1#
```

Проверка соединения через ssh

Physical Config **Desktop** Programming Attributes

Telnet / SSH Client

Session Options

Connection Type

SSH

Host Name or (IP address)

192.168.2.1

Username

Connect

SSH Client

Password:

msk-gspolyakov-sw-1>

Спасибо за внимание!