

Лабораторная работа №10

Настройка списков управления доступом (ACL)

Поляков Г. С.

07 апреля 2025


Российский университет дружбы народов, Москва, Россия

Информация


- Поляков Глеб Сергеевич
- студент
- Российский университет дружбы народов

Выполнение работы

Схема сети



Добавление лептопа



Настройка IP-адреса

The screenshot shows a web-based configuration interface for a device named 'admin'. The interface has a sidebar on the left with a tree view containing 'GLOBAL' (with a sub-item 'Settings') and 'INTERFACE' (with sub-items 'FastEthernet0' and 'Bluetooth'). The main content area is titled 'Global Settings' and contains the following fields:

- Display Name:** admin
- Interfaces:** FastEthernet0 (with a refresh icon)
- Gateway/DNS IPv4:**
 - ☐ DHCP
 - ☒ Static
 - Default Gateway:** 10.128.6.1
 - DNS Server:** 10.128.0.5
- Gateway/DNS IPv6:**
 - ☐ Automatic
 - ☒ Static
 - Default Gateway:** [empty field]
 - DNS Server:** [empty field]

At the bottom left of the window, there is a 'Top' button.


```
msk-donskaya-gspolyakov-gw-1>enable
Password:
msk-donskaya-gspolyakov-gw-1#configu
msk-donskaya-gspolyakov-gw-1#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
msk-donskaya-gspolyakov-gw-1(config)#ip acc
msk-donskaya-gspolyakov-gw-1(config)#ip access-list ex
msk-donskaya-gspolyakov-gw-1(config)#ip access-list extended ser
msk-donskaya-gspolyakov-gw-1(config)#ip access-list extended servers-out
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#remark web
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#perm
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit t
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp a
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp any h
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp any host 10.128.0.2 eq 80
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#
```



```
msk-donskaya-gspolyakov-gw-1(config)#int f0/0.3
msk-donskaya-gspolyakov-gw-1(config-subif)#ip acc
msk-donskaya-gspolyakov-gw-1(config-subif)#ip access-group ser
msk-donskaya-gspolyakov-gw-1(config-subif)#ip access-group servers-out ou
msk-donskaya-gspolyakov-gw-1(config-subif)#ip access-group servers-out out
msk-donskaya-gspolyakov-gw-1(config-subif)#
```

```
msk-donskaya-gspolyakov-gw-1(config)#ip access-list extended servers-out
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#per
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit t
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp h
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp host 10.128.6.200
% Incomplete command.
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp host 10.128.6.200 10.128.0.2 range 20 ftp
                                     ^
% Invalid input detected at '^' marker.

msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp host 10.128.6.200 host 10.128.0.2 range 20 ftp
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp host 10.128.6.200 host 10.128.0.2 e
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp host 10.128.6.200 host 10.128.0.2 eq tel
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp host 10.128.6.200 host 10.128.0.2 eq telnet
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#exit
msk-donskaya-gspolyakov-gw-1(config)#
```



```
msk-donskaya-gspolyakov-gw-1(config)#ip access-list extended servers-out
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#remar
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#remark file
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#per
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp 10.128.0.0 0.0.255.255
% Incomplete command.
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp 10.128.0.0 0.0.255.255 hos
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp 10.128.0.0 0.0.255.255 host 10.128.0.3 eq 455
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp host 10.128.6.200 host 10.128.0.3 range 20 ftp
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#
```

```
msk-donskaya-gspolyakov-gw-1(config)#ip access-list extended servers-out
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#remark mail
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#per
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp any host 10.128.0.4 eq smtp
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit tcp any host 10.128.0.4 eq pop3
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#exit
msk-donskaya-gspolyakov-gw-1(config)#ip access-list extended servers-out
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#remark dns
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit udp 10.128.0.0 0.0.255.255 host 10.128.0.5 eq 53
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#exit|
```

```
msk-donskaya-gspolyakov-gw-1(config)#ip access-list extended servers-out
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#1 per
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#1 permit ic
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#1 permit icmp an
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#1 permit icmp any any
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#exit
msk-donskaya-gspolyakov-gw-1(config)#exit
```

```
msh-donskaya-gspolyakov-gw-1#show access-lists
Extended IP access list servers-out
  1 permit icmp any any
 10 permit tcp any host 10.128.0.2 eq www (22 match(es))
 20 permit tcp host 10.128.6.200 host 10.128.0.2 range 20 ftp (8 match(es))
 30 permit tcp host 10.128.6.200 host 10.128.0.2 eq telnet
 40 permit tcp 10.128.0.0 0.0.255.255 host 10.128.0.3 eq 455
 50 permit tcp host 10.128.6.200 host 10.128.0.3 range 20 ftp
 60 permit tcp any host 10.128.0.4 eq smtp
 70 permit tcp any host 10.128.0.4 eq pop3
 80 permit udp 10.128.0.0 0.0.255.255 host 10.128.0.5 eq domain (3 match(es))

msh-donskaya-gspolyakov-gw-1#conf
msh-donskaya-gspolyakov-gw-1#configure
```

```
msk-donskaya-gspolyakov-gw-1(config)#ip access-list extended other-in
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#remark admin
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit ip hos
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit ip host 10.128.6.200
% Incomplete command.
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit ip host 10.128.6.200 any
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#exi
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#exit
msk-donskaya-gspolyakov-gw-1(config)#int f0/0.4
msk-donskaya-gspolyakov-gw-1(config-subif)#
%LINK-5-CHANGED: Interface FastEthernet0/0.4, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0.4, changed state to up
ip address
msk-donskaya-gspolyakov-gw-1(config-subif)#ip address-grou
msk-donskaya-gspolyakov-gw-1(config-subif)#ip address-group other-in in
^
% Invalid input detected at '^' marker.

msk-donskaya-gspolyakov-gw-1(config-subif)#ip access-group other-in in
```



```
msk-donskaya-gspolyakov-gw-1(config)#ip access-list extended management-out
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#remark admin
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#permit ip host 10.128.6.200 10.128.1.0 0.0.0.255
msk-donskaya-gspolyakov-gw-1(config-ext-nacl)#exit
msk-donskaya-gspolyakov-gw-1(config)#int f0/0.2
msk-donskaya-gspolyakov-gw-1(config-subif)#ip access
msk-donskaya-gspolyakov-gw-1(config-subif)#ip access-group mana
msk-donskaya-gspolyakov-gw-1(config-subif)#ip access-group management-out out
msk-donskaya-gspolyakov-gw-1(config-subif)#exit
msk-donskaya-gspolyakov-gw-1(config)#
```