

1.

Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.

ANS:-

1. Connect the USB webcam to an available USB port on the computer.
2. Wait for Windows to detect the webcam automatically.
3. If required, install the webcam driver provided by the manufacturer.
4. Open the **Camera** app from the Windows Start menu.
5. Check that the webcam video appears on the screen.
6. Adjust the webcam position if necessary.
7. Click the **Take Photo** button to capture a photo.
8. Open the saved photo to verify that the webcam is working correctly.

2.

Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.

ANS:-

1. Connect the printer to the computer using a USB cable, or connect it to the same network as the computer.
2. Turn on the printer and check that it has no error indicators.
3. Open **Settings** → **Devices** → **Printers & scanners**.
4. Click **Add a printer or scanner**.
5. Select the detected printer and complete the installation.
6. If Windows does not find the printer automatically, install the correct printer driver from the manufacturer's software.
7. After installation, select the printer and click **Manage**.
8. Open **Printer properties** and select **Print Test Page**.
9. Check that the test page prints successfully.

3.

Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem. Hint: Check for error icons and use the 'Scan for hardware changes' option after reconnecting.

ANS:-

1. Turn off the printer and unplug its **USB cable** from the computer.
2. Open **Device Manager** by right-clicking **Start** → **Device Manager**.
3. Expand **Printers, Print queues, or Universal Serial Bus controllers**.
4. Look for the printer or any device showing a **yellow warning/error icon**.
5. Reconnect the printer's USB cable and turn the printer back on.
6. In Device Manager, click **Action** → **Scan for hardware changes**.
7. Check whether Windows detects the printer again.
8. If an error remains, right-click the device and select **Update driver**.
9. If necessary, uninstall the problematic device and use **Scan for hardware changes** again to reinstall it.
10. Open **Settings** → **Devices** → **Printers & scanners** and confirm that the printer is now listed.
11. Print a test page to verify that the problem has been resolved.

4.

A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications. Hint: Check if another app is using the webcam or if Zoom permissions are enabled.

ANS:-

1. Open the **Camera** app and confirm that the webcam works correctly.
2. Close the Camera app completely because another application may still be using the webcam.
3. Close other applications that could access the camera, such as **Microsoft Teams, Skype, or Google Meet.**
4. Open **Windows Settings → Privacy → Camera.**
5. Make sure **Allow access to the camera on this device** is enabled.
6. Enable **Allow apps to access your camera** and allow desktop applications to access the camera.
7. Open **Zoom → Settings → Video.**
8. Select the correct webcam from the **Camera** drop-down menu.
9. Check whether the video preview appears in Zoom.
10. If it still does not work, completely close and restart Zoom.
11. If necessary, restart the computer and test the webcam in Zoom again.
12. Once the video appears in Zoom, the webcam is successfully working in both the **Camera app and Zoom.**