1 CheatSheet: Cloudfoundry Tile & OpsManager

VMWARE

Updated: January 23, 2019

- PDF Link: cheatsheet-tile-A4.pdf, Category: vmware
- ullet Blog URL: https://cheatsheet.dennyzhang.com/cheatsheet-tile-A4
- \bullet Related posts: PKS CheatSheet, Bosh CheatSheet, #denny-cheatsheets

File me Issues or star this repo.

1.1 om - Basic

| Name | Command |
|---------------------------------------|--|
| om | A command-line API client for Pivotal Operations Manager |
| omcli | export passwd='CHANGEME; alias omcli="om -t https://30.0.0.5 -u admin -p \$pas |
| Upload tile to opsmanager via cli | omcli upload-product -p |
| Upload stemcell to opsmanager via cli | omcli upload-stemcell -s |
| List all properties for a deployment | bosh deployments, omcli curl -p /api/v0/staged/products/\${bosh_deployment}/ |
| Get uaa admin password | <pre>omcli curl -p /api/v0/deployed/products/\${bosh_deployment}/credentials/.pr</pre> |
| Get bosh connect credential | omcli curl -p /api/v0/deployed/director/credentials/bosh_commandline_crede |
| List all installed tiles | omcli curl -p /api/v0/installations |
| Show status of apply changes | omcli installation-logid 2, omcli installation-logid \$installation_id |
| json output | omcli -kformat=json staged-products |
| Reference | PKS CheatSheet, Bosh CheatSheet, Tile CheatSheet, UAA CheatSheet |

1.2 Tile Challenges

| Name | Comment |
|--|---|
| Tiles are big | It's usually GBs. Too big to distribute |
| In Opsmanager, can't cancel task | Costly to make mistakes |
| In Opsmanager, can't downgrade | Inconvenient for development cycle |
| In Opsmanager, review changes is confusing | The review feature should be more informative |
| Slow to apply changes | Usually it takes hours, while minutes in kubernetes |

1.3 om product

| Name | Summary |
|-----------------------------|---|
| Upload tile from cli | omcli upload-product -p |
| List products | omcli curl -s -p /api/v0/staged/products |
| List all available products | omcli available-products, or omcli curl -p /api/v0/available_products |
| List all deployed products | omcli deployed-products |
| Delete all unused products | omcli delete-unused-products |
| Delete product | omcli -k delete-product -p pivotal-container-service -v 1.3.0-build.3 |
| Unstage product | omcli -k unstage-product -p pivotal-container-service |
| Stage product | omcli -k stage-product -p pivotal-container-service -v 1.3.0-build.3 |

1.4 pivnet-cli

| Name | Comment |
|--------------------------|---|
| pivnet | CLI to interact with Pivotal Network. Install pivnet CLI |
| pivnet login | <pre>pivnet loginapi-token <your_token></your_token></pre> |
| pivnet download stemcell | pivnet download-product-files -p stemcells-ubuntu-xenial -r 170.9 -g '*vsphere*' -d |
| List all products | pivnet products |
| Show product info | pivnet product -p pivotal-container-service |

1.5 Get bosh/pks tile credential from om

| Name | Summary |
|---|--|
| bosh tile -> Bosh Commandline Credentials | omcli curl -p /api/v0/deployed/director/credentials/bosh2_commandl |
| Get ops-manager ca cert | omcli curl -p /api/v0/certificate_authorities |
| pks tile -> Uaa Admin Password | <pre>omcli curl -p /api/v0/deployed/products/\${bosh_deployment}/credent</pre> |
| pks tile -> Pks Uaa Management Admin Client | <pre>omcli curl -p /api/v0/deployed/products/\${bosh_deployment}/credent</pre> |
| pks tile - $>$ api server FQDN | <pre>omcli curl -p /api/v0/deployed/products/\${bosh_deployment}/credent</pre> |
| pks tile -> pks certificates | <pre>omcli curl -p /api/v0/deployed/products/\${bosh_deployment}/credent</pre> |
| pks tile -> whether wavefront is enabled | <pre>omcli curl -p /api/v0/deployed/products/\${bosh_deployment}/credent</pre> |
| pks tile -> wavefront token | <pre>omcli curl -p /api/v0/deployed/products/\${bosh_deployment}/credent</pre> |

1.6 Tile Reference

| Name | Command |
|----------------|---|
| kiln | A command line tool to help you maintain tile metadata. Download kiln |
| Example | example-product/metadata/example-product.yml.erb |
| nozzle | |
| firehose | |
| service broker | |
| buildpack | |
| Reference | Forms Reference, Product Template Reference, Property Reference, Tile Generator |

1.7 Ops manager

| Name | Command |
|---------------------|--|
| Release folder | /var/tempest/releases |
| Restart Ops Manager | service tempest-web stop/start |
| Grant file access | <pre>chown tempest-web:tempest-web /var/tempest/releases/<your-release.tgz></your-release.tgz></pre> |
| Tile entrance file | /var/tempest/workspaces/default/metadata/*.yml |
| Tile jobs folder | /var/vcap/jobs |

1.8 om cli Online Help

```
> om --help
om helps you interact with an Ops Manager
```

```
Usage: om [options] <command> [<args>]
```

| client-id, -c | string | Client ID for the Ops Manager VM (not required for unauthenticated comma |
|-------------------------|-------------------------|--|
| client-secret, -s | string | Client Secret for the Ops Manager VM (not required for unauthenticated c |
| connect-timeout, -o | int | timeout in seconds to make TCP connections (default: 5) |
| format, -f | string | Format to print as (options: table, json) (default: table) |
| help, -h | bool | prints this usage information (default: false) |
| password, -p | string | admin password for the Ops Manager VM (not required for unauthenticated |
| request-timeout, -r | int | timeout in seconds for HTTP requests to Ops Manager (default: 1800) |
| skip-ssl-validation, -k | bool | skip ssl certificate validation during http requests (default: false) |
| target, -t | string | location of the Ops Manager VM |
| trace, -tr | bool | prints HTTP requests and response payloads |
| username, -u | string | admin username for the Ops Manager VM (not required for unauthenticated |
| version, -v | bool | prints the om release version (default: false) |
| | | |

Commands:

| activate-certificate-authority | activates a certificate authority on the Ops Manager |
|--------------------------------|--|
| apply-changes | triggers an install on the Ops Manager targeted |
| available-products | list available products |
| certificate-authorities | lists certificates managed by Ops Manager |
| certificate-authority | prints requested certificate authority |
| config-template | **EXPERIMENTAL** generates a config template for the product |
| configure-authentication | configures Ops Manager with an internal userstore and admin user account |

Updated: January 23, 2019

DEPRECATED configures Ops Manager deployed bosh director configure-bosh configure-director configures the director configure-product configures a staged product configure-saml-authentication configures Ops Manager with SAML authentication create-certificate-authority creates a certificate authority on the Ops Manager creates a VM extension create-vm-extension credential-references list credential references for a deployed product credentials fetch credentials for a deployed product issues an authenticated API request curl delete-certificate-authority deletes a certificate authority on the Ops Manager delete-installation deletes all the products on the Ops Manager targeted delete-product deletes a product from the Ops Manager deletes unused products on the Ops Manager targeted delete-unused-products deployed-manifest prints the deployed manifest for a product lists deployed products deployed-products list errands for a product errands export-installation exports the installation of the target Ops Manager generates a new certificate signed by Ops Manager's root CA generate-certificate generate-certificate-authority generates a certificate authority on the Opsman prints this usage information import-installation imports a given installation to the Ops Manager targeted installation-log output installation logs list recent installation events installations pending-changes lists pending changes regenerate-certificates deletes all non-configurable certificates in Ops Manager... reverts staged changes on the Ops Manager targeted revert-staged-changes set-errand-state sets state for a product's errand stages a given product in the Ops Manager targeted stage-product staged-config **EXPERIMENTAL** generates a config from a staged product staged-manifest prints the staged manifest for a product staged-products lists staged products unstages a given product from the Ops Manager targeted unstage-product upload-product uploads a given product to the Ops Manager targeted uploads a given stemcell to the Ops Manager targeted upload-stemcell version prints the om release version pivnet cli Online Help > pivnet --help Usage: pivnet [OPTIONS] <command> Application Options: -v, --version Print the version of this CLI and exit --format=[table|json|yaml] Format to print as (default: table) --verbose Display verbose output --profile= Name of profile (default: default) --config= Path to config file (default: /Users/zdenny/.pivnetrc) Help Options: Show this help message -h, --help Available commands: Accept EULA (Available for pivots only) (aliases: ae) accept-eula Add file group to release (aliases: afg) add-file-group Add product file to release (aliases: apf) add-product-file Add release dependency (aliases: ard) add-release-dependency

Add release upgrade path (aliases: arup)

Add user group to release (aliases: aug)

add-release-upgrade-path

add-user-group

Updated: January 23, 2019

```
add-user-group-member
                             Add user group member to group (aliases: augm)
                             Create dependency specifier (aliases: cds)
create-dependency-specifier
create-file-group
                             Create file group (aliases: cfg)
                             Create product file (aliases: cpf)
create-product-file
                             Create release (aliases: cr)
create-release
                             Create user group (aliases: cug)
create-user-group
curl
                             Curl an endpoint (aliases: c)
delete-dependency-specifier
                             Delete dependency specifier (aliases: dds)
delete-file-group
                             Delete file group (aliases: dfg)
delete-product-file
                             Delete product file (aliases: dpf)
delete-release
                             Delete release (aliases: dr)
delete-user-group
                             Delete user group (aliases: dug)
                             Get dependency specifier (aliases: ds)
dependency-specifier
dependency-specifiers
                             List dependency specifiers (aliases: dss)
                             Download product files (aliases: dlpf)
download-product-files
                             Show EULA (aliases: e)
eulas
                             List EULAs (aliases: es)
                             Show file group (aliases: fg)
file-group
file-groups
                             List file groups (aliases: fgs)
                             Print this help message (aliases: h)
help
login
                             Log in to Pivotal Network. (aliases: 1)
logout
                             Log out from Pivotal Network.
                             Show product (aliases: p)
product
product-file
                             Show product file (aliases: pf)
                             List product files (aliases: pfs)
product-files
                             List products (aliases: ps)
products
release
                             Show release (aliases: r)
                             List release dependencies (aliases: rds)
release-dependencies
release-types
                             List release types (aliases: rts)
release-upgrade-paths
                             List release upgrade paths (aliases: rups)
releases
                             List releases (aliases: rs)
remove-file-group
                             Remove file group from release (aliases: rfg)
remove-product-file
                             Remove product file from release (aliases: rpf)
remove-release-dependency
                             Remove release dependency (aliases: rrd)
remove-release-upgrade-path
                             Remove release upgrade path (aliases: rrup)
                             Remove user group from release (aliases: rug)
remove-user-group
                             Remove user group member from group (aliases: rugm)
remove-user-group-member
                             Update file group (aliases: ufg)
update-file-group
update-product-file
                             Update product file (aliases: upf)
                             Update release (aliases: ur)
update-release
update-user-group
                             Update user group (aliases: uug)
                             Show user group (aliases: ug)
user-group
user-groups
                             List user groups (aliases: ugs)
```

1.10 More Resources

version

License: Code is licensed under MIT License.

Print the version of this CLI and exit (aliases: v)

Updated: January 23, 2019