

INSTALLATION

To install PolSARpro v6.0 (Biomass Edition) Software, user has to :

1) Unpack the zip file:


PolSARpro_v6.X_Biomass_Edition_Linux_Installer_YYYYMMDD.zip into the *Download* Directory.

2) Open an **Xterm** window and type:

[user]:> cd Download / PolSARpro_v6.X_Biomass_Edition_Linux_Installer_YYYYMMDD [user]:> wish PolSARpro_v6.X_Biomass_Edition_Linux_Installer.tcl

(where v6.X = version and YYYYMMDD = date)

3) Follow the *Automatic Installation procedure for Linux*. User will be ask to enter the destination directory where **PolSARpro v6.0** (**Biomass Edition**) **Software** directory will be installed.



DIRECTORY STRUCTURE

Once installed, the **PolSARpro v6.0** (**Biomass Edition**) **Software** directory presents the following structure:

- ColorMap directory contains user defined or modified PolSARpro colour-map files
- Config directory: contains all the different software configuration files
- **GUI directory** contains all the widget window Tcl-Tk files.
- **Help directory** contains the PolSARpro Help files.
- License directory contains all the PolSARpro licenses files
- Log directory will contain all the log files created for each session.
- **Soft directory** contains ready to use executable processing files and libraries.
- **TechDoc directory** contains the technical documentations relative to all the GUI Widgets and C-Routines used in PolSARpro.
- **Tmp directory** is empty after installation and is used by PolSARpro during each session.
- Tutorial directory contains PolSARpro Tutorial material in PDF format.

It is strictly recommended not to change, extract, move or modify any component (tcl-tk widgets, executable processing files, colormaps, help files, PDF files...) included in the PolSARpro v6.0 (Biomass Edition) Software directory and / or change its structure.

RUNNING POLSARPRO V6.0 (BIOMASS EDITION) SOFTWARE

To run the **PolSARpro v6.0** (**Biomass Edition**) **Software**, start the GUI (Graphical User Interface) by double-clicking the **PolSARpro_v6.X_Biomass_Edition** icon located on the user desktop, or open an **Xterm** window in the directory where **PolSARpro v6.0** (**Biomass Edition**) **Software** directory is installed and type:

[user]:> wish PolSARpro_v6.X_Biomass_Edition.tcl

(where v6.X = version)