
Взял за основу 5 практическую и сделал сеть для директоров.



Настроил vlan и интерфейсы

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config) #vlan 4
Switch(config-vlan) #name direct
Switch(config-vlan) #int range fa0/5-6
Switch(config-if-range) #switchport mode access
Switch(config-if-range) #switchport access 4
% Invalid input detected at '^' marker.

Switch(config-if-range) #switchport access vlan 4
Switch(config-if-range) #exit
Switch(config) #
```

| VLAN | Name | | | | | tus | Ports | | | |
|------|--------------------|----------|------|--------|--------|--------|-------------------------------|---|-------------------------------|----------------------------|
| 1 | default | | | | | | Fa0/11, Fa0/15, Fa0/19, | Fa0/8, Fa0/12, 1 Fa0/16, 1 Fa0/20, 1 Fa0/24, 0 | Fa0/13, Fa0/17, Fa0/21, | Fa0/14 Fa0/18 Fa0/22 |
| 2 | programmer | | | | act: | ive | Fa0/1, | Fa0/2 | | |
| 3 | buhg | | | | | ive | Fa0/3, | Fa0/4 | | |
| 4 | direct | | | | | ive | Fa0/5, | Fa0/6 | | |
| 1002 | fddi-default | | | | | active | | | | |
| 1003 | token-ring-default | | | | | active | | | | |
| 1004 | fddinet-default | | | | | active | | | | |
| 1005 | trnet- | -default | | | act: | ive | | | | |
| VLAN | Type | SAID | MTU | Parent | RingNo | Bridge | No Stp | BrdgMode | Transl | Trans2 |
| 1 | enet | 100001 | 1500 | - | - | _ | _ | - | 0 | 0 |
| 2 | enet | 100002 | 1500 | _ | _ | _ | _ | _ | 0 | 0 |
| 3 | enet | 100003 | 1500 | _ | _ | _ | _ | _ | 0 | 0 |
| 4 | enet | 100004 | 1500 | - | _ | _ | _ | _ | 0 | 0 |
| Mo | ore | | | | | | | | | |