

Router0

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #interface fa0/0
Router(config-if) #ip address 10.3.0.1 255.255.255.0
Router(config-if) #no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if) #exit
Router(config) #ip dhcp excluded-address 10.3.0.1
Router(config) #ip dhcp pool Telephony
Router(dhcp-config) #network 10.3.0.0 255.255.255.0
Router(dhcp-config) #default-router 10.3.0.1
Router(dhcp-config) #option 150 ip 10.3.0.1
Router (dhcp-config) #exit
Router(config) #telephony-service
Router(config-telephony) #max-ephones 10
Router (config-telephony) #max-dn 10
Router(config-telephony) #ip source-address 10.3.0.1 port 2000
Router(config-telephony) #auto assign 1 to 10
Router (config-telephony) #exit
Router(config) #ephone-dn 1
Router(config-ephone-dn) #%LINK-3-UPDOWN: Interface ephone dsp DN 1.1, changed state to up
number 101
Router(config-ephone-dn) #number 101
Router (config-ephone-dn) #exit
Router (config) #ephone-dn 2
Router(config-ephone-dn) #%LINK-3-UPDOWN: Interface ephone_dsp DN 2.1, changed state to up
Router(config-ephone-dn)#number 102
Router(config-ephone-dn) #exit
Router(config) #ephone-dn 1
Router (config-ephone-dn) #exit
Router(config) #ephone-dn 3
Router(config-ephone-dn) #%LINK-3-UPDOWN: Interface ephone_dsp DN 3.1, changed state to up
Router(config-ephone-dn) #number 103
Router(config-ephone-dn) #number 103
Router (config-ephone-dn) #exit
Router(config) #ephone-dn 104
dn 104 exceeds max-dn 10
Router(config) #ephone-dn 4
Router(config-ephone-dn) #%LINK-3-UPDOWN: Interface ephone_dsp DN 4.1, changed state to up
Router(config-ephone-dn) #number 104
Router(config-ephone-dn) #exit
Router(config) #ephone-dn 5
Router(config-ephone-dn) #%LINK-3-UPDOWN: Interface ephone_dsp DN 5.1, changed state to up
Router(config-ephone-dn) #number 105
Router(config-ephone-dn) #exit
Router(config) #ephone-dn 6
Router(config-ephone-dn) #%LINK-3-UPDOWN: Interface ephone dsp DN 6.1, changed state to up
Router(config-ephone-dn) #number 106
Router(config-ephone-dn)#exit
Router (config) #
```

```
Router (config) #ephone 1
Router(config-ephone) #mac-address 0009.7C34.3C01
Router(config-ephone) #type ata
Router(config-ephone) #button 1:1
Router (config-ephone) #exit
Router(config) #ephone 2
Router(config-ephone) #mac-address 000C.CF09.D862
Router(config-ephone) #type 7960
Router(config-ephone) #button 1:2
Router(config-ephone) #exit
Router(config) #ephone 3
Router(config-ephone) #mac-address 0006.2A28.7710
Router(config-ephone) #type CIPC
Router(config-ephone) #button 1:3
Router (config-ephone) #exit
Router(config)#
```

