## STM32CUBEIDE-WIN 설치에러 / 해결방법

부제 : 윈도우가 조금 싫어졌다

## 다운로드


IDE - stm32cubeide

https://www.st.com/en/development-tools/stm32cubeide.html#get-software ide 내부 패키지 설치에서 로그인을 요구 - 이 시점에 계정을 생성할것

통신 - teraterm

https://cafe.naver.com/androiddag

별다른 문제가 발생하지 않음




실행파일 경로에 한글이 있을경우 발생

아래의 방법으로는 해결되지 않음

- 파일명을 단순하게 변경
- 관리자 권한으로 실행
- Windows PowerShell로 설치
- 클린부팅 실시 후 설치
- 설치 프로그램 재 다운로드

참고

https://m.blog.naver.com/toruin84/223268162893



사용자명에 공백/한글/특수문자 포함시 발생 윈도우에서 새로운 사용자를 생성하고, 로그인하여 설치

아래의 방법으로는 해결되지 않음

- 시작 프로그램 비활성
- 관리자 권한으로 실행
- WINDOWS POWERSHEII로 설치
- 클린부팅 실시 후 설치
- 설치 프로그램 재 다운로드
- %TEMP% 접근권한 허용

## 참고

https://community.st.com/t5/stm32cubeidemcus/stm32cubeide-install-error/m-p/196459#M9190

## 그 외 유의미한 텍스트

Debug port

```
CH.02 개발 환경 구축 : p.36 ~ p.74
MCU = 마이크로 컨트롤러 유닛
NUCLEO F103RB
      우리 보드
      STM32F103 계열임 <= 자료가 많음
스팩
      STM32 micro controller(STM32F103RBT6) with LQFP64 package
      2 types Of extension resources
      Arduino Uno Revision 3 connectivity
      STMicro electronics Morpho extension pin headers for full access tO all STM32 1/OS
      On-board ST-LINK/V2-1 debugger/programmer with SWD connector
      selection-mode switch to use the kit as a standalone ST-LINK/V2-I
      Flexible board power supply
      USB VBUS external source (3.3V, 5V, 7~12VI
      Power management access point
      3 LEDS
      USB communication(LD1), user LED(LD2), power LED(LD3)
      2 push buttons: USER and RESET
      USB re-enumeration capability: 3 different interfaces supported 0/7 USB
       Virtual Comport
      Mass storage
```