

Cel:

Serwer:

nazwa serwera: superserwer

dwie karty sieciowe nazywane jako: public(VB NAT) i local (VB sieć wewnętrzna)
adresacja lokalna: 10.100.10.0/24, serwer: .100

Wypromować serwer do roli AD : domena: test.local
dodać użytkownika: Rysio Pysio (rpysio)

Win10

adresacja lokalna: 10.100.10.0/24, adres IP: .200

Dodać komputer do Domeny
zalogować się na użytkownika Rysio Pysio

Rozwiązanie:

superserwer:

Device specifications

Device name superserwer



public
Network
Intel(R) PRO/1000 MT Desktop Ad...



local
Identifying...
Intel(R) PRO/1000 MT Desktop Ad...

Internet Protocol Version 4 (TCP/IPv4) Properties



General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address: 10 . 100 . 10 . 100

Subnet mask: 255 . 255 . 255 . 0

Default gateway: . . .

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server: . . .

Alternate DNS server: . . .

☐ Validate settings upon exit

Advanced...

OK

Cancel

Add Roles and Features Wizard



Select server roles

DESTINATION SERVER
superserver

Before You Begin

Installation Type

Server Selection

Server Roles

Features

AD DS

Confirmation

Results

Select one or more roles to install on the selected server.

Roles

- ☐ Active Directory Certificate Services
- ☒ **Active Directory Domain Services**
- ☐ Active Directory Federation Services
- ☐ Active Directory Lightweight Directory Services
- ☐ Active Directory Rights Management Services
- ☐ Device Health Attestation
- ☐ DHCP Server
- ☐ DNS Server
- ☐ Fax Server
- ☒ File and Storage Services (1 of 12 installed)
- ☐ Host Guardian Service
- ☐ Hyper-V
- ☐ Network Policy and Access Services
- ☐ Print and Document Services
- ☐ Remote Access
- ☐ Remote Desktop Services
- ☐ Volume Activation Services
- ☐ Web Server (IIS)
- ☐ Windows Deployment Services
- ☐ Windows Server Update Services

Description

Active Directory Domain Services (AD DS) stores information about objects on the network and makes this information available to users and network administrators. AD DS uses domain controllers to give network users access to permitted resources anywhere on the network through a single logon process.

< Previous

Next >

Install

Cancel

Deployment Configuration

TARGET SERVER
superserwer

Deployment Configuration

Domain Controller Options

Additional Options

Paths

Review Options

Prerequisites Check

Installation

Results

Select the deployment operation

- ☐ Add a domain controller to an existing domain
- ☐ Add a new domain to an existing forest
- ☒ Add a new forest

Specify the domain information for this operation

Root domain name:

test.local

[More about deployment configurations](#)

< Previous

Next >


Install

Cancel

You're about to be signed out

The computer is being restarted because Active Directory Domain Services was installed or removed.

Close



New Object - User



 Create in: test.local/Users

First name: Initials:

Last name:

Full name:

User logon name:

User logon name (pre-Windows 2000):

Win10:

Internet Protocol Version 4 (TCP/IPv4) Properties ✕

General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address:

Subnet mask:

Default gateway:

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server:

Alternate DNS server:

☐ Validate settings upon exit Advanced...

OK Cancel

Join a domain

Join a domain

Domain name

✕

Next Cancel

Join a domain

Join a domain

Enter your domain account info to verify you have permission to connect to the domain.



rpysio

.....



Domain: test.local

OK

Cancel

Add an account

Add an account

Enter the account info for the person who'll be using this PC. If you skip this step, the person will have default permissions for the domain.

User account

rpysio


Account type


Standard User



Next

Skip





smiga!