Settings SOP

Owner: Jericho Freight	**Effective Date: 08/25/26**
Version: 1.0	**Department: Brokerage**

General Information

Description / Objective	Teach any teammate how to use the home-page settings cog, why each tool exists, and how those tools change every quote without touching the math of a single mode.
Assignee	Santiago Rendon

Glossary

1. Where settings live
2. Change User
3. Customers
4. Terminal Locations
5. SOP's library
6. How settings show up on quotes
7. Maps key in kid words
8. Quote file names across modes
9. Load Previous Quote by mode
10. CRM in the background
11. What never to put in GitHub
12. Common mistakes
13. Definitions

1. Where settings live

1.1 The cog

On the home screen, top right of the logo bar, there is a gear. That is Settings. Click it. A short menu appears: Change User, Customers, Terminal Locations, SOP's.

There is no Modes menu in that cog. Modes are the big buttons: FTL, LTL, Dray, International.

If you have never saved a representative, the app takes you to Change User before you can quote. That is on purpose. Every PDF needs a human name.

2. Change User

2.1 Your name on the letter

This screen stores Representative name and Representative email on this computer only (a small file named like rep.json in the app data folder).

Those two fields print on every quote: LTL, FTL, Dray, International. The customer calls that person, not a generic inbox, unless you typed a generic email on purpose.

Click Save. You return home. Click Cancel only if a name is already saved.

Switching users on a shared desktop: type the new name and email and Save. The old name is overwritten. There is no password. Do not leave a teammate's email on the box if you are quoting as yourself.

3. Customers

3.1 The local phone book

Customers is a list on this computer, not the whole company CRM. Search by name or email. Pick a row to fill the boxes. Add customer saves a new row. If that name already exists, the button becomes Update.

On each quote form, Include customer on quote searches this same list. Generating with the box on can add or update the name here.

Use real spelling. 'Acme' and 'ACME LLC' are two rows if you type them differently. The quote prints whatever you typed.

Deleting or editing here does not change PDFs you already saved. It only changes the next pick.

4. Terminal Locations

4.1 The yard list for dray

Dray quotes need a real terminal name. This screen is where you add yards: name, address, city, state, ZIP.

Search the list to edit an existing yard. For a brand new yard, type in Terminal Name. Google can suggest a place. Address is not the Google search box. Name is.

Save puts the yard into the local list (and can sit beside a shared terminals file). Dray origin search uses this list. If the yard is missing, you will fight the required origin terminal field all day.

Do not invent a ZIP. Chassis and miles tools need a real postal code.

5. SOP's library

5.1 These PDFs

SOP's opens a page that lists the six how-to files, including this one. Open or download a PDF. They live in the app's sops folder so they can ship on GitHub and inside the Windows install.

If a file is missing, rebuild them with python scripts/build_sops.py after reportlab is installed. Do not replace them with Word drafts that skip the math sections.

6. How settings show up on quotes

6.1 The chain

Change User -> letterhead contact.

Customers -> optional customer name/email on the PDF when the checkbox is on.

Terminal Locations -> dray origin and return search.

SOP's -> training. They do not change prices.

None of these screens change linehaul math. If a total is wrong, fix the quote form, not Settings.

7. Maps key in kid words

7.1 How the app knows miles

Calculate Distance asks Google 'how far does a truck drive?' Google only answers if this computer has a Maps key in config.json. That file is local. It is not committed to GitHub.

If the key is missing, distance buttons explain that. You can still type miles by hand in modes that allow it, or quote dray on dollars only.

Generate does not call Google again. It uses miles already stored. That keeps quoting fast.

8. Quote file names across modes

8.1 The Q rule

Every quote gets a number from one shared counter. The print name adds letters so you know the mode.

FTL-Q4242, LTL-Q4242 (single or tiered), DRAY-Q4242, INTL-Q4242. Click Print Quote. Chrome Save as PDF should offer that name. If you save as 'quote.pdf' you will lose it on the desktop.

9. Load Previous Quote by mode

9.1 Separate cookie jars

FTL, LTL single, LTL tiered, and Dray each remember their own last quotes on this computer. International does not. A picker never mixes modes, so you cannot spill chassis days into an FTL van quote.

These history files are local. They are not for GitHub.

10. CRM in the background

10.1 Twenty

If a CRM key is saved, the app tries to tell Twenty about the quote after Generate. If Twenty is not running, the quote still prints. You may see a short line that CRM is not running. That is not a failed quote.

Do not wait on CRM to send the PDF to the customer.

11. What never to put in GitHub

11.1 Secrets stay local

Do not commit config.json, API keys, customer dumps, terminal dumps, quote history JSON, or quote_counter.json. The sops PDFs are allowed. They have no secrets.

12. Common mistakes

12.1 Watch-outs

Quoting under someone else's saved name.

Adding a terminal with a fake ZIP.

Looking for SOPs under Modes. They are under the cog.

Thinking Customers is the company CRM of record.

Definitions	
Settings cog	The gear on the home screen. Change User, Customers, Terminal Locations, SOP's.
Representative	The person whose name and email print on quotes.
Local catalog	A list saved on this computer, not the whole company database.
config.json	Local settings file for Maps and CRM. Not for GitHub.
Q prefix	FTL-Q, LTL-Q, DRAY-Q, INTL-Q printed file names.

Reviewed By:	**Date:**
Approved By:	**Date:**
Last Updated By:	**Date / Time:**