Training Checklist: **Clinitek Status UA**

INSTRUCTIONS: The Trainee will initial next to each Training Task Description upon reviewing the contents of all checklist items. The Trainer will initial next to each Training Task Description upon training the Trainee. Upon successful completion of this training checklist, the Trainee and Trainer will sign and date the checklist at the end.

Training Task Description	Trainee Initials	Trainer Initials
External Quality Control (QC) a) External QC is tested during training and whenever a new bottle of reagent strips are first opened. b) The following data must be recorded when QC is run. QC for test type, QC level, QC lot number, QC expiration date, QC results, test date, and testing personnel initials.		
Maintenance a) Know to complete daily and weekly preventive maintenance procedures. **DAILY** Decontaminate display and analyzer surfaces **WEEKLY** Clean test table and table insert Clean the white calibration bar		
Strip Handling a) Strips are stored at room temperature away from sunlight, light exposure, heat, and ambient moisture. b) The strip canister cap should always be tightly closed and never be opened for periods of time exceeding the time required to remove strip(s) from the canister. c) Strips should be removed from the canister only for immediate use. d) Do not transfer unused reagent strips to other containers. e) Do not touch the reagent areas of the strip. f) Do not remove desiccants from the bottle. g) Do not use reagent strips beyond the expiration date.		
Sample Handling a) Positively identify the patient and label the urine sample. b) The urine sample should be tested within 2 hours of sample collection. c) If testing is delayed >2 hours, urine specimens may be stored in the refrigerator prior to testing. The sample must come to room temperature prior to testing. d) Any cultures ordered on the same urine specimen should be set up first before performing urinalysis. e) Unacceptable urine specimens include urine specimens with preservatives.		
Test Procedure a) Remove a strip from the canister. b) Mix the urine sample well. c) Completely immerse the reagent areas of the strip in the urine and immediately remove the strip while running the edge of the strip against the rim of the urine container. d) Hold strip horizontally against an absorbent material (e.g. paper towel) to soak up the excess urine. e) Insert the urine-saturated strip onto the analyzer.		

Training Checklist: **Clinitek Status UA**

f) Observe the urine sample appearance for color and clarity. Enter observations on instrument prompt.		
Results Interpretation a) The analyzer will read the strip. b) Alternatively, results may be obtained by comparing reagent areas to the corresponding color blocks on the canister label.		
Support a) Know to call Siemens Healthcare Technical Support when requiring technical assistance, troubleshooting, and error reports – 1 877 229 3711.		
Trainee to run <u>one</u> level of Urinalysis QC and attach results to the Urinalysis QC Log below.		

SIEMENS Healthineers

<u>Clinitek QC-SPECIFIC INFO</u>

Strip Lot#/Exp: _____ / _____

Low ctrl Lot#/Exp: _____ / _____

High ctrl Lot#/Exp: _____ / _____

<u>General Info</u>

QC Test Date: _____

Testing Personnel Initials: _____

POSITIVE (+) QC results	**NEGATIVE (-)** QC results
(Attach Results Here)	(Attach Results Here)

Trainee signature:		Date:	
Trainer signature:		Date:	